



GlassFish Server Open Source Edition 3.1 Administration Guide

Oracle Corporation
500 Oracle Parkway
Redwood City, CA 94065
U.S.A.

Part No: 821-2445-12
July 2011

Copyright © 2010, 2011, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Preface	25
1 Overview of GlassFish Server Administration	33
Default Settings and Locations	33
Configuration Tasks	34
Initial Configuration Tasks	35
How Dotted Names Work for Configuration	37
Configuration Files	38
Impact of Configuration Changes	38
Administration Tools	42
Administration Console	42
asadmin Utility	43
REST Interfaces	43
Update Tool	44
OSGi Module Management Subsystem	44
keytool Utility	49
Java Monitoring and Management Console (JConsole)	49
Instructions for Administering GlassFish Server	49
Part I Runtime Administration	51
2 General Administration	53
Using the asadmin Utility	53
Path to the asadmin Utility	54
asadmin Utility Syntax	54
▼ To Run an asadmin Utility Subcommand in Single Mode	55
▼ To Display Help Information for the asadmin Utility or a Subcommand	56

▼ To Start a Multimode Session	57
▼ To End a Multimode Session	58
▼ To Run a Set of asadmin Subcommands From a File	59
Administering System Properties	60
▼ To Create System Properties	60
▼ To List System Properties	61
▼ To Delete a System Property	61
Administering Resources	62
▼ To Add Resources From an XML File	62
Listing Various System Elements	63
▼ To Display the GlassFish Server Version	63
▼ To List Applications	63
▼ To List Containers	64
▼ To List Modules	65
▼ To List Subcommands	66
▼ To List Timers	66
▼ To Show Component Status	67
Using REST Interfaces to Administer GlassFish Server	67
Using REST URLs to Administer GlassFish Server	68
Using REST Resource Methods to Administer GlassFish Server	71
Resources for asadmin Subcommands That Perform Non-CRUD Operations	80
Securing GlassFish Server REST Interfaces	81
Formats for Resource Representation of Configuration Objects	82
Formats for Resource Representation of Monitoring Objects	92
Formats for Resource Representation of Log File Details	100
Supported Content Types in Requests to REST Resources	104
3 Administering Domains	105
About Administering Domains	105
GlassFish Server Instances	105
Domains for Administering GlassFish Server	106
Domain Administration Server (DAS)	107
Creating, Logging In To, and Deleting a Domain	107
▼ To Create a Domain	107
▼ To Create a Domain From a Custom Template	108

▼ To List Domains	112
▼ To Log In to a Domain	112
▼ To Delete a Domain	114
Starting and Stopping a Domain	115
▼ To Start a Domain	115
▼ To Stop a Domain	116
▼ To Restart a Domain	116
Configuring a DAS or a GlassFish Server Instance for Automatic Restart	117
▼ To Configure a DAS or an Instance for Automatic Restart on Windows	118
▼ To Configure a DAS or an Instance for Automatic Restart on Linux	119
▼ To Configure a DAS or an Instance for Automatic Restart on Oracle Solaris	120
▼ To Prevent Service Shutdown When a User Logs Out on Windows	122
Backing Up and Restoring a Domain	122
▼ To Back Up a Domain	122
▼ To Restore a Domain	123
▼ To List Domain Backups	124
Re-Creating the Domain Administration Server (DAS)	125
▼ To Migrate the DAS	125
Additional Domain Tasks	127
▼ To Display Domain Uptime	127
▼ To Switch a Domain to Another Supported Java Version	127
▼ To Change the Administration Port of a Domain	128
4 Administering the Virtual Machine for the Java Platform	131
Administering JVM Options	131
▼ To Create JVM Options	132
▼ To List JVM Options	132
▼ To Delete JVM Options	133
▼ To Generate a JVM Report	134
Administering the Profiler	135
▼ To Create a Profiler	135
▼ To Delete a Profiler	136
5 Administering Thread Pools	137
About Thread Pools	137

Configuring Thread Pools	138
▼ To Create a Thread Pool	138
▼ To List Thread Pools	139
▼ To Update a Thread Pool	139
▼ To Delete a Thread Pool	140
6 Administering Web Applications	141
Invoking a Servlet by Alternate Means	141
Changing Log Output for a Servlet	142
Defining Global Features for Web Applications	142
▼ To Use the default web.xml File	143
Redirecting a URL	143
Administering mod_jk	144
▼ To Enable mod_jk	144
▼ To Load Balance Using mod_jk and GlassFish Server	146
▼ To Enable SSL Between the mod_jk Load Balancer and the Browser	148
▼ To Enable SSL Between the mod_jk Load Balancer and GlassFish Server	149
7 Administering the Logging Service	151
About Logging	151
Log Files	152
Logger Namespaces	154
Logging Targets	155
Logging Properties	155
Configuring the Logging Service	156
Changing the Name and Location of Logging Service Files	156
Setting Log Levels	159
Setting Log File Rotation	162
Adding a Custom Logging Handler	166
Viewing Log Records	167
▼ To Collect Log Files into a ZIP Archive	167
8 Administering the Monitoring Service	169
About Monitoring	169

How the Monitoring Tree Structure Works	170
About Monitoring for Add-on Components	175
Tools for Monitoring GlassFish Server	176
Configuring Monitoring	176
▼ To Enable Monitoring	176
▼ To Disable Monitoring	177
Viewing Common Monitoring Data	179
▼ To View Common Monitoring Data	179
Common Monitoring Statistics	180
Viewing Comprehensive Monitoring Data	181
Guidelines for Using the <code>list</code> and <code>get</code> Subcommands for Monitoring	181
▼ To View Comprehensive Monitoring Data	182
Comprehensive Monitoring Statistics	184
Configuring JConsole to View GlassFish Server Monitoring Data	208
▼ To Connect JConsole to GlassFish Server	208
9 Administering Life Cycle Modules	211
About Life Cycle Modules	211
Configuring Life Cycle Modules	212
▼ To Create a Life Cycle Module	212
▼ To List Life Cycle Modules	213
▼ To Update a Life Cycle Module	213
▼ To Delete a Life Cycle Module	214
10 Extending and Updating GlassFish Server	215
About Add-On Components	215
Preconfigured Repositories for GlassFish Server	216
Oracle GlassFish Server Repositories	216
GlassFish Server Open Source Edition Repositories	219
Tools for Extending and Updating GlassFish Server	219
Update Tool	220
The <code>pkg</code> Command	220
Administration Console	220
Adding Components	221
▼ To Install an Add-on Component	221

Updating Installed Components	224
▼ To Update an Installed Component	224
▼ To Update All Installed Components in an Image	226
Removing Installed Components	227
▼ To Uninstall an Installed Component	227
▼ To Uninstall and Revert to an Older Version of a Component	229
Upgrading to Oracle GlassFish Server From GlassFish Server Open Source Edition	230
▼ To Upgrade to GlassFish Server Open Source Edition by Using Update Tool	231
▼ To Upgrade to GlassFish Server Open Source Edition by Using the pkg Command	232
Extending and Updating GlassFish Server Inside a Closed Network	234
▼ To Install the Pre-Installed Toolkit Image Inside a Closed Network	235
▼ To Configure a Local Repository Server Inside a Closed Network	236
▼ To Configure a GlassFish Server Installation to Use a Local Repository Server Inside a Closed Network	239
▼ To Install Updates From a Local Repository	240
 Part II Resources and Services Administration	 243
 11 Administering Database Connectivity	 245
About Database Connectivity	245
Setting Up the Database	246
▼ To Install the Database and Database Driver	247
▼ To Start the Database	247
▼ To Stop the Database	248
Java DB Utility Scripts	248
Configuring Access to the Database	249
Administering JDBC Connection Pools	250
Administering JDBC Resources	258
Enabling the jdbc/ __default Resource in a Clustered Environment	261
Integrating the JDBC Driver	262
Configuration Specifics for JDBC Drivers	263
IBM DB2 Database Type 2 Driver	263
IBM DB2 Database Type 4 Driver	264
Java DB/Derby Type 4 Driver	264
MySQL Server Database Type 4 Driver	265

Oracle 10 Database Driver	265
Oracle 11 Database Driver	266
PostgreSQL Type 4 Driver	267
DataDirect Type 4 Driver for IBM DB2 Database	267
DataDirect Type 4 Driver for IBM Informix	268
DataDirect Type 4 Driver for Microsoft SQL Server Database	268
DataDirect Type 4 Driver for MySQL Server Database	269
DataDirect Type 4 Driver for Oracle 11 Database	269
DataDirect Type 4 Driver for Sybase Database	270
Inet Oraxo Driver for Oracle Database	270
Inet Merlia Driver for Microsoft SQL Server Database	271
Inet Sybelux Driver for Sybase Database	271
JConnect Type 4 Driver for Sybase ASE 12.5 Database	272
 12 Administering EIS Connectivity	273
About EIS Connectivity	274
Administering Connector Connection Pools	275
▼ To Create a Connector Connection Pool	275
▼ To List Connector Connection Pools	276
▼ To Connect to (Ping) or Reset (Flush) a Connector Connection Pool	277
▼ To Update a Connector Connection Pool	277
▼ To Delete a Connector Connection Pool	278
Administering Connector Resources	278
▼ To Create a Connector Resource	278
▼ To List Connector Resources	279
▼ To Update a Connector Resource	280
▼ To Delete a Connector Resource	280
Administering the Resource Adapter Configuration	281
▼ To Create Configuration Information for a Resource Adapter	281
▼ To List Resource Adapter Configurations	282
▼ To Update a Resource Adapter Configuration	282
▼ To Delete a Resource Adapter Configuration	283
Administering Connector Security Maps	283
▼ To Create a Connector Security Map	284
▼ To List Connector Security Maps	284

▼ To Update a Connector Security Map	285
▼ To Delete a Connector Security Map	286
Administering Connector Work Security Maps	286
▼ To Create a Connector Work Security Map	287
▼ To List Connector Work Security Maps	288
▼ To Update a Connector Work Security Map	288
▼ To Delete a Connector Work Security Map	289
Administering Administered Objects	289
▼ To Create an Administered Object	290
▼ To List Administered Objects	290
▼ To Update an Administered Object	291
▼ To Delete an Administered Object	291
13 Administering Internet Connectivity	293
About Internet Connectivity	293
About HTTP Network Listeners	293
About Virtual Servers	294
Administering HTTP Network Listeners	295
▼ To Create an Internet Connection	296
Administering HTTP Protocols	296
Administering HTTP Configurations	298
Administering HTTP Transports	299
Administering HTTP Network Listeners	301
Administering Virtual Servers	305
▼ To Create a Virtual Server	306
▼ To List Virtual Servers	307
▼ To Update a Virtual Server	307
▼ To Delete a Virtual Server	307
To Assign a Default Web Module to a Virtual Server	308
▼ To Assign a Virtual Server to an Application or Module	308
▼ To Set JSESSIONIDSSO Cookie Attributes	309
14 Administering the Object Request Broker (ORB)	311
About the ORB	311
Configuring the ORB	312

Administering IIOP Listeners	312
▼ To Create an IIOP Listener	312
▼ To List IIOP Listeners	313
▼ To Update an IIOP Listener	313
▼ To Delete an IIOP Listener	314
15 Administering the JavaMail Service	315
About JavaMail	315
Administering JavaMail Resources	316
▼ To Create a JavaMail Resource	316
▼ To List JavaMail Resources	317
▼ To Update a JavaMail Resource	317
▼ To Delete a JavaMail Resource	318
16 Administering the Java Message Service (JMS)	319
About the JMS Service	320
JMS Service High Availability	321
Updating the JMS Service Configuration	321
Setting Message Queue Broker Properties in the JMS Service Configuration	323
Administering JMS Hosts	323
About JMS Host Types	323
Configuring Embedded and Local JMS Hosts	324
▼ To Create a JMS Host	325
▼ To List JMS Hosts	326
▼ To Update a JMS Host	327
▼ To Delete a JMS Host	328
Administering JMS Connection Factories and Destinations	328
▼ To Create a Connection Factory or Destination Resource	329
▼ To List JMS Resources	331
▼ To Delete a Connection Factory or Destination Resource	331
Administering JMS Physical Destinations	332
▼ To Create a JMS Physical Destination	332
▼ To List JMS Physical Destinations	333
▼ To Purge Messages From a Physical Destination	334
▼ To Delete a JMS Physical Destination	334

Special Situations When Using the JMS Service	335
Troubleshooting the JMS Service	336
Using the Generic Resource Adapter for JMS to Integrate Supported External JMS Providers	336
Configuring GenericJMSRA for Supported External JMS Providers	337
Using GenericJMSRA with WebLogic JMS	344
Using GenericJMSRA with IBM WebSphere MQ	357
17 Administering the Java Naming and Directory Interface (JNDI) Service	367
About JNDI	367
Java EE Naming Environment	368
How the Naming Environment and the Container Work Together	368
Naming References and Binding Information	369
Administering JNDI Resources	369
Administering Custom JNDI Resources	370
Administering External JNDI Resources	372
18 Administering Transactions	377
About Transactions	377
Transaction Resource Managers	379
Transaction Scope	379
Configuring the Transaction Service	380
Managing the Transaction Service for Rollbacks	381
▼ To Stop the Transaction Service	382
▼ To Roll Back a Transaction	382
▼ To Restart the Transaction Service	383
Determining Local Transaction Completion at Shutdown	384
Recovering Transactions	384
Automatic Transaction Recovery	384
▼ To Manually Recover Transactions	385
Distributed Transaction Recovery	386
Recovery Workarounds and Limitations	386
Transaction Logging	388
▼ To Store Transaction Logs in a Database	388

Part III	Appendixes	391
A	Subcommands for the asadmin Utility	393
	General Administration Subcommands	394
	Connectivity Subcommands	396
	Domain Subcommands	399
	Internet Connectivity Subcommands	400
	JavaMail Subcommands	401
	JMS Subcommands	402
	JNDI Subcommands	403
	JVM Subcommands	404
	Life Cycle Module Subcommands	404
	Logging and Monitoring Subcommands	405
	ORB Subcommands	406
	Thread Pool Subcommands	406
	Transaction Service Subcommands	406
	Index	409

Figures

FIGURE 2-1	Web Page for the REST Resource for Managing a Domain	70
FIGURE 2-2	Web Page for the REST Resource That Provides Class Loader Statistics	99

Tables

TABLE 1-1	Default Administration Values	34
TABLE 1-2	Default Locations	34
TABLE 2-1	REST Resource Methods for Administering Monitoring and Configuration Data	71
TABLE 6-1	URL Fields for Servlets Within an Application	141
TABLE 8-1	HTTP Listener Common Monitoring Statistics	180
TABLE 8-2	JVM Common Monitoring Statistics	180
TABLE 8-3	Web Module Common Monitoring Statistics	181
TABLE 8-4	Example Resources Level Dotted Names	182
TABLE 8-5	EJB Cache Monitoring Statistics	186
TABLE 8-6	EJB Container Monitoring Statistics	186
TABLE 8-7	EJB Method Monitoring Statistics	187
TABLE 8-8	EJB Pool Monitoring Statistics	188
TABLE 8-9	Timer Monitoring Statistics	188
TABLE 8-10	HTTP Service Virtual Server Monitoring Statistics	189
TABLE 8-11	Jersey Statistics	190
TABLE 8-12	Connector Connection Pool Monitoring Statistics (JMS)	191
TABLE 8-13	Connector Work Management Monitoring Statistics (JMS)	192
TABLE 8-14	JVM Monitoring Statistics for Java SE Class Loading	193
TABLE 8-15	JVM Monitoring Statistics for Java SE - Threads	193
TABLE 8-16	JVM Monitoring Statistics for Java SE Compilation	194
TABLE 8-17	JVM Monitoring Statistics for Java SE Garbage Collectors	194
TABLE 8-18	JVM Monitoring Statistics for Java SE Memory	195
TABLE 8-19	JVM Statistics for the Java SE Operating System	195
TABLE 8-20	JVM Monitoring Statistics for Java SE Runtime	196
TABLE 8-21	Network Keep Alive Statistics	197
TABLE 8-22	Network Connection Queue Statistics	197
TABLE 8-23	Network File Cache Statistics	198
TABLE 8-24	Network Thread Pool Statistics	199

TABLE 8-25	ORB Monitoring Statistics (Connection Manager)	199
TABLE 8-26	General Resource Monitoring Statistics (Connection Pool)	200
TABLE 8-27	Application Specific Resource Monitoring Statistics (Connection Pool)	202
TABLE 8-28	EJB Security Monitoring Statistics	202
TABLE 8-29	Web Security Monitoring Statistics	203
TABLE 8-30	Realm Security Monitoring Statistics	203
TABLE 8-31	Thread Pool Monitoring Statistics	204
TABLE 8-32	JVM Monitoring Statistics for Java SE - Thread Info	204
TABLE 8-33	Transaction Service Monitoring Statistics	205
TABLE 8-34	Web Module Servlet Statistics	206
TABLE 8-35	Web JSP Monitoring Statistics	206
TABLE 8-36	Web Request Monitoring Statistics	207
TABLE 8-37	Web Servlet Monitoring Statistics	207
TABLE 8-38	Web Session Monitoring Statistics	208
TABLE 10-1	Oracle GlassFish Server Preconfigured Repositories	216
TABLE 10-2	GlassFish Server Open Source Edition Preconfigured Repositories	219
TABLE 13-1	Default Ports for Listeners	295
TABLE 17-1	JNDI Lookup Names and Their Associated References	369

Examples

EXAMPLE 1-1	Determining if the DAS Requires Restart	40
EXAMPLE 1-2	Determining if an Instance Requires Restart	40
EXAMPLE 1-3	Connecting to the Apache Felix Gogo Remote Shell	47
EXAMPLE 1-4	Listing All Installed OSGi Bundles	47
EXAMPLE 1-5	Determining the Services That an OSGi Bundle Provides	47
EXAMPLE 2-1	Running an asadmin Utility Subcommand in Single Mode	56
EXAMPLE 2-2	Specifying an asadmin Utility Option With a Subcommand in Single Mode	56
EXAMPLE 2-3	Specifying an asadmin Utility Option and a Subcommand Option in Single Mode	56
EXAMPLE 2-4	Displaying Help Information for the asadmin Utility	57
EXAMPLE 2-5	Displaying Help Information for an asadmin Utility Subcommand	57
EXAMPLE 2-6	Starting a Multimode Session With asadmin Utility Options	58
EXAMPLE 2-7	Starting a Multimode Session by Using the multimode Subcommand	58
EXAMPLE 2-8	Running a Subcommand in a Multimode Session	58
EXAMPLE 2-9	Running a Set of asadmin Subcommands From a File	59
EXAMPLE 2-10	Creating a System Property	60
EXAMPLE 2-11	Listing System Properties	61
EXAMPLE 2-12	Deleting a System Property	62
EXAMPLE 2-13	Adding Resources	62
EXAMPLE 2-14	Displaying Version Information	63
EXAMPLE 2-15	Listing Applications	64
EXAMPLE 2-16	Listing Containers	64
EXAMPLE 2-17	Listing Modules	65
EXAMPLE 2-18	Listing Subcommands	66
EXAMPLE 2-19	Listing Timers	67
EXAMPLE 2-20	Showing Status of a Component	67
EXAMPLE 2-21	Determining the Methods and Method Parameters That an Object in the Tree Supports	72
EXAMPLE 2-22	Retrieving Data for an Object in the Tree	74

EXAMPLE 2-23	Adding an Object to the Tree	75
EXAMPLE 2-24	Updating an Object in the Tree	77
EXAMPLE 2-25	Deleting an Object From the Tree	79
EXAMPLE 3-1	Creating a Domain	108
EXAMPLE 3-2	Listing Domains	112
EXAMPLE 3-3	Logging In To a Domain on a Remote Machine	113
EXAMPLE 3-4	Logging In to a Domain on the Default Port of Localhost	114
EXAMPLE 3-5	Deleting a Domain	114
EXAMPLE 3-6	Starting a Domain	115
EXAMPLE 3-7	Stopping a Domain (or Server)	116
EXAMPLE 3-8	Restarting a Domain (or Server)	117
EXAMPLE 3-9	Restarting a Domain in a Browser	117
EXAMPLE 3-10	Creating a Service to Restart a DAS Automatically on Windows	118
EXAMPLE 3-11	Querying the Service to Restart a DAS Automatically on Windows	119
EXAMPLE 3-12	Creating a Service to Restart a DAS Automatically on Linux	119
EXAMPLE 3-13	Creating a Service to Restart a Domain Automatically on Oracle Solaris	121
EXAMPLE 3-14	Backing Up the Default Domain	123
EXAMPLE 3-15	Restoring the Default Domain	124
EXAMPLE 3-16	Listing Backups of the Default Domain	124
EXAMPLE 3-17	Displaying the DAS Uptime	127
EXAMPLE 3-18	Changing the Administration Port of a Domain	129
EXAMPLE 4-1	Creating JVM Options	132
EXAMPLE 4-2	Listing JVM Options	132
EXAMPLE 4-3	Deleting a JVM Option	133
EXAMPLE 4-4	Deleting Multiple JVM Options	134
EXAMPLE 4-5	Generating a JVM Report	134
EXAMPLE 4-6	Creating a Profiler	135
EXAMPLE 4-7	Deleting a Profiler	136
EXAMPLE 5-1	Creating a Thread Pool	138
EXAMPLE 5-2	Listing Thread Pools	139
EXAMPLE 5-3	Updating a Thread Pool	139
EXAMPLE 5-4	Deleting a Thread Pool	140
EXAMPLE 6-1	Invoking a Servlet With a URL	142
EXAMPLE 6-2	Invoking a Servlet From Within a JSP File	142
EXAMPLE 6-3	Redirecting a URL	144
EXAMPLE 6-4	httpd.conf File for mod_jk	146

EXAMPLE 6-5	workers.properties File for mod_jk	146
EXAMPLE 6-6	httpd.conf File for Load Balancing	147
EXAMPLE 6-7	workers.properties File for Load Balancing	147
EXAMPLE 6-8	http-ssl.conf File for mod_jk Security	149
EXAMPLE 7-1	Changing the Name and Location of a Cluster's Log File	157
EXAMPLE 7-2	Setting the java.util.logging.config.file System Property	158
EXAMPLE 7-3	Listing Logger Levels for Modules	160
EXAMPLE 7-4	Listing Log Levels for an Instance	160
EXAMPLE 7-5	Changing the Global Log Level for All Module Loggers	161
EXAMPLE 7-6	Setting the Log Level for a Module Logger	162
EXAMPLE 7-7	Setting Log Levels for Multiple Loggers	162
EXAMPLE 7-8	Changing the Rotation Size	163
EXAMPLE 7-9	Changing the Rotation Interval	164
EXAMPLE 7-10	Changing the Limit Number of Retained Files	165
EXAMPLE 7-11	Rotating Log Files Manually	166
EXAMPLE 7-12	Adding a New Log Handler	167
EXAMPLE 7-13	Creating a ZIP Archive	168
EXAMPLE 8-1	Enabling the Monitoring Service Dynamically	177
EXAMPLE 8-2	Enabling Monitoring for Modules Dynamically	177
EXAMPLE 8-3	Enabling Monitoring for Modules by Using the set Subcommand	177
EXAMPLE 8-4	Disabling the Monitoring Service Dynamically	178
EXAMPLE 8-5	Disabling Monitoring for Modules Dynamically	178
EXAMPLE 8-6	Disabling Monitoring by Using the set Subcommand	178
EXAMPLE 8-7	Viewing Common Monitoring Data	179
EXAMPLE 8-8	Viewing Attributes for a Specific Type	183
EXAMPLE 8-9	Viewing Monitorable Applications	184
EXAMPLE 8-10	Viewing Attributes for an Application	184
EXAMPLE 8-11	Viewing a Specific Attribute	184
EXAMPLE 9-1	Creating a Life Cycle Module	212
EXAMPLE 9-2	Listing Life Cycle Modules	213
EXAMPLE 9-3	Updating a Life Cycle Module	214
EXAMPLE 9-4	Deleting a Life Cycle Module	214
EXAMPLE 10-1	Starting a Local Repository Daemon	238
EXAMPLE 10-2	Configuring the pkg Command to Use a Local Repository	240
EXAMPLE 11-1	Starting a Database	247
EXAMPLE 11-2	Stopping a Database	248

EXAMPLE 11-3	Creating a JDBC Connection Pool	251
EXAMPLE 11-4	Listing JDBC Connection Pools	251
EXAMPLE 11-5	Contacting a Connection Pool	252
EXAMPLE 11-6	Resetting (Flushing) a Connection Pool	253
EXAMPLE 11-7	Deleting a JDBC Connection Pool	254
EXAMPLE 11-8	Creating a JDBC Resource	259
EXAMPLE 11-9	Listing JDBC Resources	260
EXAMPLE 11-10	Updating a JDBC Resource	260
EXAMPLE 11-11	Deleting a JDBC Resource	261
EXAMPLE 12-1	Creating a Connector Connection Pool	276
EXAMPLE 12-2	Listing Connector Connection Pools	276
EXAMPLE 12-3	Deleting a Connector Connection Pool	278
EXAMPLE 12-4	Creating a Connector Resource	279
EXAMPLE 12-5	Listing Connector Resources	279
EXAMPLE 12-6	Deleting a Connector Resource	281
EXAMPLE 12-7	Creating a Resource Adapter Configuration	281
EXAMPLE 12-8	Listing Configurations for a Resource Adapter	282
EXAMPLE 12-9	Deleting a Resource Adapter Configuration	283
EXAMPLE 12-10	Creating a Connector Security Map	284
EXAMPLE 12-11	Listing All Connector Security Maps for a Connector Connection Pool	285
EXAMPLE 12-12	Listing Principals for a Specific Security Map for a Connector Connection Pool	285
EXAMPLE 12-13	Listing Principals of All Connector Security Maps for a Connector Connection Pool	285
EXAMPLE 12-14	Updating a Connector Security Map	286
EXAMPLE 12-15	Deleting a Connector Security Map	286
EXAMPLE 12-16	Creating Connector Work Security Maps	287
EXAMPLE 12-17	Listing the Connector Work Security Maps	288
EXAMPLE 12-18	Updating a Connector Work Security Map	289
EXAMPLE 12-19	Deleting a Connector Work Security Map	289
EXAMPLE 12-20	Creating an Administered Object	290
EXAMPLE 12-21	Listing Administered Objects	291
EXAMPLE 12-22	Deleting an Administered Object	291
EXAMPLE 13-1	Creating an HTTP Protocol	297
EXAMPLE 13-2	Listing the Protocols	297
EXAMPLE 13-3	Deleting a Protocol	298

EXAMPLE 13-4	Creating an HTTP Configuration	299
EXAMPLE 13-5	Deleting an HTTP Configuration	299
EXAMPLE 13-6	Creating a Transport	300
EXAMPLE 13-7	Listing HTTP Transports	300
EXAMPLE 13-8	Deleting a Transport	301
EXAMPLE 13-9	Creating an HTTP Listener	302
EXAMPLE 13-10	Creating a Network Listener	302
EXAMPLE 13-11	Listing HTTP Listeners	302
EXAMPLE 13-12	Updating an HTTP Network Listener	303
EXAMPLE 13-13	Deleting an HTTP Listener	303
EXAMPLE 13-14	Configuring an HTTP Listener for SSL	304
EXAMPLE 13-15	Deleting SSL From an HTTP Listener	304
EXAMPLE 13-16	Creating a Virtual Server	306
EXAMPLE 13-17	Listing Virtual Servers	307
EXAMPLE 13-18	Deleting a Virtual Server	308
EXAMPLE 14-1	Creating an IIOP Listener	312
EXAMPLE 14-2	Listing IIOP Listeners	313
EXAMPLE 14-3	Updating an IIOP Listener	313
EXAMPLE 14-4	Deleting an IIOP Listener	314
EXAMPLE 15-1	Creating a JavaMail Resource	317
EXAMPLE 15-2	Listing JavaMail Resources	317
EXAMPLE 15-3	Updating a JavaMail Resource	318
EXAMPLE 15-4	Deleting a JavaMail Resource	318
EXAMPLE 16-1	Creating a JMS Host	326
EXAMPLE 16-2	Listing JMS Hosts	326
EXAMPLE 16-3	Updating a JMS Host	328
EXAMPLE 16-4	Deleting a JMS Host	328
EXAMPLE 16-5	Creating a JMS Connection Factory	330
EXAMPLE 16-6	Creating a JMS Destination	330
EXAMPLE 16-7	Listing All JMS Resources	331
EXAMPLE 16-8	Listing a JMS Resources of a Specific Type	331
EXAMPLE 16-9	Deleting a JMS Resource	332
EXAMPLE 16-10	Creating a JMS Physical Destination	333
EXAMPLE 16-11	Listing JMS Physical Destinations	333
EXAMPLE 16-12	Flushing Messages From a JMS Physical Destination	334
EXAMPLE 16-13	Deleting a Physical Destination	335

EXAMPLE 17-1	Creating a Custom Resource	370
EXAMPLE 17-2	Listing Custom Resources	371
EXAMPLE 17-3	Updating a Custom JNDI Resource	371
EXAMPLE 17-4	Deleting a Custom Resource	371
EXAMPLE 17-5	Registering an External JNDI Resource	372
EXAMPLE 17-6	Listing JNDI Resources	373
EXAMPLE 17-7	Listing JNDI Entries	373
EXAMPLE 17-8	Updating an External JNDI Resource	374
EXAMPLE 17-9	Deleting an External JNDI Resource	374
EXAMPLE 18-1	Stopping the Transaction Service	382
EXAMPLE 18-2	Rolling Back a Transaction	383
EXAMPLE 18-3	Restarting the Transaction Service	383
EXAMPLE 18-4	Manually Recovering Transactions	385

Preface

GlassFish Server Open Source Edition 3.1 Administration Guide provides instructions for configuring and administering GlassFish Server Open Source Edition.

This preface contains information about and conventions for the entire GlassFish Server Open Source Edition (GlassFish Server) documentation set.

GlassFish Server 3.1 is developed through the GlassFish project open-source community at <http://glassfish.java.net/>. The GlassFish project provides a structured process for developing the GlassFish Server platform that makes the new features of the Java EE platform available faster, while maintaining the most important feature of Java EE: compatibility. It enables Java developers to access the GlassFish Server source code and to contribute to the development of the GlassFish Server. The GlassFish project is designed to encourage communication between Oracle engineers and the community.

The following topics are addressed here:

- “GlassFish Server Documentation Set” on page 25
- “Related Documentation” on page 27
- “Typographic Conventions” on page 28
- “Symbol Conventions” on page 29
- “Default Paths and File Names” on page 29
- “Documentation, Support, and Training” on page 30
- “Searching Oracle Product Documentation” on page 30
- “Third-Party Web Site References” on page 31

GlassFish Server Documentation Set

The GlassFish Server documentation set describes deployment planning and system installation. For an introduction to GlassFish Server, refer to the books in the order in which they are listed in the following table.

TABLE P-1 Books in the GlassFish Server Documentation Set

Book Title	Description
<i>Release Notes</i>	Provides late-breaking information about the software and the documentation and includes a comprehensive, table-based summary of the supported hardware, operating system, Java Development Kit (JDK), and database drivers.
<i>Quick Start Guide</i>	Explains how to get started with the GlassFish Server product.
<i>Installation Guide</i>	Explains how to install the software and its components.
<i>Upgrade Guide</i>	Explains how to upgrade to the latest version of GlassFish Server. This guide also describes differences between adjacent product releases and configuration options that can result in incompatibility with the product specifications.
<i>Deployment Planning Guide</i>	Explains how to build a production deployment of GlassFish Server that meets the requirements of your system and enterprise.
<i>Administration Guide</i>	Explains how to configure, monitor, and manage GlassFish Server subsystems and components from the command line by using the <code>asadmin(1M)</code> utility. Instructions for performing these tasks from the Administration Console are provided in the Administration Console online help.
<i>Security Guide</i>	Provides instructions for configuring and administering GlassFish Server security.
<i>Application Deployment Guide</i>	Explains how to assemble and deploy applications to the GlassFish Server and provides information about deployment descriptors.
<i>Application Development Guide</i>	Explains how to create and implement Java Platform, Enterprise Edition (Java EE platform) applications that are intended to run on the GlassFish Server. These applications follow the open Java standards model for Java EE components and application programmer interfaces (APIs). This guide provides information about developer tools, security, and debugging.
<i>Add-On Component Development Guide</i>	Explains how to use published interfaces of GlassFish Server to develop add-on components for GlassFish Server. This document explains how to perform <i>only</i> those tasks that ensure that the add-on component is suitable for GlassFish Server.
<i>Embedded Server Guide</i>	Explains how to run applications in embedded GlassFish Server and to develop applications in which GlassFish Server is embedded.
<i>High Availability Administration Guide</i>	Explains how to configure GlassFish Server to provide higher availability and scalability through failover and load balancing.
<i>Performance Tuning Guide</i>	Explains how to optimize the performance of GlassFish Server.

TABLE P-1 Books in the GlassFish Server Documentation Set (Continued)

Book Title	Description
<i>Troubleshooting Guide</i>	Describes common problems that you might encounter when using GlassFish Server and explains how to solve them.
<i>Error Message Reference</i>	Describes error messages that you might encounter when using GlassFish Server.
<i>Reference Manual</i>	Provides reference information in man page format for GlassFish Server administration commands, utility commands, and related concepts.
<i>Message Queue Release Notes</i>	Describes new features, compatibility issues, and existing bugs for Open Message Queue.
<i>Message Queue Technical Overview</i>	Provides an introduction to the technology, concepts, architecture, capabilities, and features of the Message Queue messaging service.
<i>Message Queue Administration Guide</i>	Explains how to set up and manage a Message Queue messaging system.
<i>Message Queue Developer's Guide for JMX Clients</i>	Describes the application programming interface in Message Queue for programmatically configuring and monitoring Message Queue resources in conformance with the Java Management Extensions (JMX).
<i>Message Queue Developer's Guide for Java Clients</i>	Provides information about concepts and procedures for developing Java messaging applications (Java clients) that work with GlassFish Server.
<i>Message Queue Developer's Guide for C Clients</i>	Provides programming and reference information for developers working with Message Queue who want to use the C language binding to the Message Queue messaging service to send, receive, and process Message Queue messages.

Related Documentation

The following tutorials explain how to develop Java EE applications:

- *Your First Cup: An Introduction to the Java EE Platform* (<http://download.oracle.com/javaee/6/firstcup/doc/>). For beginning Java EE programmers, this short tutorial explains the entire process for developing a simple enterprise application. The sample application is a web application that consists of a component that is based on the Enterprise JavaBeans specification, a JAX-RS web service, and a JavaServer Faces component for the web front end.
- *The Java EE 6 Tutorial* (<http://download.oracle.com/javaee/6/tutorial/doc/>). This comprehensive tutorial explains how to use Java EE 6 platform technologies and APIs to develop Java EE applications.

Javadoc tool reference documentation for packages that are provided with GlassFish Server is available as follows.

- The API specification for version 6 of Java EE is located at <http://download.oracle.com/javaee/6/api/>.
- The API specification for GlassFish Server 3.1, including Java EE 6 platform packages and nonplatform packages that are specific to the GlassFish Server product, is located at <http://glassfish.java.net/nonav/docs/v3/api/>.

Additionally, the [Java EE Specifications](http://www.oracle.com/technetwork/java/javaee/tech/index.html) (<http://www.oracle.com/technetwork/java/javaee/tech/index.html>) might be useful.

For information about creating enterprise applications in the NetBeans Integrated Development Environment (IDE), see the [NetBeans Documentation, Training & Support page](http://www.netbeans.org/kb/) (<http://www.netbeans.org/kb/>).

For information about the Java DB database for use with the GlassFish Server, see the [Java DB product page](http://www.oracle.com/technetwork/java/javadb/overview/index.html) (<http://www.oracle.com/technetwork/java/javadb/overview/index.html>).

The Java EE Samples project is a collection of sample applications that demonstrate a broad range of Java EE technologies. The Java EE Samples are bundled with the Java EE Software Development Kit (SDK) and are also available from the [Java EE Samples project page](http://java.net/projects/glassfish-samples) (<http://java.net/projects/glassfish-samples>).

Typographic Conventions

The following table describes the typographic changes that are used in this book.

TABLE P-2 Typographic Conventions

Typeface	Meaning	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name%</code> you have mail.
AaBbCc123	What you type, contrasted with onscreen computer output	<code>machine_name% su</code> Password:
<i>AaBbCc123</i>	A placeholder to be replaced with a real name or value	The command to remove a file is <i>rm filename</i> .
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized (note that some emphasized items appear bold online)	Read Chapter 6 in the <i>User's Guide</i> . A <i>cache</i> is a copy that is stored locally. Do <i>not</i> save the file.

Symbol Conventions

The following table explains symbols that might be used in this book.

TABLE P-3 Symbol Conventions

Symbol	Description	Example	Meaning
[]	Contains optional arguments and command options.	ls [-l]	The -l option is not required.
{ }	Contains a set of choices for a required command option.	-d {y n}	The -d option requires that you use either the y argument or the n argument.
\${ }	Indicates a variable reference.	\${com.sun.javaRoot}	References the value of the com.sun.javaRoot variable.
-	Joins simultaneous multiple keystrokes.	Control-A	Press the Control key while you press the A key.
+	Joins consecutive multiple keystrokes.	Ctrl+A+N	Press the Control key, release it, and then press the subsequent keys.
→	Indicates menu item selection in a graphical user interface.	File → New → Templates	From the File menu, choose New. From the New submenu, choose Templates.

Default Paths and File Names

The following table describes the default paths and file names that are used in this book.

TABLE P-4 Default Paths and File Names

Placeholder	Description	Default Value
<i>as-install</i>	Represents the base installation directory for GlassFish Server. In configuration files, <i>as-install</i> is represented as follows: \${com.sun.aas.installRoot}	Installations on the Oracle Solaris operating system, Linux operating system, and Mac OS operating system: <i>user's-home-directory/glassfish3/glassfish</i> Windows, all installations: <i>SystemDrive:\glassfish3\glassfish</i>

TABLE P-4 Default Paths and File Names (Continued)

Placeholder	Description	Default Value
<i>as-install-parent</i>	Represents the parent of the base installation directory for GlassFish Server.	Installations on the Oracle Solaris operating system, Linux operating system, and Mac operating system: <i>user's-home-directory/glassfish3</i> Windows, all installations: <i>SystemDrive:\glassfish3</i>
<i>domain-root-dir</i>	Represents the directory in which a domain is created by default.	<i>as-install/domains/</i>
<i>domain-dir</i>	Represents the directory in which a domain's configuration is stored. In configuration files, <i>domain-dir</i> is represented as follows: <code>\${com.sun.aas.instanceRoot}</code>	<i>domain-root-dir/domain-name</i>

Documentation, Support, and Training

The Oracle web site provides information about the following additional resources:

- Documentation (<http://www.oracle.com/technetwork/indexes/documentation/index.html>)
- Support (<http://www.oracle.com/us/support/index.html>)
- Training (<http://education.oracle.com/>)

Searching Oracle Product Documentation

Besides searching Oracle product documentation from the [Oracle Documentation](http://www.oracle.com/technetwork/indexes/documentation/index.html) (<http://www.oracle.com/technetwork/indexes/documentation/index.html>) web site, you can use a search engine by typing the following syntax in the search field:

search-term **site:oracle.com**

For example, to search for “broker,” type the following:

broker site:oracle.com

Third-Party Web Site References

Third-party URLs are referenced in this document and provide additional, related information.

Note – Oracle is not responsible for the availability of third-party web sites mentioned in this document. Oracle does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Oracle will not be responsible or liable for any actual or alleged damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

Overview of GlassFish Server Administration

GlassFish Server Open Source Edition provides a server for developing and deploying Java Platform Enterprise Edition (Java EE) applications and web Java Web Services.

As an administrator of GlassFish Server, your main responsibilities are to establish a secure GlassFish Server environment and to oversee the services, resources, and users that participate in that environment. Your key tasks include configuring resources and services, managing GlassFish Server at runtime, and fixing problems that are associated with the server. You might also be involved in installing software, integrating add-on components, and deploying applications.

The following topics are addressed here:

- [“Default Settings and Locations” on page 33](#)
- [“Configuration Tasks” on page 34](#)
- [“Administration Tools” on page 42](#)
- [“Instructions for Administering GlassFish Server” on page 49](#)

Default Settings and Locations

After installation, you might need to perform some immediate configuration tasks to make your installation function as intended. If configuration defaults have been accepted, some features are enabled and some not. For an overview of initial configuration tasks for GlassFish Server services and resources, see [“Initial Configuration Tasks” on page 35](#).

In addition, you might want to reset default passwords, change names or locations of files, and so on. The following tables list the default administration values.

Note – For the zip bundle of GlassFish Server 3.1, the default administrator login is `admin`, with no password, which means that no login is required.

TABLE 1-1 Default Administration Values

Item	Default
Domain Name	domain1
Master Password	changeit
Administration Password	admin
Administration Server Port	4848
HTTP Port	8080
HTTPS Port	8181
Pure JMX Clients Port	8686
Message Queue Port	7676
IIOP Port	3700
IIOP/SSL Port	3820
IIOP/SSL Port With Mutual Authentication	3920

TABLE 1-2 Default Locations

Item	Default
Command-line Utility (asadmin)	as-install/bin
Configuration Files	domain-dir/config
Log Files	domain-dir/logs
Upgrade Tool (asupgrade Command)	as-install/bin
Update Tool and pkg Command	as-install-parent/bin

For information about replaceable items and default paths and files, see [“Default Paths and File Names” on page 29](#).

Configuration Tasks

Some configuration tasks must be performed directly after installation for your GlassFish Server environment to work as intended. For example, if you are using a database with GlassFish Server, you need to set up database connectivity right away.

Some configuration situations are ongoing and will require you to make changes many times during the life of your installation. You can use either the Administration Console or the `asadmin` utility to modify the configuration. Changes are automatically applied to the appropriate configuration file.

The following topics are addressed here:

- [“Initial Configuration Tasks” on page 35](#)
- [“How Dotted Names Work for Configuration” on page 37](#)
- [“Configuration Files” on page 38](#)
- [“Impact of Configuration Changes” on page 38](#)

Initial Configuration Tasks

This section maps the common configuration tasks to the command-line procedures in this guide. In some situations, the resource or service is automatically enabled and your configuration tasks involve adjusting or changing the default settings to suit your specific needs.

The following resources and services frequently require configuration immediately after installation:

System Properties

See [“Administering System Properties” on page 60](#).

Domains

The initial `domain1` is created during installation. Additional configuration tasks might include such tasks as configuring additional domains or setting up automatic restart. See [Chapter 3, “Administering Domains.”](#)

JVM

The initial tasks for configuring the JVM include creating JVM options and profilers. See [Chapter 4, “Administering the Virtual Machine for the Java Platform.”](#)

Logging

By default, logging is enabled, so basic logging works without additional configuration. However, you might want to change log levels, property values, or the location of log files. See [Chapter 7, “Administering the Logging Service.”](#)

Monitoring

By default, the monitoring service is enabled. However, monitoring for the individual modules is not enabled, so your first monitoring task is to enable monitoring for the modules that you want to monitor. See [Chapter 8, “Administering the Monitoring Service.”](#)

Life Cycle Modules

See [Chapter 9, “Administering Life Cycle Modules.”](#)

Security

- **System Security.** Initial configuration tasks might include setting up passwords, audit modules, and certificates. See Chapter 1, “Administering System Security,” in *GlassFish Server Open Source Edition 3.1 Security Guide*.
- **User Security.** Initial configuration tasks might include creating authentication realms and file users. See Chapter 2, “Administering User Security,” in *GlassFish Server Open Source Edition 3.1 Security Guide*.
- **Message Security.** Initial configuration tasks might include configuring a Java Cryptography Extension (JCE) provider, enabling default and non-default security providers, and configuring message protection policies. See Chapter 3, “Administering Message Security,” in *GlassFish Server Open Source Edition 3.1 Security Guide*.

Database Connectivity

The initial tasks involved in configuring GlassFish Server to connect to the Java DB database include creating a Java Database Connectivity (JDBC) connection pool, creating a JDBC resource, and integrating a JDBC driver. See [Chapter 11, “Administering Database Connectivity.”](#)

EIS Connectivity

The initial tasks involved in configuring GlassFish Server to connect to an enterprise information system (EIS) include creating a connector connection pool, creating a connector resource, editing a resource adapter configuration, creating a connector security map, creating a connector work security map, and creating an administered object (if needed). See [Chapter 12, “Administering EIS Connectivity.”](#)

Internet Connectivity

The initial tasks involved in making deployed web applications accessible by internet clients include creating HTTP network listeners and virtual servers, and configuring the HTTP listeners for SSL (if needed). See [Chapter 13, “Administering Internet Connectivity.”](#)

Object Request Broker (ORB)

An initial configuration task might involve creating an IIOP listener. See [Chapter 14, “Administering the Object Request Broker \(ORB\).”](#)

JavaMail Service

An initial configuration task might involve creating a JavaMail resource. See [Chapter 15, “Administering the JavaMail Service.”](#)

Java Message Service (JMS)

Initial configuration tasks might include creating a physical destination, creating connection factories or destination resources, creating a JMS host (if the default JMS host is not adequate), adjusting connection pool settings (if needed), and configuring resource adapters for JMS. See [Chapter 16, “Administering the Java Message Service \(JMS\).”](#)

JNDI Service

An initial configuration task might involve creating a JNDI resource. See [Chapter 17, “Administering the Java Naming and Directory Interface \(JNDI\) Service.”](#)

Information and instructions for accomplishing the tasks by using the Administration Console are contained in the Administration Console online help.

How Dotted Names Work for Configuration

After the initial configuration is working, you will continue to manage ongoing configuration for the life of your GlassFish Server installation. You might need to adjust resources to improve productivity, or issues might arise that require settings to be modified or defaults to be reset. In some situations, an `asadmin` subcommand is provided for updating, such as the `update-connector-work-security-map` subcommand. However, most updating is done by using the `list`, `get`, and `set` subcommands with dotted names. For detailed information about dotted names, see the `dotted-names(5ASC)` help page.

Note – Dotted names also apply to monitoring, but the method is different. For information on using dotted names for monitoring, see [“How the Monitoring Tree Structure Works” on page 170](#).

The general process for working with configuration changes on the command line is as follows:

1. List the modules for the component of interest.

The following single mode example uses the `|` (pipe) character and the `grep` command to narrow the search:

```
asadmin list "*" | grep http | grep listener
```

Information similar to the following is returned:

```
configs.config.server-config.network-config.network-listeners.network-listener.http-listener-1
configs.config.server-config.network-config.network-listeners.network-listener.http-listener-2
configs.config.server-config.network-config.protocols.protocol.admin-listener.http
configs.config.server-config.network-config.protocols.protocol.admin-listener.http.file-cache
configs.config.server-config.network-config.protocols.protocol.http-listener-1
configs.config.server-config.network-config.protocols.protocol.http-listener-1.http
configs.config.server-config.network-config.protocols.protocol.http-listener-1.http.file-cache
configs.config.server-config.network-config.protocols.protocol.http-listener-2
configs.config.server-config.network-config.protocols.protocol.http-listener-2.http
configs.config.server-config.network-config.protocols.protocol.http-listener-2.http.file-cache
configs.config.server-config.network-config.protocols.protocol.http-listener-2.ssl
```

2. Get the attributes that apply to the module you are interested in.

The following multimode example gets the attributes and values for `http-listener-1`:

```
asadmin> get server-config.network-config.network-listeners.network-listener.http-listener-1.*
```

Information similar to the following is returned:

```
server.http-service.http-listener.http-listener-1.acceptor-threads = 1
server.http-service.http-listener.http-listener-1.address = 0.0.0.0
server.http-service.http-listener.http-listener-1.blocking-enabled = false
```

```
server.http-service.http-listener.http-listener-1.default-virtual-server = server
server.http-service.http-listener.http-listener-1.enabled = true
server.http-service.http-listener.http-listener-1.external-port =
server.http-service.http-listener.http-listener-1.family = inet
server.http-service.http-listener.http-listener-1.id = http-listener-1
server.http-service.http-listener.http-listener-1.port = 8080
server.http-service.http-listener.http-listener-1.redirect-port =
server.http-service.http-listener.http-listener-1.security-enabled = false
server.http-service.http-listener.http-listener-1.server-name =
server.http-service.http-listener.http-listener-1.xpowered-by = true
```

3. Modify an attribute by using the set subcommand.

This example sets the security-enabled attribute of http-listener-1 to true:

```
asadmin> set server.http-service.http-listener.http-listener-1.security-enabled = true
```

Configuration Files

The bulk of the configuration information about GlassFish Server resources, applications, and instances is stored in the `domain.xml` configuration file. This file is the central repository for a given administrative domain and contains an XML representation of the GlassFish Server domain model. The default location for the `domain.xml` file is `as-install/domains/domain-name/config`.

Note – GlassFish Server maintains a backup of the `domain.xml` file that is named `domain.xml.bak`. The purpose of this file is solely to enable GlassFish Server to start a domain if the `domain.xml` file cannot be read. Do *not* modify or delete the `domain.xml.bak` file and do *not* use this file for any other purpose.

The `logging.properties` file is used to configure logging levels for individual modules. The default `logging.properties` file is located in the same directory as the `domain.xml` file. For further information on the `logging.properties` file, see [“Logging Properties” on page 155](#).

The `asenv.conf` file is located in the `as-install/config` directory. Its purpose is to store the GlassFish Server environment variables, such as the installation location of the database, Message Queue, and so on.

Note – Changes are automatically applied to the appropriate configuration file. Do not edit the configuration files directly. Manual editing is prone to error and can have unexpected results.

Impact of Configuration Changes

Some configuration changes require that you restart the DAS or GlassFish Server instances for the changes to take effect. Other changes are applied dynamically without requiring that the

DAS or instances be restarted. The procedures in this guide indicate when a restart is required. GlassFish Server enables you to determine whether the DAS or an instance must be restarted to apply configuration changes.

Some changes to resources or connection pools affect the applications that use the resources or connection pools. These changes do not require restart. However, any applications that use the resources or connection pools must be disabled and re-enabled or redeployed for the change to take effect.

The following topics are addressed here:

- [“To Determine Whether the DAS or an Instance Requires Restart” on page 39](#)
- [“Configuration Changes That Require Restart” on page 40](#)
- [“Dynamic Configuration Changes” on page 41](#)
- [“Changes That Affect Applications” on page 41](#)

▼ To Determine Whether the DAS or an Instance Requires Restart

1 Ensure that the DAS is running.

To obtain information about the DAS or an instance, a running server is required.

2 Do one of the following:

- **To determine if the DAS requires restart, list the domains in your GlassFish Server installation.**

Use the `list-domains(1)` subcommand for this purpose.

```
asadmin> list-domains [--domaindir domain-dir]
```

domain-dir

The directory that contains the directories in which individual domains' configuration is stored. The default is *as-install/domains*, where *as-install* is the base installation directory of the GlassFish Server software.

If the DAS requires restart, a statement that restart is required is displayed.

- **To determine if an instance requires restart, list information about the instance.**

Use the `list-instances(1)` subcommand for this purpose.

```
asadmin> list-instances instance-name
```

instance-name

The name of the instance for which you are listing information.

If the instance requires restart, one of the following pieces of information is displayed:

- A statement that restart is required
- A list of configuration changes that are not yet applied to the instance

Example 1–1 Determining if the DAS Requires Restart

This example determines that the DAS for the domain `domain1` requires restart to apply configuration changes.

```
asadmin> list-domains
domain1 running, restart required to apply configuration changes
Command list-domains executed successfully.
```

Example 1–2 Determining if an Instance Requires Restart

This example determines that the instance `pmd-i1` requires restart to apply configuration changes.

```
asadmin> list-instances pmd-i1
pmd-i1 running; requires restart
Command list-instances executed successfully.
```

- See Also**
- `list-domains(1)`
 - `list-instances(1)`

You can also view the full syntax and options of the subcommands by typing the following commands at the command line.

- `asadmin help list-domains`
- `asadmin help list-instances`

Configuration Changes That Require Restart

The following configuration changes require restart for the changes to take effect:

- Changing JVM options
- Changing port numbers

Note – Changes to some port numbers, for example HTTP listener ports, do not require restart.

- Changing log handler elements
- Configuring certificates
- Managing HTTP, JMS, IIOP, JNDI services
- Enabling or disabling secure administration as explained in “Running Secure Admin” in *GlassFish Server Open Source Edition 3.1 Security Guide*

Dynamic Configuration Changes

With *dynamic configuration*, changes take effect while the DAS or instance is running. The following configuration changes do not require restart:

- Adding or deleting add-on components
- Adding or removing JDBC, JMS, and connector resources and pools (Exception: Some connection pool properties affect applications.)
- Changing a system property that is not referenced by a JVM option or a port
- Adding file realm users
- Changing logging levels
- Enabling and disabling monitoring
- Changing monitoring levels for modules
- Enabling and disabling resources and applications
- Deploying, undeploying, and redeploying applications

Changes That Affect Applications

Some changes to resources or connection pools affect the applications that use the resources or connection pools. These changes do not require restart. However, any applications that use the resources or connection pools must be disabled and re-enabled or redeployed for the change to take effect.

Note – If you do not know which applications use the changed resources or connection pools, you can apply these changes by restarting the clusters or GlassFish Server instances to which applications are deployed. However, to minimize the disruption to the services that your applications provide, avoid restarting clusters or instances to apply these changes if possible.

The following changes affect applications:

- Creating or deleting resources (Exception: Changes to some JDBC, JMS, or connector resources do not affect applications.)
- Modifying the following JDBC connection pool properties:
 - `datasource-classname`
 - `associate-with-thread`
 - `lazy-connection-association`
 - `lazy-connection-enlistment`
 - JDBC driver vendor-specific properties
- Modifying the following connector connection pool properties:
 - `resource-adapter-name`
 - `connection-definition-name`

- transaction-support
- associate-with-thread
- lazy-connection-association
- lazy-connection-enlistment
- Vendor-specific properties

Administration Tools

For the most part, you can perform the same tasks by using either the graphical Administration Console or the `asadmin` command-line utility, however, there are exceptions.

The following GlassFish Server administration tools are described here:

- [“Administration Console” on page 42](#)
- [“asadmin Utility” on page 43](#)
- [“REST Interfaces” on page 43](#)
- [“Update Tool” on page 44](#)
- [“OSGi Module Management Subsystem” on page 44](#)
- [“keytool Utility” on page 49](#)
- [“Java Monitoring and Management Console \(JConsole\)” on page 49](#)

Administration Console

The Administration Console is a browser-based utility that features an easy-to-navigate graphical interface that includes extensive online help for the administrative tasks.

To use the Administration Console, the domain administration server (DAS) must be running. Each domain has its own DAS, which has a unique port number. When GlassFish Server was installed, you chose a port number for the DAS, or used the default port of 4848. You also specified a user name and password if you did not accept the default login (admin with no password).

When specifying the URL for the Administration Console, use the port number for the domain to be administered. The format for starting the Administration Console in a web browser is `http://hostname:port`. For example:

`http://kindness.example.com:4848`

If the Administration Console is running on the host where GlassFish Server was installed, specify `localhost` for the host name. For example:

`http://localhost:4848`

For Microsoft Windows, an alternate way to start the GlassFish Server Administration Console is by using the Start menu.

You can display the help material for a page in the Administration Console by clicking the Help button on the page. The initial help page describes the functions and fields of the page itself. Associated task instructions can be accessed on additional pages by clicking a link in the See Also list.

asadmin Utility

The `asadmin` utility is a command-line tool that runs subcommands for identifying the operation or task that you want to perform. You can run `asadmin` subcommands either from a command prompt or from a script. Running `asadmin` subcommands from a script is helpful for automating repetitive tasks. Basic information about how the `asadmin` utility works can be found in the `asadmin(1M)` help page. For instructions on using the `asadmin` utility, see [“Using the asadmin Utility” on page 53](#).

To issue an `asadmin` subcommand in the standard command shell (single mode), go to the `as-install/bin` directory and type the `asadmin` command followed by a subcommand. For example:

```
asadmin list-jdbc-resources
```

You can invoke multiple command mode (multimode) by typing `asadmin` at the command prompt, after which the `asadmin>` prompt is presented. The `asadmin` utility continues to accept subcommands until you exit multimode and return to the standard command shell. For example:

```
asadmin> list-jdbc-resources
```

You can display a help page for any `asadmin` subcommand by typing `help` before the subcommand name. For example:

```
asadmin> help restart-domain
```

or

```
asadmin help restart-domain
```

A collection of the `asadmin` help pages is available in HTML and PDF format in the *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual*.

REST Interfaces

GlassFish Server provides representational state transfer (REST) interfaces to enable you to access monitoring and configuration data for GlassFish Server, including data that is provided by newly installed add-on components. For more information, see [“Using REST Interfaces to Administer GlassFish Server” on page 67](#).

Update Tool

GlassFish Server provides a set of image packaging system (IPS) tools for updating software on a deployed GlassFish Server. Typical updates include new releases of GlassFish Server, and new or revised releases of GlassFish Server add-on components or modules.

- The Update Tool graphical utility can either be run in the Administration Console, or invoked from the command line by using the `updatetool` command. You can use either tool to add components. However, to update or remove existing components, you must use the standalone version. Instructions for using the graphical versions of the Update Tool are contained in the Administration Console online help and the standalone Update Tool online help.
- The `pkg` command is the command-line version of Update Tool. Instructions for using the `pkg` command with add-on components are contained in [Chapter 10, “Extending and Updating GlassFish Server.”](#)

Two distributions are supported for GlassFish Server: the Web Profile and the Full Platform. After installation, you can view the modules on your system by using the graphical Update Tool or the `pkg` command.

Note – If you chose the Web Profile, you can change to the Full Platform by selecting the comparable Full Platform package in Update Tool. All dependent modules are automatically added.

You can add and delete individual modules from a distribution, but such configurations are not supported.

If you need information on upgrading your domain configuration data to work with a new version of GlassFish Server, see *GlassFish Server Open Source Edition 3.1 Upgrade Guide*.

OSGi Module Management Subsystem

The OSGi module management subsystem that is provided with GlassFish Server is the [Apache Felix OSGi framework](#). To administer this framework, use either of the following tools:

- [Apache Felix Gogo](#) remote shell, which is provided with GlassFish Server. This shell uses the Felix Gogo shell service to interact with the OSGi module management subsystem.
- GlassFish OSGi Administration Console, which is available as an add-on component for GlassFish Server or from the Maven GlassFish repository. The GlassFish OSGi Administration Console is a customized version of the [Apache Felix Web Console](#).

These tools enable you to perform administrative tasks on OSGi bundles such as:

- Browsing installed OSGi bundles

- Viewing the headers of installed OSGi bundles
- Installing OSGi bundles
- Controlling the life cycle of installed bundles

▼ To Enable the Apache Felix Gogo Remote Shell in GlassFish Server 3.1

By default, the Apache Felix Gogo remote shell in GlassFish Server is disabled. Before using the shell to administer OSGi bundles in GlassFish Server, you must enable the shell.

In GlassFish Server 3.1, enabling the Apache Felix Gogo remote shell in GlassFish Server involves adding the following OSGi bundles to the list of bundles that the system property `org.glassfish.additionalOSGiBundlesToStart` specifies.

- `org.apache.felix.shell.remote`
- `org.apache.felix.fileinstall`

- 1 Ensure that the DAS is running.
- 2 Remove all existing OSGi bundles from the list that the system property `org.glassfish.additionalOSGiBundlesToStart` specifies in the following named configurations:

- `server-config`
- `default-config`

For each named configuration, type the following command:

```
asadmin> asadmin delete-jvm-options --target config
-Dorg.glassfish.additionalOSGiBundlesToStart="org.apache.felix.shell,
org.apache.felix.gogo.runtime,org.apache.felix.gogo.shell,
org.apache.felix.gogo.command"
```

config

The configuration in which you are modifying the system property, which is either `server-config` or `default-config`.

- 3 Add all required OSGi bundles to the list that the system property `org.glassfish.additionalOSGiBundlesToStart` specifies in the following named configurations:

- `server-config`
- `default-config`

For each named configuration, type the following command:

```
asadmin create-jvm-options --target config
-Dorg.glassfish.additionalOSGiBundlesToStart="org.apache.felix.shell,
org.apache.felix.gogo.runtime,org.apache.felix.gogo.shell,
org.apache.felix.gogo.command,org.apache.felix.shell.remote,
org.apache.felix.fileinstall"
```

config

The configuration in which you are modifying the system property, which is either `server-config` or `default-config`.

4 Restart the DAS.

For instructions, see [“To Restart a Domain” on page 116](#).

▼ **To Enable the Apache Felix Gogo Remote Shell in GlassFish Server 3.1.1 and Later**

By default, the Apache Felix Gogo remote shell in GlassFish Server is disabled. Before using the shell to administer OSGi bundles in GlassFish Server, you must enable the shell.

In GlassFish Server 3.1.1 and later, enabling the Apache Felix Gogo remote shell in GlassFish Server involves adding the OSGi bundle `org.apache.felix.shell.remote` to the list of bundles that the Felix configuration property `optional.bundles` specifies.

1 Edit the `as-install/osgi/felix/conf/config.properties` file:

Insert the following line to the value of the `optional.bundles` property just before the line for the `org.apache.felix.fileinstall` bundle:

```
${com.sun.aas.installRootURI}modules/org.apache.felix.shell.remote.jar \
```

2 If the domain includes clustered or standalone instances on remote hosts, perform Step 1 on each remote host.

3 Restart the server.

For instructions, see [“To Restart a Domain” on page 116](#).

▼ **To Start the Apache Felix Gogo Remote Shell**

The Apache Felix Gogo remote shell is accessible to telnet clients from anywhere in the network.

1 Ensure that the DAS is running.

2 Connect to the Apache Felix Gogo remote shell through the telnet service by using the `telnet(1)` command as follows:

```
telnet host felix-remote-shell-port
```

host

The host where the DAS is running.

felix-remote-shell-port

The port for connecting to the Apache Felix Gogo remote shell through the telnet service. GlassFish Server is preconfigured to use port 6666 for this purpose.

To see a list of the commands that are available in the Apache Felix Gogo remote shell, type `help` at the prompt for Apache Felix Gogo remote shell.

Example 1–3 Connecting to the Apache Felix Gogo Remote Shell

This example connects to the Apache Felix Gogo remote shell for a domain that is running on the local host and that uses the preconfigured port for connecting to this shell through the telnet service.

```
telnet localhost 6666
```

After the connection is established, the following information is displayed:

```
Connected to localhost.
Escape character is '^'.

-----
Welcome to Apache Felix Gogo

g!
```

Example 1–4 Listing All Installed OSGi Bundles

This example runs the Felix Remote Shell Command `lb` without any arguments to list all installed OSGi bundles. For better readability, some bundles that would be listed by this example are not shown.

```
g! lb
START LEVEL 1
  ID|State      |Level|Name
  0|Active      | 0|System Bundle (3.0.8)
  1|Active      | 1|jaxb-api (2.2.2)
  2|Active      | 1|Metro Web Services API OSGi Bundle (2.1.0)
  3|Active      | 1|javax.annotation API v.1.1 (3.1.0)
  4|Active      | 1|HK2 OSGi Main Bundle (1.1.0)
  5|Resolved    | 1|Cluster SSH Provisioning (3.1.0)
  6|Resolved    | 1|woodstox (0.0.0)
  7|Resolved    | 1|Web container and GUI plug-in common classes (3.1.0)
  8|Resolved    | 1|javax.resource API v.1.6 (3.1.0)
  9|Active      | 1|GlassFish ha-shoal-cache-bootstrap (3.1.0)
 10|Installed   | 1|Admin Console JDBC Plugin (3.1.0)
...
 248|Active      | 1|GlassFish JPA Support (rfc #143) for OSGi Bundles (3.1.0)
 249|Active      | 1|GlassFish JDBC Support (rfc #122) for OSGi Bundles (3.1.0)
 250|Active      | 1|Apache Felix EventAdmin (1.2.8)
 251|Active      | 1|GlassFish EJB Container for OSGi Enabled EJB Applications
(3.1.0)
g!
```

Example 1–5 Determining the Services That an OSGi Bundle Provides

This example runs the Felix Remote Shell Command `inspect` with the `service` option and the `capability` option to determine the services that OSGi bundle 251 provides.

```
g! inspect service capability 251
GlassFish EJB Container for OSGi Enabled EJB Applications (251) provides services:
-----
objectClass = org.glassfish.osgijavaeebase.Extender
service.id = 68
----
objectClass = org.glassfish.osgijavaeebase.OSGiDeployer
service.id = 69
service.ranking = -2147483648
```

▼ To Install and Start the GlassFish OSGi Web Console

The GlassFish OSGi Web Console is available as follows:

- As an add-on component for GlassFish Server
- As a set of files from the [GlassFish Maven repository](http://maven.glassfish.org/content/groups/glassfish/org/glassfish/packager/glassfish-osgi-http/3.1/) (<http://maven.glassfish.org/content/groups/glassfish/org/glassfish/packager/glassfish-osgi-http/3.1/>)

1 Download and install the GlassFish OSGi Web Console.

- If you are obtaining the console as an add-on component, install the GlassFish OSGi Admin Console component.

For information about tools for installing add-on components, see [Chapter 10, “Extending and Updating GlassFish Server.”](#)

- If you are obtaining the console from the Maven repository, download and unzip the required files.
 - a. Download the following files to the parent of the `glassfish3` directory of your GlassFish Server installation.
 - `glassfish-osgi-http-3.1.zip` (<http://maven.glassfish.org/content/groups/glassfish/org/glassfish/packager/glassfish-osgi-http/3.1/glassfish-osgi-http-3.1.zip>)
 - `glassfish-osgi-gui-3.1.zip` (<http://maven.glassfish.org/content/groups/glassfish/org/glassfish/packager/glassfish-osgi-gui/3.1/glassfish-osgi-gui-3.1.zip>)

b. Unzip the files that you downloaded.

The contents of the files are added to the *as-install/modules/autostart* directory of your GlassFish Server installation.

The changes are applied automatically without restarting the DAS.

2 Start the GlassFish OSGi Web Console.

- a. Ensure that the DAS is running.

b. In a web browser, open the following location:**`http://host:http-port/osgi/system/console/`***host*

The host where the DAS is running.

http-port

The port on which GlassFish Server listens for HTTP requests. The default is 8080.

For example, if the DAS is running on the local host and GlassFish Server listens for HTTP requests on the default port, open the following location:

`http://localhost:8080/osgi/system/console/`**c. When prompted, provide the user name and password of the administrative user of the GlassFish OSGi Web Console.**

The user name and password of this user are both preset to admin.

keytool Utility

The `keytool` utility is used to set up and work with Java Security Socket Extension (JSSE) digital certificates. See “Administering JSSE Certificates” in *GlassFish Server Open Source Edition 3.1 Security Guide* for instructions on using `keytool`.

Java Monitoring and Management Console (JConsole)

Java SE provides tools to connect to an MBean server and view the MBeans that are registered with the server. JConsole is one such popular JMX Connector Client and is available as part of the standard Java SE distribution. For instructions on implementing JConsole in the GlassFish Server environment, see “[Configuring JConsole to View GlassFish Server Monitoring Data](#)” on [page 208](#).

Instructions for Administering GlassFish Server

Information and instructions on performing most of the administration tasks from the command line are provided in this document and in the `asadmin` utility help pages. For instructions on accessing `asadmin` online help, see “[To Display Help Information for the asadmin Utility or a Subcommand](#)” on [page 56](#)).

Information and instructions for accomplishing the tasks by using the Administration Console are contained in the Administration Console online help.

Note – Instructions written for the GlassFish Server tools use standard UNIX® forward slashes (/) for directory path separators in commands and file names. If you are running GlassFish Server on a Microsoft Windows system, use backslashes (\) instead. For example:

- UNIX: *as-install/bin/asadmin*
 - Windows: *as-install\bin\asadmin*
-

The following additional documents address specific administration areas:

- Installing GlassFish Server software; updating add-on components using the Update Tool
GlassFish Server Open Source Edition 3.1 Installation Guide
- Verifying and deploying applications
GlassFish Server Open Source Edition 3.1 Application Deployment Guide
- Diagnosing and resolving problems
GlassFish Server Open Source Edition 3.1 Troubleshooting Guide

PART I

Runtime Administration

General Administration

This chapter provides instructions for performing general administration tasks in the GlassFish Server Open Source Edition 3.1 environment by using the `asadmin` command-line utility.

The following topics are addressed here:

- [“Using the `asadmin` Utility” on page 53](#)
- [“Administering System Properties” on page 60](#)
- [“Administering Resources” on page 62](#)
- [“Listing Various System Elements” on page 63](#)
- [“Using REST Interfaces to Administer GlassFish Server” on page 67](#)

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

Using the `asadmin` Utility

Use the `asadmin` utility to perform administrative tasks for GlassFish Server from the command line or from a script. You can use this utility instead of the Administration Console interface.

The following topics are addressed here:

- [“Path to the `asadmin` Utility” on page 54](#)
- [“`asadmin` Utility Syntax” on page 54](#)
- [“To Run an `asadmin` Utility Subcommand in Single Mode” on page 55](#)
- [“To Display Help Information for the `asadmin` Utility or a Subcommand” on page 56](#)
- [“To Start a Multimode Session” on page 57](#)
- [“To End a Multimode Session” on page 58](#)
- [“To Run a Set of `asadmin` Subcommands From a File” on page 59](#)

Path to the asadmin Utility

The asadmin utility is located in the *as-install/bin* directory. To run the asadmin utility without specifying the path, ensure that this directory is in your path.

asadmin Utility Syntax

The syntax for running the asadmin utility is as follows:

```
asadmin [asadmin-util-options] [subcommand [subcommand-options] [operands]]
```

The replaceable items in this syntax are described in the subsections that follow. For full details of this syntax, see the asadmin(1M) help page.

Subcommands of the asadmin Utility

The *subcommand* identifies the operation or task that you are performing. Subcommands are case-sensitive. Each subcommand is either a local subcommand or a remote subcommand.

- A *local subcommand* can be run without a running domain administration server (DAS). However, to run the subcommand and have access to the installation directory and the domain directory, the user must be logged in to the machine that hosts the domain.
- A *remote subcommand* is always run by connecting to a DAS and running the subcommand there. A running DAS is required.

For a list of the subcommands for this release of GlassFish Server, see Section 1 of *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual*.

asadmin Utility Options and Subcommand Options

Options control the behavior of the asadmin utility and its subcommands. Options are case-sensitive.

The asadmin utility has the following types of options:

- **asadmin utility options.** These options control the behavior of the asadmin utility, not the subcommand. The asadmin utility options may precede or follow the subcommand, but asadmin utility options after the subcommand are deprecated. All asadmin utility options must either precede or follow the subcommand. If asadmin utility options are specified both before and after the subcommand, an error occurs. For a description of the asadmin utility options, see the asadmin(1M) help page.
- **Subcommand Options.** These options control the behavior of the subcommand, not the asadmin utility. Subcommand options must follow the subcommand. For a description of a subcommand's options, see the entry for the subcommand in *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual*.

Note – Not all subcommand options are supported for this release of GlassFish Server. If you specify an unsupported option, a syntax error does not occur. Instead, the command runs successfully and the unsupported option is silently ignored.

A subcommand option may have the same name as an `asadmin` utility option, but the effects of the two options are different.

Options have a long form and a short form.

- The short form of an option has a single dash (-) followed by a single character.
- The long form of an option has two dashes (- -) followed by an option word.

For example, the short form and the long form of the option for specifying terse output are as follows:

- Short form: `-t`
- Long form: `--terse`

Most options require argument values, except Boolean options, which toggle to enable or disable a feature.

Operands of `asadmin` Utility Subcommands

Operands specify the items on which the subcommand is to act. Operands must follow the argument values of subcommand options, and are set off by a space, a tab, or double dashes (- -). The `asadmin` utility treats anything that follows the subcommand options and their values as an operand.

▼ To Run an `asadmin` Utility Subcommand in Single Mode

In single mode, you must type a separate `asadmin` command for each subcommand that you want to use. After the subcommand has run, you are returned to the operating system's command shell. Any `asadmin` utility options must be specified in each separate `asadmin` command that you run. If you require the same `asadmin` utility options for multiple subcommands, use the `asadmin` utility in multimode. For more information, see [“To Start a Multimode Session” on page 57](#).

- **In the operating system's command shell, run the `asadmin` utility, specifying the subcommand.**
If necessary, also specify any required `asadmin` utility options, subcommand options, and operands.

Example 2-1 Running an asadmin Utility Subcommand in Single Mode

This example runs the `list-applications(1)` subcommand in single mode. In this example, the default values for all options are used.

The example shows that the application `hello` is deployed on the local host.

```
asadmin list-applications
hello <web>
Command list-applications executed successfully.
```

Example 2-2 Specifying an asadmin Utility Option With a Subcommand in Single Mode

This example specifies the `--host` asadmin utility option with the `list-applications` subcommand in single mode. In this example, the DAS is running on the host `srvr1.example.com`.

The example shows that the applications `basic-ezcomp`, `scrumtoys`, `ejb31-war`, and `automatic-timer-ejb` are deployed on the host `srvr1.example.com`.

```
asadmin --host srvr1.example.com list-applications
basic-ezcomp <web>
scrumtoys <web>
ejb31-war <ejb, web>
automatic-timer-ejb <ejb>
Command list-applications executed successfully.
```

Example 2-3 Specifying an asadmin Utility Option and a Subcommand Option in Single Mode

This example specifies the `--host` asadmin utility option and the `--type` subcommand option with the `list-applications` subcommand in single mode. In this example, the DAS is running on the host `srvr1.example.com` and applications of type `web` are to be listed.

```
asadmin --host srvr1.example.com list-applications --type web
basic-ezcomp <web>
scrumtoys <web>
ejb31-war <ejb, web>
Command list-applications executed successfully.
```

▼ To Display Help Information for the asadmin Utility or a Subcommand

GlassFish Server provides help information about the syntax, purpose, and options of the `asadmin` utility and its subcommands. This help information is written in the style of UNIX platform man pages. This help information is also available in *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual*.

- 1 **If you are displaying help information for a remote subcommand, ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Specify the subcommand of interest as the operand of the `help` subcommand.**
If you run the `help` subcommand without an operand, help information for the `asadmin` utility is displayed.

Example 2-4 Displaying Help Information for the `asadmin` Utility

This example displays the help information for the `asadmin` utility.

```
asadmin help
```

Example 2-5 Displaying Help Information for an `asadmin` Utility Subcommand

This example displays the help information for the `create-jdbc-resource` subcommand.

```
asadmin help create-jdbc-resource
```

See Also To display the available subcommands, use the `list-commands(1)` subcommand. Local subcommands are displayed before remote subcommands. If the server is not running, only local subcommands are displayed.

▼ To Start a Multimode Session

The `asadmin` utility can be used in multiple command mode, or *multimode*. In multimode, you run the `asadmin` utility once to start a multimode session. During the session, the `asadmin` utility continues to accept subcommands until you end the session and return to the operating system's command shell. Any `asadmin` utility options that you set for your multimode session are used for all subsequent subcommands in the session.

Note – Starting a multimode session does *not* require a running DAS.

- **Do one of the following:**
 - **Run the `asadmin` utility without a subcommand.**
 - **Use the `multimode(1)` subcommand.**

If necessary, also specify any `asadmin` utility options that will apply throughout the multimode session.

In a multimode session, the `asadmin>` prompt is displayed on the command line. You can now type `asadmin` subcommands at this prompt to administer GlassFish Server.

Example 2-6 Starting a Multimode Session With `asadmin` Utility Options

This example starts a multimode session in which the `asadmin` utility options `--user` and `--passwordfile` are set for the session.

```
asadmin --user admin1 --passwordfile pwd.txt multimode
```

Example 2-7 Starting a Multimode Session by Using the `multimode` Subcommand

This example uses the `multimode` subcommand to start a multimode session in which the default `asadmin` utility options are used.

```
asadmin multimode
```

The `asadmin>` prompt is displayed on the command line.

Example 2-8 Running a Subcommand in a Multimode Session

This example starts a multimode session and runs the `list-domains` subcommand in the session.

```
asadmin
Enter commands one per "line", ^D to quit
asadmin> list-domains
Name: domain1 Status: Running
Command list-domains executed successfully.
asadmin>
```

More Information Starting a Multimode Session From Within an Existing Multimode Session

You can start a multimode session from within an existing session by running the `multimode` subcommand from within the existing session. After you end the second multimode session, you return to your original multimode session.

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help multimode` at the command line.

▼ To End a Multimode Session

- At the `asadmin>` prompt, type one of the following commands or key combinations:
 - `exit`
 - `quit`

- UNIX and Linux systems: Ctrl-D
- Windows systems: Ctrl-Z



Caution – Do *not* type Ctrl-C to end a multimode session. If a domain or GlassFish Server instance is started from the multimode session, typing Ctrl-C kills the domain or instance process.

You are returned to the operating system's command shell and the `asadmin>` prompt is no longer displayed. If the `asadmin>` prompt is still displayed, you might have opened a multimode session within a multimode session. In this situation, repeat this procedure to end the remaining multimode session.

▼ To Run a Set of asadmin Subcommands From a File

Running a set of `asadmin` subcommands from a file enables you to automate repetitive tasks.

- 1 **Create a plain text file that contains the sequence of subcommands that you want to run.**
- 2 **Run the `multimode(1)` subcommand, specifying the file that you created.**

If necessary, also specify any `asadmin` utility options that are required to enable subcommands in the file to run.

Example 2–9 Running a Set of asadmin Subcommands From a File

This example contains the following:

- A listing of a file that is named `commands_file.txt`, which contains a sequence of `asadmin` subcommands
- The command to run the subcommands in the file `commands_file.txt`

The `commands_file.txt` file contains the `asadmin` utility subcommands to perform the following sequence of operations:

1. Creating the domain `customdomain`
2. Starting the domain `customdomain`
3. Listing all available subcommands
4. Stopping the domain `customdomain`
5. Deleting the domain `customdomain`

The content of the `commands_file.txt` file is as follows:

```
create-domain --portbase 9000 customdomain
start-domain customdomain
list-commands
stop-domain customdomain
delete-domain customdomain
```

This example runs the sequence of subcommands in the `commands_file.txt` file. Because the `--portbase` option is specified for the `create-domain` subcommand in the file, the `--port` `asadmin` utility option must also be set.

```
asadmin --port 9048 multimode --file commands_file.txt
```

See Also For more information about the subcommands in the preceding example, see the following help pages:

- `create-domain(1)`
- `delete-domain(1)`
- `list-commands(1)`
- `multimode(1)`
- `start-domain(1)`
- `stop-domain(1)`

Administering System Properties

Shared server instances will often need to override attributes defined in their referenced configuration. Any configuration attribute can be overridden through a system property of the corresponding name.

The following topics are addressed here:

- [“To Create System Properties” on page 60](#)
- [“To List System Properties” on page 61](#)
- [“To Delete a System Property” on page 61](#)

▼ To Create System Properties

Use the `create-system-properties` subcommand in remote mode to create or update one or more system properties of the domain or configuration. Any configuration attribute can be overwritten through a system property of the corresponding name.

- 1 Ensure that the server is running.**
Remote subcommands require a running server.
- 2 Create system properties by using the `create-system-properties(1)` subcommand.**
Information about properties for the subcommand is included in this help page.

Example 2–10 Creating a System Property

This example creates a system property associated with `http-listener-port=1088` on `localhost`.

```
asadmin> create-system-properties http-listener-port=1088  
Command create-system-properties executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-system-properties` at the command line.

▼ To List System Properties

Use the `list-system-properties` subcommand in remote mode to list the system properties that apply to a domain or configuration.

- 1 Ensure that the server is running.**

Remote subcommands require a running server.

- 2 List system properties by using the `list-system-properties(1)` subcommand.**

The existing system properties are displayed, including predefined properties such as `HTTP_LISTENER_PORT` and `HTTP_SSL_LISTENER_PORT`.

Example 2–11 Listing System Properties

This example lists the system properties on host `localhost`.

```
asadmin> list-system-properties  
http-listener-port=1088  
Command list-system-properties executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-system-properties` at the command line.

▼ To Delete a System Property

Use the `delete-system-property` subcommand in remote mode to delete system properties.

- 1 Ensure that the server is running.**

Remote subcommands require a running server.

- 2 List the existing system properties by using the `list-system-properties(1)` subcommand.**

- 3 Delete the system property by using the `delete-system-property(1)` subcommand.**

- 4 If necessary, notify users that the system property has been deleted.**

Example 2–12 Deleting a System Property

This example deletes a system property named `http-listener-port` from `localhost`.

```
asadmin> delete-system-property http-listener-port
Command delete-system-property executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-system-property` at the command line.

Administering Resources

This section contains instructions for integrating resources into the GlassFish Server environment. Information about administering specific resources, such as JDBC, is contained in other chapters.

▼ To Add Resources From an XML File

Use the `add-resources` subcommand in remote mode to create the resources named in the specified XML file. The following resources are supported: JDBC connection pool and resource, JMS, JNDI, and JavaMail resources, custom resource, connector resource and work security map, admin object, and resource adapter configuration.

The XML file must reside in the `as-install/domains/domain1/config` directory. If you specify a relative path or simply provide the name of the XML file, this subcommand will prepend `as-install/domains/domain1/config` to this operand.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Add resources from an XML file by using the `add-resources(1)` subcommand.

Information about properties for the subcommand is included in this help page.

3 Restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

Example 2–13 Adding Resources

This example creates resources using the contents of the `resource.xml` file on `localhost`.

```
asadmin> add-resources c:\tmp\resource.xml
Command : JDBC resource jdbc1 created successfully.
Command : JDBC connection pool poolA created successfully.
Command add-resources executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help add-resources` at the command line.

Listing Various System Elements

The following topics are addressed here:

- “To Display the GlassFish Server Version” on page 63
- “To List Applications” on page 63
- “To List Containers” on page 64
- “To List Modules” on page 65
- “To List Subcommands” on page 66
- “To List Timers” on page 66
- “To Show Component Status” on page 67

▼ To Display the GlassFish Server Version

Use the `version` subcommand in remote mode to display information about the GlassFish Server version for a particular server. If the subcommand cannot communicate with the server by using the specified login (user/password) and target (host/port) information, then the local version is displayed along with a warning message.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Display the version by using the `version(1)` subcommand.**

Example 2–14 Displaying Version Information

This example displays the version of GlassFish Server on the local host.

```
asadmin> version
Version = Oracle GlassFish Server 3.0.1 (build 19)
Command version executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help version` at the command line.

▼ To List Applications

Use the `list-applications` subcommand in remote mode to list the deployed Java applications. If the `--type` option is not specified, all applications are listed.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List applications by using the `list-applications(1)` subcommand.**

Example 2–15 Listing Applications

This example lists the web applications on localhost.

```
asadmin> list-applications --type web
hellojsp <web>
Command list-applications executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-applications` at the command line.

▼ To List Containers

Use the `list-containers` subcommand in remote mode to list application containers.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List containers by using the `list-containers(1)` subcommand.**

Example 2–16 Listing Containers

This example lists the containers on localhost.

```
asadmin> list-containers
List all known application containers
Container : grizzly
Container : ejb
Container : webservices
Container : ear
Container : appclient
Container : connector
Container : jpa
Container : web
Container : security
Container : webbeans
Command list-containers executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-containers` at the command line.

▼ To List Modules

Use the `list-modules` subcommand in remote mode to list the modules that are accessible to the GlassFish Server module subsystem. The status of each module is included. Possible statuses include `NEW` and `READY`.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List modules by using the `list-modules(1)` subcommand.

Example 2–17 Listing Modules

This example lists the accessible modules.

```
asadmin> list-modules
```

Information similar to the following is displayed (partial output):

```
List Of Modules
Module : org.glassfish.web.jstl-connector:10.0.0.b28
  properties=(visibility=public,State=READY,Sticky=true)
  Module Characteristics : List of Jars implementing the module
    Jar : file:/C:/Preview/v3_Preview_release/distributions/web/target/glassfish/modules/web/jstl-connector.jar
  Module Characteristics : List of imported modules
  Module Characteristics : Provides to following services
Module : org.glassfish.admingui.console-common:10.0.0.b28
  properties=(visibility=public,State=NEW,Sticky=true)
Module : org.glassfish.admin.launcher:10.0.0.b28
  properties=(visibility=public,State=NEW,Sticky=true)
Module : org.glassfish.external.commons-codec-repackaged:10.0.0.b28
  properties=(visibility=public,State=NEW,Sticky=true)
Module : com.sun.enterprise.tiger-types-osgi:0.3.32.Preview-b28
  properties=(visibility=public,State=READY,Sticky=true)
  Module Characteristics : List of imported modules
  Module Characteristics : Provides to following services
  Module Characteristics : List of Jars implementing the module
    Jar : file:/C:/Preview/v3_Preview_release/distributions/web/target/glassfish/modules/tiger-types-osgi.jar.
...
Command list-modules executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-modules` at the command line.

▼ To List Subcommands

Use the `list-commands` subcommand in remote mode to list the deployed `asadmin` subcommands. You can specify that only remote subcommands or only local subcommands are listed. By default, this subcommand displays a list of local subcommands followed by a list of remote subcommands.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List subcommands by using the `list-commands(1)` subcommand.**

Example 2-18 Listing Subcommands

This example lists only local subcommands.

```
asadmin> list-commands --localonly
create-domain
delete-domain
list-commands
list-domains
login
monitor
start-database
start-domain
stop-domain
stop-database
version
Command list-commands executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-commands` at the command line.

▼ To List Timers

The timer service is a persistent and transactional notification service that is provided by the enterprise bean container and is used to schedule notifications or events used by enterprise beans. All enterprise beans except stateful session beans can receive notifications from the timer service. Persistent timers set by the service are not destroyed when the server is shut down or restarted.

Use the `list-timers` subcommand in remote mode to list the persistent timers owned by a specific server instance. You can use this information to decide whether to do a timer migration, or to verify that a migration has been completed successfully.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.

2 List timers by using the `list-timers(1)` subcommand.

Example 2–19 Listing Timers

This example lists the timers in a particular standalone server instance. There is one currently active timer set.

```
asadmin> list-timers server
1
The list-timers command was executed successfully.
```

▼ To Show Component Status

Use the `show-component-status` subcommand in remote mode to get the status (either enabled or disabled) of the specified deployed component.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Show component status by using the `show-component-status(1)` subcommand.**

Example 2–20 Showing Status of a Component

This example shows the status of the MEjbApp component.

```
asadmin> show-component-status MEjbApp
Status of MEjbApp is enabled
Command show-component-status executed successfully.
```

Using REST Interfaces to Administer GlassFish Server

GlassFish Server provides representational state transfer (REST) interfaces to enable you to access monitoring and configuration data for GlassFish Server, including data that is provided by newly installed add-on components.

You can access the GlassFish Server REST interfaces through client applications such as:

- Web browsers
- `cURL` (<http://curl.haxx.se/>)
- `GNU Wget` (<http://www.gnu.org/software/wget/>)

You can also use the GlassFish Server REST interfaces in REST client applications that are developed in languages such as:

- JavaScript
- Ruby
- Perl
- Java
- JavaFX

The implementation of the GlassFish Server REST interfaces is based on [project Jersey](#). Project Jersey is the reference implementation of [Java Specification Request \(JSR\) 311: JAX-RS: The Java API for RESTful Web Services](#). Information about JSR 311 is also available from the [JSR 311 project home page](#).

The following topics are addressed here:

- “Using REST URLs to Administer GlassFish Server” on page 68
- “Using REST Resource Methods to Administer GlassFish Server” on page 71
- “Resources for `asadmin` Subcommands That Perform Non-CRUD Operations” on page 80
- “Securing GlassFish Server REST Interfaces” on page 81
- “Formats for Resource Representation of Configuration Objects” on page 82
- “Formats for Resource Representation of Monitoring Objects” on page 92
- “Formats for Resource Representation of Log File Details” on page 100
- “Supported Content Types in Requests to REST Resources” on page 104

Using REST URLs to Administer GlassFish Server

Each object in the configuration and monitoring object trees is represented as a REST resource that is accessible through an HTTP uniform resource locator (URL). Access to REST resources for GlassFish Server monitoring and configuration data requires a running DAS.

REST URLs to Resources for Configuration and Monitoring Objects

The formats of the URLs to resources that represent objects in the configuration and monitoring object trees are as follows:

- **Configuration:** `http://host:port/management/domain/path`
- **Monitoring:** `http://host:port/monitoring/domain/path`

The replaceable items in these URLs are as follows:

host

The host where the DAS is running.

port

The HTTP port or HTTPS port for administration.

path

The path to the object. The path is the dotted name of the object in which each dot (.) is replaced with a slash (/).

Note – The path to a GlassFish Server instance is `servers/server/instance-name`, where *instance-name* is the name of the instance. For the DAS, *instance-name* is `server` and the path is `servers/server/server`.

For more information, see the following documentation:

- The dotted-names(5ASC) help page
- [“How the Monitoring Tree Structure Works” on page 170](#)
- [“How Dotted Names Work for Configuration” on page 37](#)

If the URL to a REST resource for GlassFish Server monitoring or configuration data is opened in a web browser, the browser displays a web page that contains the following information about the resource:

- A list of the attributes of the resource and their values. If the resource represents an object in the configuration tree, these attributes are presented in an HTML form that you can use to update the resource. Attributes of a resource for an object in the monitoring tree are read only.
- A list of hypertext links to the children of the resource. This list of links enables you to traverse the tree that contains the resource and to discover the all resources in the tree.
- A list of hypertext links to resources that represent `admin` subcommands for non-CRUD operations on the resource.

The following figure shows the web page for the REST resource for managing a domain.

FIGURE 2-1 Web Page for the REST Resource for Managing a Domain



The screenshot shows a web browser window with the address bar displaying `http://localhost:4848/management/domain/nodes/node/sj01`. The page title is "GlassFish REST Interface". Below the title, there is a section titled "Node Attributes" which contains a form with four input fields: "installDir:" with the value "/export/glassfish3", "nodeDir:" which is empty, "nodeHost:" with the value "sj01.example.com", and "type:" with the value "SSH". Below these fields is an "Update" button. Underneath the "Node Attributes" section is a section titled "Child Resources" which contains three links: [application-ref](#), [resource-ref](#), and [ssh-connector](#). At the bottom of the page is a section titled "Commands" which contains three links: [ping-node-ssh](#), [update-node-ssh](#), and [update-node-config](#).

REST URLs for Accessing the Log File

The server . log file of the DAS is represented as a child that is named view - log of the resource for managing the domain. A child of the resource for the server . log file represents the log file details

The formats of the URLs to resources that represent the log file are as follows:

- **Log file:** `http://host:port/management/domain/view-log`
- **Log file details:** `http://host:port/monitoring/domain/view-log/details`

The replaceable items in these URLs are as follows:

host

The host where the DAS is running.

port

The HTTP port or HTTPS port for administration.

You can use the optional `start` parameter in the URL to the resource for the log file to specify the number of characters at the start of the file to skip. For example, to skip 10,000 characters, specify the URL as `http://localhost:4848/management/domain/view-log?start=10000`. This example assumes that the DAS is running on the local host and uses the default port for administration.

The resource for the log file returns the HTTP header "X-Text-Append-Next", which contains the entire URL to pass to the GET method to return the changes since the last call. You can use this header in client applications to get all log entries that were added in particular interval. For example, by testing the value of the "X-Text-Append-Next" header in a client thread every 10 seconds, you can monitor the log entries that were added in the last 10 seconds.

Using REST Resource Methods to Administer GlassFish Server

The GlassFish Server REST interfaces support methods for accessing objects in the monitoring and configuration object trees.

The following table shows the REST methods for administering monitoring and configuration data and the tasks that you can perform with each method. These methods are HTTP 1.1 primitives. For the detailed specification of these primitives, see [Hypertext Transfer Protocol -- HTTP/1.1](http://www.w3.org/Protocols/rfc2616/rfc2616.html) (<http://www.w3.org/Protocols/rfc2616/rfc2616.html>).

TABLE 2-1 REST Resource Methods for Administering Monitoring and Configuration Data

Task	REST Method
Determine the methods and method parameters that an object in the tree supports	GET
Retrieve data for an object in the tree	GET
Add an object to the tree	POST
Update an object in the tree	POST
Delete an object from the tree	DELETE

Note – The GET determines the methods and method parameters that an object in the tree supports and provides additional information about the object. For details, see [“To Retrieve Data for an Object in the Tree” on page 73](#).

▼ To Determine the Methods and Method Parameters That an Object in the Tree Supports

The methods and method parameters that an object in the tree supports depend on the REST resource that represents the object:

- REST resources for monitoring support only the GET method.
- All REST resources for configuration support the GET method. However, only some REST resources for configuration also support the POST method and the DELETE method.

Before performing any operations on an object in the tree, determine the methods and method parameters that the object supports.

You can specify the format in which this information is presented. For more information, see [“Formats for Resource Representation of Configuration Objects” on page 82](#).

Note – Each POST method and DELETE method that a REST resource supports has an equivalent `asadmin` subcommand. The parameters of a POST method or a DELETE method correspond to the options of the method's equivalent `asadmin` subcommand. For information about the options of `asadmin` subcommand, see *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual*.

1 Ensure that the server is running.

Operations on REST resources for GlassFish Server data require a running server.

2 Use the GET method on the REST resource that represents the object.

The GET method returns the list of methods that the resource supports. For each method, the list of acceptable message parameters or the list of acceptable query parameters are returned.

Example 2–21 Determining the Methods and Method Parameters That an Object in the Tree Supports

This example uses the `cURL` utility to determine the methods and method parameters that the resource for the node `sj01` supports. The example uses the following options of the `cURL` utility:

- `-X` to specify that the GET method is used
- `-H` to specify that the resource is represented in JavaScript Object Notation (JSON)

In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The resource supports the GET method and the POST method.

Line breaks and white space are added to enhance readability.

```
curl -X GET -H "Accept: application/json" http://localhost:4848/management/domain/nodes/node/sj01
{
  "command": "Node",
  "exit_code": "SUCCESS",
  "extraProperties": {
    "commands": [
      { "path": "delete-node", "command": "delete-node", "method": "DELETE" },
      { "path": "update-node", "command": "update-node", "method": "POST" },
      { "path": "ping-node-ssh", "command": "ping-node-ssh", "method": "GET" },
      { "path": "update-node-ssh", "command": "update-node-ssh", "method": "POST" },
      { "path": "update-node-config", "command": "update-node-config", "method": "POST" }
    ],
    "methods": [
      { "name": "GET" },
      { "name": "POST", "messageParameters": {
        "installDir": { "optional": "true", "type": "string", "key": "false" },
        "nodeDir": { "optional": "true", "type": "string", "key": "false" },
        "nodeHost": { "optional": "true", "type": "string", "key": "false" },
        "type": { "optional": "true", "type": "string", "key": "false" }
      }
    ]
  },
  "entity": {
    "installDir": "\\export\\glassfish3",
    "name": "sj01",
    "nodeDir": null,
    "nodeHost": "sj01.example.com",
    "type": "SSH"
  },
  "childResources": {
    "application-ref": "https://localhost:4848/management/domain/nodes/node/sj01/application-ref",
    "resource-ref": "https://localhost:4848/management/domain/nodes/node/sj01/resource-ref",
    "ssh-connector": "https://localhost:4848/management/domain/nodes/node/sj01/ssh-connector"
  }
}
```

▼ To Retrieve Data for an Object in the Tree

Retrieving data for an object in the tree obtains the following information about the REST resource that represents the object:

- A list of the REST methods that the resource supports
- A list of the attributes of the resource and their values
- A list of URLs to the children of the resource

You can specify the format in which this information is presented. For more information, see [“Formats for Resource Representation of Configuration Objects” on page 82](#).

1 Ensure that the server is running.

Operations on REST resources for GlassFish Server data require a running server.

2 Use the GET method on the REST resource that represents the object.**Example 2-22 Retrieving Data for an Object in the Tree**

This example uses the cURL utility to retrieve data for the resource for a the node `sj01`. The example uses the following options of the cURL utility:

- `-X` to specify that the GET method is used
- `-H` to specify that the resource is represented in JavaScript Object Notation (JSON)

In this example, the DAS is running on the local host and the HTTP port for administration is 4848.

Line breaks and white space are added to enhance readability.

```
curl -X GET -H "Accept: application/json" http://localhost:4848/management/domain/nodes/node/sj01
{
  "command": "Node",
  "exit_code": "SUCCESS",
  "extraProperties": {
    "commands": [
      { "path": "delete-node", "command": "delete-node", "method": "DELETE" },
      { "path": "update-node", "command": "update-node", "method": "POST" },
      { "path": "ping-node-ssh", "command": "ping-node-ssh", "method": "GET" },
      { "path": "update-node-ssh", "command": "update-node-ssh", "method": "POST" },
      { "path": "update-node-config", "command": "update-node-config", "method": "POST" }
    ],
    "methods": [
      { "name": "GET" },
      { "name": "POST", "messageParameters": {
        "installDir": { "optional": "true", "type": "string", "key": "false" },
        "nodeDir": { "optional": "true", "type": "string", "key": "false" },
        "nodeHost": { "optional": "true", "type": "string", "key": "false" },
        "type": { "optional": "true", "type": "string", "key": "false" }
      }
    ]
  }
},
  "entity": {
    "installDir": "\\export\\glassfish3",
    "name": "sj01",
    "nodeDir": null,
    "nodeHost":
      "sj01.example.com",
    "type": "SSH"
  },
  "childResources": {
    "application-ref":
      "https://localhost:4848/management/domain/nodes/node/sj01/application-ref",
    "resource-ref":
      "https://localhost:4848/management/domain/nodes/node/sj01/resource-ref",
    "ssh-connector":
  }
```

```

    "https://localhost:4848/management/domain/nodes/node/sj01/ssh-connector"
  }
}
}

```

▼ To Add an Object to the Tree

1 Ensure that the server is running.

Operations on REST resources for GlassFish Server data require a running server.

2 Determine the acceptable message parameters for the POST method of the resource that represents the parent of the object.

For information about how to perform this step, see [“To Determine the Methods and Method Parameters That an Object in the Tree Supports” on page 72](#).

3 Use the POST method on the REST resource that represents the parent of the object that you are adding.

4 Confirm that the object has been added.

Perform this step on the resource that represents the object that you have just added, *not* the parent. For information about how to perform this step, see [“To Retrieve Data for an Object in the Tree” on page 73](#).

Example 2–23 Adding an Object to the Tree

This example uses the cURL utility to add a JDBC resource object to the tree by creating a REST resource to represent the JDBC resource.

In this example, the DAS is running on the local host and the HTTP port for administration is 4848.

Line breaks are added to enhance readability.

1. This step determines the acceptable message parameters for the POST method of the resource jdbc-resource.

```

curl -X GET -H "Accept: application/json"
http://localhost:4848/management/domain/resources/jdbc-resource
{
  "command": "Jdbc-resource",
  "exit_code": "SUCCESS",
  "extraProperties": {
    "commands": [],
    "methods": [
      { "name": "GET" },
      { "name": "POST", "messageParameters": {
        "description": { "acceptableValues": "", "optional": "true", "type": "string", "defaultValue": "" },
        "enabled": { "acceptableValues": "", "optional": "true", "type": "boolean", "defaultValue": "true" },

```

```

    "id":{"acceptableValues":"","optional":"false","type":"string","defaultValue":""},
    "poolName":{"acceptableValues":"","optional":"false","type":"string","defaultValue":""},
    "property":{"acceptableValues":"","optional":"true","type":"string","defaultValue":""},
    "target":{"acceptableValues":"","optional":"true","type":"string","defaultValue":""}
  }
},
"childResources":{
  "jdbc\__TimerPool":
    "https://localhost:4848/management/domain/resources/jdbc-resource/jdbc%2F__TimerPool",
  "jdbc\__default":
    "https://localhost:4848/management/domain/resources/jdbc-resource/jdbc%2F__default"
}
}
}

```

2. This step adds a resource as a child of the jdbc-resource resource. The -d option of the cURL utility sets the required message parameters as follows:

- id is set to jdbc/myjdbcresource.
- connectionpoolid is set to DerbyPool.

```

curl -X POST -d id=jdbc/myjdbcresource -d id=poolName=DerbyPool
http://localhost:4848/management/domain/resources/jdbc-resource

```

3. This step confirms that the object has been added by retrieving data for the REST resource that represents the object.

```

curl -X GET -H "Accept: application/json"
http://localhost:4848/management/domain/resources/
jdbc-resource/jdbc%2Fmyjdbcresource
{
  "command":"Jdbc-resource",
  "exit_code":"SUCCESS",
  "extraProperties":{
    "commands":[],
    "methods":[
      {"name":"GET"},
      {"name":"POST","messageParameters":{
        "description":{"optional":"true","type":"string","key":"false"},
        "enabled":{"optional":"true","type":"boolean","defaultValue":"true","key":"false"},
        "jndiName":{"optional":"true","type":"string","key":"true"},
        "objectType":{"optional":"true","type":"string","defaultValue":"user","key":"false"},
        "poolName":{"optional":"true","type":"string","key":"false"}
      }
    ],
    {"name":"DELETE","messageParameters":{
      "target":{"acceptableValues":"","optional":"true","type":"string","defaultValue":""}
    }
  }
},
"childResources":{
  "property":
    "https://localhost:4848/management/domain/resources/jdbc-resource/jdbc%2Fmyjdbcresource/property"
}
}
}

```

▼ To Update an Object in the Tree

1 Ensure that the server is running.

Operations on REST resources for GlassFish Server data require a running server.

2 Determine the acceptable message parameters for the POST method of the resource that represents the object.

For information about how to perform this step, see [“To Determine the Methods and Method Parameters That an Object in the Tree Supports” on page 72.](#)

3 Use the POST method on the REST resource that represents the object that you are updating.

4 Confirm that the object has been updated.

For information about how to perform this step, see [“To Retrieve Data for an Object in the Tree” on page 73.](#)

Example 2-24 Updating an Object in the Tree

This example uses the cURL utility to update a JDBC resource in the tree by modifying the REST resource that represents the JDBC resource.

In this example, the DAS is running on the local host and the HTTP port for administration is 4848.

Line breaks are added to enhance readability.

1. This step determines the acceptable message parameters for the POST method of the resource `jdbc-myjdbcresource`.

```
curl -X OPTIONS -H "Accept: application/json"
http://localhost:4848/management/domain/resources/
jdbc-resource/jdbc-myjdbcresource
{
  "command": "Jdbc-resource",
  "exit_code": "SUCCESS",
  "extraProperties": {
    "commands": [],
    "methods": [
      {
        "name": "GET",
        {
          "name": "POST", "messageParameters": {
            "description": { "optional": "true", "type": "string", "key": "false" },
            "enabled": { "optional": "true", "type": "boolean", "defaultValue": "true", "key": "false" },
            "jndiName": { "optional": "true", "type": "string", "key": "true" },
            "objectType": { "optional": "true", "type": "string", "defaultValue": "user", "key": "false" },
            "poolName": { "optional": "true", "type": "string", "key": "false" }
          }
        }
      },
      {
        "name": "DELETE", "messageParameters": {
          "target": { "acceptableValues": "", "optional": "true", "type": "string", "defaultValue": "" }
        }
      }
    ]
  }
}
```

```
    }  
  },  
  "childResources":{  
    "property":  
      "https://localhost:4848/management/domain/resources/jdbc-resource/jdbc%2Fmyjdbcresource/property"  
    }  
  }  
}
```

2. This step updates the REST resource jdbc-myjdbcresource to disable the JDBC resource that jdbc-myjdbcresource represents. The -d option of the cURL utility sets the enabled message parameter to disabled.

```
curl -X POST -d "enabled=false"  
http://localhost:4848/management/domain/resources/  
jdbc-resource/jdbc%2Fmyjdbcresource
```

3. This step confirms that the object has been updated by retrieving data for the REST resource that represents the object.

```
curl -X GET -H "Accept: application/json"  
http://localhost:4848/management/domain/resources/  
jdbc-resource/jdbc%2Fmyjdbcresource  
{  
  "command": "Jdbc-resource",  
  "exit_code": "SUCCESS",  
  "extraProperties": {  
    "commands": [],  
    "methods": [  
      {  
        "name": "GET",  
        "name": "POST", "messageParameters": {  
          "description": { "optional": "true", "type": "string", "key": "false",  
            "enabled": { "optional": "true", "type": "boolean", "defaultValue": "true", "key": "false",  
              "jndiName": { "optional": "true", "type": "string", "key": "true",  
                "objectType": { "optional": "true", "type": "string", "defaultValue":  
                  "user", "key": "false",  
                    "poolName": { "optional": "true", "type": "string", "key": "false"}  
                }  
              }  
            }  
          },  
          {  
            "name": "DELETE", "messageParameters": {  
              "target": { "acceptableValues": "", "optional": "true", "type": "string", "defaultValue": "" }  
            }  
          }  
        ],  
        "entity": {  
          "description": null,  
          "enabled": "false",  
          "jndiName": "jdbc/myjdbcresource",  
          "objectType":  
            "user",  
            "poolName": "DerbyPool"  
        },  
        "childResources": {  
          "property":  
            "https://localhost:4848/management/domain/resources/jdbc-resource/  
            jdbc%2Fmyjdbcresource/property"  
          }  
        }  
      }  
    ]  
  }  
}
```

▼ To Delete an Object From the Tree

1 Ensure that the server is running.

Operations on REST resources for GlassFish Server data require a running server.

2 Confirm that the object can be deleted.

For information about how to perform this step, see [“To Determine the Methods and Method Parameters That an Object in the Tree Supports”](#) on page 72.

3 Confirm that the object has been deleted.

Perform this step on the resource that represents the parent of the object that you have just deleted. For information about how to perform this step, see [“To Retrieve Data for an Object in the Tree”](#) on page 73.

Example 2–25 Deleting an Object From the Tree

This example uses the cURL utility to delete a JDBC resource from the tree by deleting the REST resource that represents the JDBC resource.

In this example, the DAS is running on the local host and the HTTP port for administration is 4848.

Line breaks and white space are added to enhance readability.

1. This step confirms that the object can be deleted by retrieving the REST methods that the resource jdbc-myjdbcresource supports.

```
curl -X GET -H "Accept: application/json"
http://localhost:4848/management/domain/resources/
jdbc-resource/jdbc%2Fmyjdbcresource
{
  "command": "Jdbc-resource",
  "exit_code": "SUCCESS",
  "extraProperties": {
    "commands": [],
    "methods": [
      { "name": "GET" },
      { "name": "POST", "messageParameters": {
        "description": { "optional": "true", "type": "string", "key": "false" },
        "enabled": { "optional": "true", "type": "boolean", "defaultValue": "true", "key": "false" },
        "jndiName": { "optional": "true", "type": "string", "key": "true" },
        "objectType": { "optional": "true", "type": "string", "defaultValue": "user", "key": "false" },
        "poolName": { "optional": "true", "type": "string", "key": "false" }
      }
    },
    { "name": "DELETE", "messageParameters": {
      "target": { "acceptableValues": "", "optional": "true", "type": "string", "defaultValue": "" }
    }
  }
},
],
```

```

"childResources":{
  "property":
    "https://localhost:4848/management/domain/resources/jdbc-resource/
    jdbc%2Fmyjdbcresource/property"
}
}
}

```

2. This step deletes the jdbc/myjdbcresource resource.

```
curl -X DELETE http://localhost:4848/management/domain/resources/
jdbc-resource/jdbc%2Fmyjdbcresource
```

3. This step confirms that the object has been deleted by retrieving data for the REST resource that represents the parent of the object.

```

curl -X GET -H "Accept: application/json"
http://localhost:4848/management/domain/resources/jdbc-resource
{
  "command":"Jdbc-resource",
  "exit_code":"SUCCESS",
  "extraProperties":{"
    "commands":[],
    "methods":[
      {"name":"GET"},
      {"name":"POST","messageParameters":{"
        "description":{"acceptableValues":"","optional":"true","type":"string","defaultValue":""},
        "enabled":{"acceptableValues":"","optional":"true","type":"boolean","defaultValue":"true"},
        "id":{"acceptableValues":"","optional":"false","type":"string","defaultValue":""},
        "poolName":{"acceptableValues":"","optional":"false","type":"string","defaultValue":""},
        "property":{"acceptableValues":"","optional":"true","type":"string","defaultValue":""},
        "target":{"acceptableValues":"","optional":"true","type":"string","defaultValue":""}
      }}
    ]
  },
  "childResources":{"
    "jdbc/TimerPool":
      "https://localhost:4848/management/domain/resources/jdbc-resource/jdbc%2FTimerPool",
    "jdbc/default":
      "https://localhost:4848/management/domain/resources/jdbc-resource/jdbc%2Fdefault"
  }
}
}

```

Resources for asadmin Subcommands That Perform Non-CRUD Operations

The GlassFish Server REST interfaces also support operations other than create, read, update, and delete (CRUD) operations, for example:

- State management
- Queries
- Application deployment

These operations are supported through REST resources that represent the `asadmin` subcommands for performing these operations. Each resource is a child of the resource on which the operation is performed. The child resources do *not* represent objects in the configuration object tree.

For example, the resource that represents a node provides child resources for the following `asadmin` subcommands that perform non-CRUD operations on the node:

- `ping-node-ssh`
- `update-node-config`
- `update-node-ssh`

Securing GlassFish Server REST Interfaces

The GlassFish Server REST interfaces support the following authentication schemes for securing the REST interfaces:

- Basic authentication over a secure connection
- Authentication by using session tokens

When security is enabled, you must specify `https` as the protocol in the URLs to REST resources and provide a username and password.

Setting Up Basic Authentication Over a Secure Connection

Setting up basic authentication over a secure connection to secure GlassFish Server REST interfaces involves the following sequence of tasks:

1. Adding an `admin-realm` user to the `asadmin` user group
2. Enabling Secure Sockets Layer (SSL)

For information about how to perform these tasks from the command line, see the following documentation:

- “To Create an Authentication Realm” in *GlassFish Server Open Source Edition 3.1 Security Guide*
- “To Create a File User” in *GlassFish Server Open Source Edition 3.1 Security Guide*
- [“To Configure an HTTP Listener for SSL” on page 304](#)

For information about how to perform these tasks by using the Administration Console, see the following topics in the Administration Console online help:

- To Add a User to the Admin Realm
- To Edit SSL Settings for a Protocol

▼ To Secure REST Interfaces by Using Session Tokens

Basic authentication requires a REST client to cache a user's credentials to enable the client to pass the credentials with each request. If you require a REST client not to cache credentials, your client must use session tokens for authentication.

- 1 **Request a session token by using the GET method on the resource at `http://host:port/management/sessions`.**

GlassFish Server uses basic authentication to authenticate the client, generates a session token, and passes the token to the client.

- 2 **In each subsequent request that requires authentication, use the token to authenticate the client.**
 - a. **Create a cookie that is named `gfresttoken` the value of which is the token.**
 - b. **Send the cookie with the request.**
- 3 **When the token is no longer required, retire the token by using the DELETE method on the resource at `http://host:port/management/sessions/{tokenvalue}`.**

Note – If a client does not explicitly retire a token, the token is retired after 30 minutes of inactivity.

Formats for Resource Representation of Configuration Objects

The GlassFish Server REST interfaces represent resources for configuration objects in the following formats:

- JSON (<http://www.json.org/>)
- XML
- HTML

GlassFish Server enables you to specify the resource representation through the filename extension in the URL or through the HTTP header:

- To specify the resource representation through the filename extension in the URL, specify the appropriate extension as follows:
 - For JSON, specify the `.json` extension.
 - For XML, specify the `.xml` extension.
 - For HTML, omit the extension.

- How to specify the resource representation through the HTTP header depends on the client that you are using to access the resource. For example, if you are using the cURL utility, specify the resource representation through the `-H` option as follows:
 - For JSON, specify `-H "Accept: application/json"`.
 - For XML, specify `-H "Accept: application/xml"`.
 - For HTML, omit the `-H` option.

JSON Resource Representation for Configuration Objects

The general format for the JSON representation of a resource for a configuration object is as follows:

```
{
  "command": "resource",
  "exit_code": "code",
  "extraProperties": {
    "commands": [command-list],
    "methods": [method-list],
    "entity": {attributes},
    "childResources": {children}
  }
}
```

The replaceable items in this format are as follows:

resource

The name of the resource.

code

The result of the attempt to get the resource.

command-list

One or more metadata sets separated by a comma (,) that represent the `asadmin` subcommands for performing non—CRUD operations on the resource. For the format of each metadata set, see [“JSON Representation of a Command in a Command List” on page 84](#).

method-list

One or more metadata sets separated by a comma (,) that represent the methods that the resource supports. For the format of each metadata set, see [“JSON Representation of a Method in a Method List” on page 84](#).

attributes

Zero or more name-value pairs separated by a comma (,). Each name-value pair is specified as `"name": value`.

children

Zero or more child resources separated by a comma (,). Each child resource is specified as `"resource-name": "url"`.

resource-name

The name of the resource as displayed in client applications that access the parent of the resource.

url

The URL to the child resource.

JSON Representation of a Command in a Command List

The JSON representation of a command in a command list is as follows:

```
{
  "path": "command-path",
  "command": "command-name",
  "method": "rest-method"
}
```

The replaceable items in this format are as follows:

command-path

The relative path to REST resource that represents the command. This path is relative to the URL of the REST resource that is the parent of the resource that represents the command.

command-name

The name of the command as displayed in client applications that access the resource.

rest-method

The REST resource method that the command invokes when the command is run. The method is GET, POST, or DELETE.

JSON Representation of a Method in a Method List

The JSON representation of a method in a method list is as follows:

```
{
  "name": "method-name",
  "messageParameters": {
    message-parameter-list
  },
  "queryParameters": {
    queryparameter-list
  }
}
```

The replaceable items in this format are as follows:

method-name

The name of the method, which is GET, POST, or DELETE.

message-parameter-list

Zero or more metadata sets separated by a comma (,) that represent the message parameters that are allowed for the method. For the format of each metadata set, see [“JSON Representation of a Message Parameter or a Query Parameter” on page 85](#).

query-parameter-list

Zero or more metadata sets separated by a comma (,) that represent the query parameters that are allowed for the method. For the format of each metadata set, see [“JSON Representation of a Message Parameter or a Query Parameter” on page 85](#).

JSON Representation of a Message Parameter or a Query Parameter

The JSON representation of a message parameter or a query parameter is as follows:

```
"parameter-name": {attribute-list}
```

The replaceable items in this format are as follows:

parameter-name

The name of the parameter.

attribute-list

A comma-separated list of name-value pairs of attributes for the parameter. Each pair is in the following format:

```
"name": "value"
```

Possible attributes are as follows:

defaultValue

The default value of the parameter.

acceptableValues

The set or range of acceptable values for the parameter.

type

The data type of the parameter, which is one of the following types:

- `boolean`
- `int`
- `string`

optional

Indicates whether the parameter is optional. If `true`, the parameter is optional. If `false`, the parameter is required.

key

Indicates whether the parameter is key. If `true`, the parameter is key. If `false`, the parameter is not key.

Example JSON Resource Representation for a Configuration Object

This example shows the JSON representation of the resource for the node `sj01`. In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The URL to the resource in this example is

`http://localhost:4848/management/domain/nodes/node/sj01`.

Line breaks and white space are added to enhance readability.

```
{
  "command": "Node",
  "exit_code": "SUCCESS",
  "extraProperties": {
    "commands": [
      { "path": "delete-node", "command": "delete-node", "method": "DELETE" },
      { "path": "update-node", "command": "update-node", "method": "POST" },
      { "path": "ping-node-ssh", "command": "ping-node-ssh", "method": "GET" },
      { "path": "update-node-ssh", "command": "update-node-ssh", "method": "POST" },
      { "path": "update-node-config", "command": "update-node-config", "method": "POST" }
    ],
    "methods": [
      { "name": "GET" },
      { "name": "POST", "messageParameters": {
        "installDir": { "optional": "true", "type": "string", "key": "false" },
        "nodeDir": { "optional": "true", "type": "string", "key": "false" },
        "nodeHost": { "optional": "true", "type": "string", "key": "false" },
        "type": { "optional": "true", "type": "string", "key": "false" }
      }
    ]
  },
  "entity": {
    "installDir": "\\export\\glassfish3",
    "name": "sj01",
    "nodeDir": null,
    "nodeHost": "sj01.example.com",
    "type": "SSH"
  },
  "childResources": {
    "application-ref": "https://localhost:4848/management/domain/nodes/node/sj01/application-ref",
    "resource-ref": "https://localhost:4848/management/domain/nodes/node/sj01/resource-ref",
    "ssh-connector": "https://localhost:4848/management/domain/nodes/node/sj01/ssh-connector"
  }
}
```

XML Resource Representation for Configuration Objects

The general format for the XML representation of a resource for a configuration object is as follows:

```
<map>
  <entry key="extraProperties">
    <map>
```

```

<entry key="methods">
  <list>
    methods
  </list>
</entry>
<entry key="entity">
  <map>
    attributes
  </map>
</entry>
<entry key="commands">
  <list>
    commands
  </list>
</entry>
<entry key="childResources">
  <map>
    children
  </map>
</entry>
</map>
<entry key="message"></entry>
<entry key="exit_code" value="code"></entry>
<entry key="command" value="resource"></entry>
</map>

```

The replaceable items in this format are as follows:

methods

One or more XML elements that represent the methods that the resource supports. For the format of each element, see [“XML Representation of a Resource Method” on page 88](#).

attributes

Zero or more XML elements that represent the attributes of the resource. Each element specifies a name-value pair as follows:

```
<entry key="name" value="value"></entry>
```

commands

One or more XML elements that represent the `asadmin` subcommands for performing non—CRUD operations on the resource. For the format of each element, see [“XML Representation of a Command” on page 88](#).

children

Zero or more XML elements that represent the children of the resource. Each element is specified as follows:

```
<entry key="resource-name" value="url"></entry>
```

resource-name

The name of the resource as displayed in client applications that access the parent of the resource.

url

The URL to the child resource.

code

The result of the attempt to get the resource.

resource

The name of the resource.

XML Representation of a Resource Method

The XML representation of a method in a method list is as follows:

```
<map>
  <entry key="name" value="method-name"></entry>
  <entry key="messageParameters">
    message-parameter-list
  </entry>
  <entry key="queryParameters">
    message-parameter-list
  </entry>
</map>
```

The replaceable items in this format are as follows:

method-name

The name of the method, which is GET, POST, or DELETE.

message-parameter-list

Zero or more XML elements that represent the message parameters that are allowed for the method. For the format of each element, see [“XML Representation of a Message Parameter or a Query Parameter” on page 89](#).

query-parameter-list

Zero or more XML elements that represent the query parameters that are allowed for the method. For the format of each element, see [“XML Representation of a Message Parameter or a Query Parameter” on page 89](#).

XML Representation of a Command

The XML representation of a command is as follows:

```
<map>
  <entry key="command" value="command-name"></entry>
  <entry key="path" value="command-path"></entry>
  <entry key="method" value="rest-method"></entry>
</map>
```

The replaceable items in this format are as follows:

command-name

The name of the command as displayed in client applications that access the resource.

command-path

The relative path to REST resource that represents the command. This path is relative to the URL of the REST resource that is the parent of the resource that represents the command.

rest-method

The REST resource method that the command invokes when the command is run. The method is GET, POST, or DELETE.

XML Representation of a Message Parameter or a Query Parameter

The XML representation of a message parameter or a query parameter is as follows:

```
<map>
  <entry key="parameter-name">
    <map>
      attributes
    </map>
  </entry>
</map>
```

The replaceable items in this format are as follows:

parameter-name

The name of the parameter.

attributes

One or more XML elements that represent the attributes for the parameter. Each element specifies a name-value pair as follows:

```
<entry key="name" value="value"></entry>
```

Possible attributes are as follows:

defaultValue

The default value of the parameter.

acceptablevalues

The set or range of acceptable values for the parameter.

type

The data type of the parameter, which is one of the following types:

- `boolean`
- `int`
- `string`

optional

Indicates whether the parameter is optional. If `true`, the parameter is optional. If `false`, the parameter is required.

key

Indicates whether the parameter is key. If `true`, the parameter is key. If `false`, the parameter is not key.

Example XML Resource Representation

This example shows the XML representation of the resource for the node `sj01`. In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The URL to the resource in this example is

`http://localhost:4848/management/domain/nodes/node/sj01`.

Line breaks and white space are added to enhance readability.

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<map>
  <entry key="extraProperties">
    <map>
      <entry key="methods">
        <list>
          <map>
            <entry key="name" value="GET"/>
          </map>
          <map>
            <entry key="name" value="POST"/>
            <entry key="messageParameters">
              <map>
                <entry key="installDir">
                  <map>
                    <entry key="optional" value="true"/>
                    <entry key="type" value="string"/>
                    <entry key="key" value="false"/>
                  </map>
                </entry>
                <entry key="nodeDir">
                  <map>
                    <entry key="optional" value="true"/>
                    <entry key="type" value="string"/>
                    <entry key="key" value="false"/>
                  </map>
                </entry>
                <entry key="type">
                  <map>
                    <entry key="optional" value="true"/>
                    <entry key="type" value="string"/>
                    <entry key="key" value="false"/>
                  </map>
                </entry>
                <entry key="nodeHost">
                  <map>
                    <entry key="optional" value="true"/>
                    <entry key="type" value="string"/>
                    <entry key="key" value="false"/>
                  </map>
                </entry>
              </map>
            </entry>
          </list>
        </entry>
      <entry key="entity">
        <map>
```

```

    <entry key="installDir" value="/export/glassfish3"/>
    <entry key="name" value="sj01"/>
    <entry key="nodeDir" value=""/>
    <entry key="type" value="SSH"/>
    <entry key="nodeHost" value="sj01example.com"/>
  </map>
</entry>
<entry key="commands">
  <list>
    <map>
      <entry key="command" value="delete-node"/>
      <entry key="path" value="_delete-node"/>
      <entry key="method" value="DELETE"/>
    </map>
    <map>
      <entry key="command" value="_update-node"/>
      <entry key="path" value="_update-node"/>
      <entry key="method" value="POST"/>
    </map>
    <map>
      <entry key="command" value="ping-node-ssh"/>
      <entry key="path" value="ping-node-ssh"/>
      <entry key="method" value="GET"/>
    </map>
    <map>
      <entry key="command" value="update-node-ssh"/>
      <entry key="path" value="update-node-ssh"/>
      <entry key="method" value="POST"/>
    </map>
    <map>
      <entry key="command" value="update-node-config"/>
      <entry key="path" value="update-node-config"/>
      <entry key="method" value="POST"/>
    </map>
  </list>
</entry>
<entry key="childResources">
  <map>
    <entry key="application-ref"
      value="https://localhost:4848/management/domain/nodes/node/sj01/application-ref"/>
    <entry key="ssh-connector"
      value="https://localhost:4848/management/domain/nodes/node/sj01/ssh-connector"/>
    <entry key="resource-ref"
      value="https://localhost:4848/management/domain/nodes/node/sj01/resource-ref"/>
  </map>
</entry>
</map>
</entry>
<entry key="message"/>
<entry key="exit_code" value="SUCCESS"/>
<entry key="command" value="Node"/>
</map>

```

HTML Resource Representation for Configuration Objects

The format for the HTML representation of a resource for a configuration object is a web page that provides the following information about the resource:

- A list of the attributes of the resource and their values.
- A list of the methods and method parameters that the resource supports. Each method and its parameters are presented as a field of the appropriate type in an HTML form.
- A list of hypertext links to the children of the resource.
- A list of hypertext links to resources that represent `admin` subcommands for non-CRUD operations on the resource.

For a sample web page, see [Figure 2–1](#). In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The URL to the resource in this example is `http://localhost:4848/management/domain/nodes/node/sj01`.

Formats for Resource Representation of Monitoring Objects

The GlassFish Server REST interfaces represent resources for monitoring data in the following formats:

- JSON (<http://www.json.org/>)
- XML
- HTML

JSON Resource Representation for Monitoring Objects

The general format for the JSON representation of a resource for a monitoring object is as follows:

```
{
  "message": "",
  "command": "Monitoring Data",
  "exit_code": "code",
  "extraProperties": {
    "entity": {
      statistics-list
    },
    "childResources": {
      children
    }
  }
}
```

The replaceable items in this format are as follows:

code

The result of the attempt to get the resource.

statistics-list

Zero or more metadata sets separated by a comma (,) that represent the statistics that the monitoring object provides. For the format of each metadata set, see [“JSON Representation of a Statistic in a Statistics List” on page 93](#).

children

Zero or more child resources separated by a comma (,). Each child resource is specified as *"resource-name":url*.

resource-name

The name of the resource as displayed in client applications that access the parent of the resource.

url

The URL to the child resource.

JSON Representation of a Statistic in a Statistics List

The JSON representation of a counter statistic in a statistics list is as follows:

```
"statistic":{
  "count":count,
  "lastsampletime":last-sample-time,
  "description":"description",
  "unit":"unit",
  "name":"name",
  "starttime":start-time
}
```

The JSON representation of a range statistic in a statistics list is as follows:

```
"statistic":{
  "highwatermark":highest-value,
  "lowwatermark":lowest-value,
  "current":current-value
  "lastsampletime":last-sample-time,
  "description":"description",
  "unit":"unit",
  "name":"name",
  "starttime":start-time
}
```

The replaceable items in these formats are as follows:

statistic

The name of the statistic.

count

Counter statistics only: The current value of the statistic.

highest-value

Range statistics only: The highest value of the statistic since monitoring of the statistic began.

lowest-value

Range statistics only: The lowest value of the statistic since monitoring of the statistic began.

current-value

Range statistics only: The lowest value of the statistic since monitoring of the statistic began.

last-sample-time

The time in UNIX time at which the statistic was last sampled.

description

A textual description of what the statistic represents.

unit

The unit of measurement of the statistic, which is one of the following units of measurement:

name

The name of the statistic as displayed in client applications that access the resource that contains the statistic.

start-time

The time in UNIX time at which monitoring of the statistic began.

Example JSON Resource Representation for a Monitoring Object

This example shows the JSON representation of the monitoring object that provides class loader statistics for the virtual machine for the Java platform. In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The URL to the resource in this example is

<http://localhost:4848/monitoring/domain/server/jvm/class-loading-system>.

Line breaks and white space are added to enhance readability.

```
{
  "message": "",
  "command": "Monitoring Data",
  "exit_code": "SUCCESS",
  "extraProperties": {
    "entity": {
      "loadedclass-count": {
        "count": 8521,
        "lastsampletime": 1300726961018,
        "description": "Number of classes currently loaded in the Java virtual machine",
        "unit": "count",
        "name": "LoadedClassCount",
        "starttime": 1300483924126
      },
      "totalloadedclass-count": {
        "count": 8682,
        "lastsampletime": 1300726961018,
        "description": "Total number of classes that have been loaded since the Java virtual machine has started execution",

```

```

        "unit": "count",
        "name": "TotalLoadedClassCount",
        "starttime": 1300483924127
    },
    "unloadedclass-count": {
        "count": 161,
        "lastsampletime": 1300726961018,
        "description": "Total number of classes unloaded since the Java virtual
            machine has started execution",
        "unit": "count",
        "name": "UnLoadedClassCount",
        "starttime": 1300483924127
    }
}, "childResources": {}
}
}

```

XML Resource Representation for Monitoring Objects

The general format for the XML representation of a resource for a monitoring object is as follows:

```

<?xml version="1.0" encoding="UTF-8"?>
<map>
  <entry key="extraProperties">
    <map>
      <entry key="entity">
        <map>
          statistics
        </map>
      </entry>
      <entry key="childResources">
        <map>
          children
        </map>
      </entry>
    </map>
  </entry>
  <entry key="message" value=""></entry>
  <entry key="exit_code" value="code"></entry>
  <entry key="command" value="Monitoring Data"></entry>
</map>

```

The replaceable items in this format are as follows:

statistics

Zero or more XML elements that represent the statistics that the monitoring object provides.

For the format of each element, see [“XML Representation of a Statistic” on page 96](#).

children

Zero or more XML elements that represent the children of the resource. Each element is specified as follows:

```

<entry key="resource-name" value="url"></entry>

```

resource-name

The name of the resource as displayed in client applications that access the parent of the resource.

url

The URL to the child resource.

code

The result of the attempt to get the resource.

XML Representation of a Statistic

The XML representation of a counter statistic is as follows:

```
<entry key="statistic">
  <map>
    <entry key="unit" value="unit"></entry>
    <entry key="starttime">
      <number>start-time</number>
    </entry>
    <entry key="count">
      <number>count</number>
    </entry>
    <entry key="description" value="description"></entry>
    <entry key="name" value="name"></entry>
    <entry key="lastsampletime">
      <number>last-sample-time</number>
    </entry>
  </map>
</entry>
```

The XML representation of a range statistic is as follows:

```
<entry key="statistic">
  <map>
    <entry key="unit" value="unit"></entry>
    <entry key="starttime">
      <number>start-time</number>
    </entry>
    <entry key="highwatermark">
      <number>highest-value</number>
    </entry>
    <entry key="lowwatermark">
      <number>lowest-value</number>
    </entry>
    <entry key="current">
      <number>current-value</number>
    </entry>
    <entry key="description" value="description"></entry>
    <entry key="name" value="name"></entry>
    <entry key="lastsampletime">
      <number>last-sample-time</number>
    </entry>
  </map>
</entry>
```


The replaceable items in these formats are as follows:

statistic

The name of the statistic.

unit

The unit of measurement of the statistic, which is one of the following units of measurement:

start-time

The in time in UNIX time at which monitoring of the statistic began.

count

Counter statistics only: The current value of the statistic.

highest-value

Range statistics only: The highest value of the statistic since monitoring of the statistic began.

lowest-value

Range statistics only: The lowest value of the statistic since monitoring of the statistic began.

current-value

Range statistics only: The lowest value of the statistic since monitoring of the statistic began.

description

A textual description of what the statistic represents.

name

The name of the statistic as displayed in client applications that access the resource that contains the statistic.

last-sample-time

The time in UNIX time at which the statistic was last sampled.

Example XML Resource Representation for a Monitoring Object

This example shows the XML representation of the monitoring object that provides class loader statistics for the virtual machine for the Java platform. In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The URL to the resource in this example is

<http://localhost:4848/monitoring/domain/server/jvm/class-loading-system>.

Line breaks and white space are added to enhance readability.

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<map>
  <entry key="extraProperties">
    <map>
      <entry key="entity">
        <map>
          <entry key="unloadedclass-count">
            <map>
```

```
<entry key="unit" value="count"/>
<entry key="starttime">
  <number>1300483924127</number>
</entry><entry key="count">
  <number>161</number>
</entry>
<entry key="description" value="Total number of classes unloaded since
  the Java virtual machine has started execution"/>
<entry key="name" value="UnLoadedClassCount"/>
<entry key="lastsampletime">
  <number>1300726989505</number>
</entry>
</map>
</entry>
<entry key="totalloadedclass-count">
  <map>
    <entry key="unit" value="count"/>
    <entry key="starttime">
      <number>1300483924127</number>
    </entry>
    <entry key="count">
      <number>8682</number>
    </entry>
    <entry key="description" value="Total number of classes that have been
      loaded since the Java virtual machine has started execution"/>
    <entry key="name" value="TotalLoadedClassCount"/>
    <entry key="lastsampletime">
      <number>1300726989505</number>
    </entry>
  </map>
</entry>
<entry key="loadedclass-count">
  <map>
    <entry key="unit" value="count"/>
    <entry key="starttime">
      <number>1300483924126</number>
    </entry><entry key="count">
      <number>8521</number>
    </entry>
    <entry key="description" value="Number of classes currently loaded in
      the Java virtual machine"/>
    <entry key="name" value="LoadedClassCount"/>
    <entry key="lastsampletime">
      <number>1300726989505</number>
    </entry>
  </map>
</entry>
</map>
<entry key="childResources">
  <map/>
</entry>
</map>
</entry>
<entry key="message" value=""/>
<entry key="exit_code" value="SUCCESS"/>
<entry key="command" value="Monitoring Data"/>
</map>
```

HTML Resource Representation for Monitoring Objects

The format for the HTML representation of a resource for a monitoring object is a web page that provides the following information about the resource:

- A list of the statistics that the resource provides.
- A list of hypertext links to the children of the resource.

The following figure shows the web page for the REST resource that provides class loader statistics for the virtual machine for the Java platform. .

FIGURE 2-2 Web Page for the REST Resource That Provides Class Loader Statistics



GlassFish REST Interface

- [loadedclass-count](#)
 - count : 9787
 - lastsampletime : 1300741760533
 - description : Number of classes currently loaded in the Java virtual machine
 - unit : count
 - name : LoadedClassCount
 - starttime : 1300483924126
- [totalloadedclass-count](#)
 - count : 9972
 - lastsampletime : 1300741760533
 - description : Total number of classes that have been loaded since the Java virtual machine has started execution
 - unit : count
 - name : TotalLoadedClassCount
 - starttime : 1300483924127
- [unloadedclass-count](#)
 - count : 185
 - lastsampletime : 1300741760533
 - description : Total number of classes unloaded since the Java virtual machine has started execution
 - unit : count
 - name : UnLoadedClassCount
 - starttime : 1300483924127

Formats for Resource Representation of Log File Details

The GlassFish Server REST interfaces represent resources for log file details in the following formats:

- [JSON \(http://www.json.org/\)](http://www.json.org/)
- XML

JSON Resource Representation for Log File Details

The general format for the JSON representation of a resource for log file details is as follows:

```
{
  "records": [
    record-list
  ]
}
```

The replaceable items in this format are as follows:

record-list

One or more metadata sets separated by a comma (,) that represent the log records in the log file. For the format of each metadata set, see [“JSON Representation of a Log Record in a Record List” on page 100](#).

JSON Representation of a Log Record in a Record List

The JSON representation of a log record in a record list is as follows:

```
{
  "recordNumber": record-number,
  "loggedDateTimeInMS": logged-date,
  "loggedLevel": "log-level",
  "productName": "product-name",
  "loggerName": "logger-class-name",
  "nameValuePairs": "_ ThreadID=thread-id;_ ThreadName=thread-name;",
  "messageID": "message-id",
  "Message": "message-text"
}
```

The replaceable items in this format are as follows:

record-number

A serial number in the form of a decimal integer that uniquely identifies the log record.

logged-date

The date and time in UNIX time that the record was created.

log-level

The severity level of the message in the log record. For more information, see [“Setting Log Levels” on page 159](#).

product-name

The application that created the log message, for example, `glassfish3.1`.

logger-class-name

The fully qualified name of the Java class of the logger class that created the log message. Each component of GlassFish Server provides its own logger class. For detailed information about the names of logger classes in GlassFish Server, see [“Logger Namespaces” on page 154](#).

thread-id

The numerical identifier of the thread that created the message.

thread-name

The name of the thread that created the message.

message-id

A unique identifier for the message. For messages from GlassFish Server, this identifier consists of a module code and a numerical value, for example, `CORE5004`. All SEVERE and WARNING messages and some INFO messages from GlassFish Server contain a message identifier. For more information, see *GlassFish Server Open Source Edition 3.1 Error Message Reference*.

message-text

The text of the log message.

Example JSON Resource Representation for Log File Details

This example shows the JSON representation of the resource for log file details. In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The URL to the resource in this example is

`http://localhost:4848/management/domain/view-log/details`.

Line breaks and white space are added to enhance readability.

```
{
  "records": [
    {
      "recordNumber": 475,
      "loggedDateTimeInMS": 1300743782815,
      "loggedLevel": "INFO",
      "productName": "glassfish3.1",
      "loggerName": "org.glassfish.admingui",
      "nameValuePair": "_ThreadID=25;_ThreadName=Thread-1;",
      "messageID": "",
      "Message": "Admin Console: Initializing Session Attributes..."
    },
    {
      "recordNumber": 474,
      "loggedDateTimeInMS": 1300728893368,
      "loggedLevel": "INFO",
      "productName": "glassfish3.1",
      "loggerName": "javax.enterprise.system.core.com.sun.enterprise.v3.admin.adapter",

```

```
        "nameValuePairs": "_ ThreadID=238;_ ThreadName=Thread-1;",
        "messageID": "",
        "Message": "The Admin Console application is loaded."
    },
    {
        "recordNumber": 473,
        "loggedDateTimeInMS": 1300728893367,
        "loggedLevel": "INFO",
        "productName": "glassfish3.1",
        "loggerName": "javax.enterprise.system.core.com.sun.enterprise.v3.server",
        "nameValuePairs": "_ ThreadID=238;_ ThreadName=Thread-1;",
        "messageID": "CORE10010",
        "Message": " Loading application __admingui done in 40,063 ms"
    }
  ]
}
```

XML Resource Representation for Log File Details

The general format for the XML representation of a resource for log file details is as follows:

```
<records>
  records
</records>
```

The replaceable items in this format are as follows:

records

One or more XML elements that represent the log records in the log file. For the format of each element, see [“XML Representation of a Log Record” on page 102](#).

XML Representation of a Log Record

The XML representation of a log record is as follows:

```
<record loggedDateTimeInMS="logged-date" loggedLevel="log-level"
  loggerName="logger-class-name" messageID="message-id"
  nameValuePairs="_ ThreadID=thread-id;_ thread-name;" productName="product-name"
  recordNumber="record-number" />
```

The replaceable items in this format are as follows:

logged-date

The date and time in UNIX time that the record was created.

log-level

The severity level of the message in the log record. For more information, see [“Setting Log Levels” on page 159](#).

logger-class-name

The fully qualified name of the Java class of the logger class that created the log message.

Each component of GlassFish Server provides its own logger class. For detailed information about the names of logger classes in GlassFish Server, see [“Logger Namespaces” on page 154](#).

message-id

A unique identifier for the message. For messages from GlassFish Server, this identifier consists of a module code and a numerical value, for example, CORE5004. All SEVERE and WARNING messages and some INFO messages from GlassFish Server contain a message identifier. For more information, see *GlassFish Server Open Source Edition 3.1 Error Message Reference*.

thread-id

The numerical identifier of the thread that created the message.

thread-name

The name of the thread that created the message.

product-name

The application that created the log message, for example, glassfish3.1.

record-number

A serial number in the form of a decimal integer that uniquely identifies the log record.

Example XML Resource Representation for Log File Details

This example shows the XML representation of the resource for log file details. In this example, the DAS is running on the local host and the HTTP port for administration is 4848. The URL to the resource in this example is

`http://localhost:4848/management/domain/view-log/details.`

Line breaks and white space are added to enhance readability.

```
<records>
  <record loggedDateTimeInMS="1300743782815" loggedLevel="INFO"
    loggerName="org.glassfish.admingui" messageID=""
    nameValuePairs="_ ThreadID=25;_ ThreadName=Thread-1;"
    productName="glassfish3.1" recordNumber="475"/>
  <record loggedDateTimeInMS="1300728893368" loggedLevel="INFO"
    loggerName="javax.enterprise.system.core.com.sun.enterprise.v3.admin.adapter"
    messageID="" nameValuePairs="_ ThreadID=238;_ ThreadName=Thread-1;"
    productName="glassfish3.1" recordNumber="474"/>
  <record loggedDateTimeInMS="1300728893367" loggedLevel="INFO"
    loggerName="javax.enterprise.system.core.com.sun.enterprise.v3.server"
    messageID="CORE10010" nameValuePairs="_ ThreadID=238;_ ThreadName=Thread-1;"
    productName="glassfish3.1" recordNumber="473"/>
</records>
```

Supported Content Types in Requests to REST Resources

The GlassFish Server REST interfaces support the following types in the content-type header of a client request:

- [JSON \(http://www.json.org/\)](http://www.json.org/)
- XML
- [Form URL encoded](#)

How to specify the type in the content-type header depends on how you are sending the request. For example, if you are using the cURL utility, specify the type through the -H option as follows:

- For JSON, specify -H "Content-type: application/json".
- For XML, specify -H "Content-type: application/xml".
- For form URL encoded, specify
-H "Content-type: application/x-www-form-urlencoded".

Administering Domains

This chapter provides procedures for administering domains in the GlassFish Server Open Source Edition environment by using the `asadmin` command-line utility.

The following topics are addressed here:

- “About Administering Domains” on page 105
- “Creating, Logging In To, and Deleting a Domain” on page 107
- “Starting and Stopping a Domain” on page 115
- “Configuring a DAS or a GlassFish Server Instance for Automatic Restart” on page 117
- “Backing Up and Restoring a Domain” on page 122
- “Re-Creating the Domain Administration Server (DAS)” on page 125
- “Additional Domain Tasks” on page 127

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

About Administering Domains

A domain contains a group of GlassFish Server instances that are administered together. Each domain has a domain administration server (DAS) that hosts administrative applications. These concepts are explained in more detail in the following sections:

- “GlassFish Server Instances” on page 105
- “Domains for Administering GlassFish Server” on page 106
- “Domain Administration Server (DAS)” on page 107

GlassFish Server Instances

A GlassFish Server *instance* is a single Virtual Machine for the Java platform (Java Virtual Machine or JVM machine) on a single node in which GlassFish Server is running. A node

defines the host where the GlassFish Server instance resides. The JVM machine must be compatible with the Java Platform, Enterprise Edition (Java EE).

GlassFish Server instances form the basis of an application deployment.

Whenever a domain is created, GlassFish Server creates a default instance that is named `server`. If a single instance meets your requirements, you can use this instance for deploying applications without the need to administer GlassFish Server instances explicitly. You administer the default instance when you administer its domain.

If you require multiple instances, you must administer the instances explicitly. For more information, see Chapter 5, “Administering GlassFish Server Instances,” in *GlassFish Server Open Source Edition 3.1 High Availability Administration Guide*.

For an instance, you can also create virtual servers. Virtual servers do not span instances. For many purposes, you can use virtual servers instead of multiple instances in operational deployments. Virtual servers enable you to offer, within a single instance, separate domain names, IP addresses, and some administration capabilities to organizations or individuals. To these users, a virtual server behaves like a dedicated web server, but without the hardware and basic web server maintenance.

For more information about virtual servers, see “[Administering Virtual Servers](#)” on page 305.

Domains for Administering GlassFish Server

A *domain* is an administrative boundary that contains a group of GlassFish Server instances that are administered together. Each instance can belong to only one domain. A domain provides a preconfigured runtime for user applications. Each domain has its own configuration data, log files, and application deployment areas that are independent of other domains. If the configuration is changed for one domain, the configurations of other domains are not affected.

Domains enable different organizations and administrators to share securely a single GlassFish Server installation. Each organization or administrator can administer the instances in a single domain without affecting the instances in other domains.

At installation time, GlassFish Server creates a default domain that is named `domain1`. After installation, you can create additional domains as necessary.

When a domain is created, you are prompted for the administration user name and password. If you accept the default, the user `admin` is created without password. To reset the administration password, see “To Change an Administration Password” in *GlassFish Server Open Source Edition 3.1 Security Guide*.

Domain Administration Server (DAS)

The *domain administration server (DAS)* is a specially designated GlassFish Server instance that hosts administrative applications. The DAS is similar to any other GlassFish Server instance, except that the DAS has additional administration capabilities. The DAS authenticates the administrator, accepts requests from administration tools, and communicates with other instances in the domain to carry out the requests from administration tools.

Each domain has its own DAS with a unique administration port number. The default administration port is 4848, but a different port can be specified when a domain is created.

The DAS has the master copy of the configuration data for all instances in a domain. If an instance is destroyed, for example, because a host failed, the instance can be re-created from the data in the DAS.

The DAS is the default GlassFish Server instance in a domain and is named `server`. If a single instance meets your requirements, you can use the DAS for deploying applications and for administering the domain.

The graphical Administration Console communicates with a specific DAS to administer the domain that is associated with the DAS. Each Administration Console session enables you to configure and manage only one domain. If you create multiple domains, you must start a separate Administration Console session to manage each domain.

Creating, Logging In To, and Deleting a Domain

The following topics are addressed here:

- [“To Create a Domain” on page 107](#)
- [“To Create a Domain From a Custom Template” on page 108](#)
- [“To List Domains” on page 112](#)
- [“To Log In to a Domain” on page 112](#)
- [“To Delete a Domain” on page 114](#)

▼ To Create a Domain

After installing GlassFish Server and creating the default domain (`domain1`), you can create additional domains by using the local `create-domain` subcommand. This subcommand creates the configuration of a domain. Any user who has access to the `asadmin` utility on a given system can create a domain and store the domain configuration in a folder of choice. By default, the domain configuration is created in the default directory for domains. You can override this location to store the configuration elsewhere.

You are required to specify an administrative user when you create a domain, or you can accept the default login identity which is username `admin` with no password.

1 Select a name for the domain that you are creating.

You can verify that a name is not already in use by using the `list-domains(1)` subcommand

2 Create a domain by using the `create-domain(1)` subcommand.

Information about the options for this subcommand is included in this help page.

3 Type an admin user name and password for the domain.

To avoid setting up an admin login, you can accept the default admin, with no password. Pressing Return also selects the default.

Example 3–1 Creating a Domain

This example creates a domain named `domain1`. When you type the command, you might be prompted for login information.

```
asadmin> create-domain --adminport 4848 domain1
Enter admin user name[Enter to accept default]>
Using port 4848 for Admin.
Default port 8080 for HTTP Instance is in use. Using 1161
Using default port 7676 for JMS.
Using default port 3700 for IIOP.
Using default port 8081 for HTTP_SSL.
Using default port 3820 for IIOP_SSL.
Using default port 3920 for IIOP_MUTUALAUTH.
Default port 8686 for JMX_ADMIN is in use. Using 1162
Distinguished Name of the self-signed X.509 Server Certificate is:
[CN=moonbeam.gateway.2wire.net,OU=GlassFish,O=Oracle Corp.,L=Redwood Shores,ST
California,C=US]
Domain domain1 created.
Command create-domain executed successfully.
```

To start the Administration Console in a browser, enter the URL in the following format:

```
http://hostname:5000
```

For this example, the domain's log files, configuration files, and deployed applications now reside in the following directory:

```
domain-root-dir/mydomain
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-domain` at the command line.

▼ To Create a Domain From a Custom Template

A custom template enables you to customize the configuration of any domain that you create from the template.

1 Create a domain to use as the basis for the template.

For more information, see [“To Create a Domain” on page 107](#).

2 Use the `asadmin` utility or the Administration Console to configure the domain.

Your configuration changes will be included in the template that you create from the domain.

3 Copy the domain's `domain.xml` file under a new name to the `as-install/lib/templates` directory.

A domain's `domain.xml` file is located in the `domain-dir/config` directory.

4 In a plain text editor, edit the file that you copied to replace with tokens values that are to be substituted when a domain is created.

Each token is identified as `%%token-name%%`, where *token-name* is one of the following names:

ADMIN_PORT

Represents the port number of the HTTP port or the HTTPS port for administration. This token is replaced with one of the following values in the command to create a domain from the template:

- The value of the `--adminport` option
- The value of the `domain.adminPort` property

CONFIG_MODEL_NAME

Represents the name of the configuration that is created for the domain that is being created. This token is replaced with the string `server-config`.

DOMAIN_NAME

Represents the name of the domain that is being created. This token is replaced with the operand of `create-domain` subcommand.

HOST_NAME

Represents the name of the host on which the domain is being created. This token is replaced with the fully qualified host name of the host where the domain is being created.

HTTP_PORT

Represents the port number of the port that is used to listen for HTTP requests. This token is replaced with one of the following values in the command to create a domain from the template:

- The value of the `--instanceport` option
- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `domain.instancePort` property

HTTP_SSL_PORT

Represents the port number of the port that is used to listen for secure HTTP requests. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `http.ssl.port` property

JAVA_DEBUGGER_PORT

Represents the port number of the port that is used for connections to the [Java Platform Debugger Architecture \(JPDA\)](#) debugger. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `java.debugger.port` property

JMS_PROVIDER_PORT

Represents the port number for the Java Message Service provider. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `jms.port` property

JMX_SYSTEM_CONNECTOR_PORT

Represents the port number on which the JMX connector listens. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `domain.jmxPort` property

ORB_LISTENER_PORT

Represents the port number of the port that is used for IIOP connections. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `orb.listener.port` property

ORB_MUTUALAUTH_PORT

Represents the port number of the port that is used for secure IIOP connections with client authentication. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `orb.mutualauth.port` property

ORB_SSL_PORT

Represents the port number of the port that is used for secure IIOP connections. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `orb.ssl.port` property

OSGI_SHELL_TELNET_PORT

Represents the port number of the port that is used for connections to the [Apache Felix Remote Shell](#). This shell uses the Felix shell service to interact with the OSGi module management subsystem. This token is replaced with one of the following values in the command to create a domain from the template:

- A value that the `create-domain` subcommand calculates from the value of the `--portbase` option
- The value of the `osgi.shell.telnet.port` property

SERVER_ID

Represents the name of the DAS for the domain that is being created. This token is replaced with the string `server`.

Tip – For information about how these tokens are used in the default template, examine the `as-install/lib/templates/domain.xml` file.

5 Create the domain that you want to be based on a custom template.

In the command to create the domain, pass the name of file that you edited in the previous step as the `--template` option of the `create-domain(1)` subcommand.

6 Before starting the domain, verify that the domain's `domain.xml` file is valid.

Use the `verify-domain-xml(1)` subcommand for this purpose.

Information about the options for this subcommand is included in the subcommand's help page.

- See Also**
- [“To Create a Domain” on page 107](#)
 - `create-domain(1)`
 - `verify-domain-xml(1)`

You can also view the full syntax and options of the subcommands by typing the following commands at the command line.

- `asadmin help create-domain`
- `asadmin help verify-domain-xml`

▼ To List Domains

Use the `list-domains` subcommand to display a list of domains and their statuses. If the domain directory is not specified, the contents of the default *as-install/domains* directory is listed. If there is more than one domain, the domain name must be specified.

To list domains that were created in other directories, specify the `--domaindir` option.

- **List domains by using the `list-domains(1)` subcommand.**

Example 3-2 Listing Domains

This example lists the domains in the default *as-install/domains* directory:

```
asadmin> list-domains
Name: domain1 Status: Running
Name: domain4 Status: Not Running
Name: domain6 Status: Not Running
Command list-domains executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-domain` at the command line.

▼ To Log In to a Domain

All remote subcommands require that credentials be specified in terms of an administration user name and its password. By default, the domain is created with an identity that allows an `asadmin` user to perform administrative operations when no identity is explicitly or implicitly specified.

The *default identity* is in the form of a user whose name is `admin` and has no password. If you specify no user name on the command line or on prompt, and specify no password in the `--passwordfile` option or on prompt, and you have never logged in to a domain using either the `login` subcommand or the `create-domain` subcommand with the `----saveLogin` option, then the `asadmin` utility will attempt to perform a given administrative operation without specifying any identity.

A server (domain) allows administrative operations to be run using this default identity if the following conditions are true:

- The server (domain) uses file realm for authentication of administrative users.
If this condition is not true, you will need to specify the user name and password.
- The file realm has one and only one user (what the user name is does not matter).
If this condition is not true, you will also need to specify the user name.
- That one user has no password.
If this condition is not true, you will need to specify the password.

By default, all of these conditions are true, unless you have created the domain with a specific user name and password. Thus, by default, the only administrative user is admin with no password.

Use the `login` subcommand in local mode to authenticate yourself (log in to) a specific domain. After such login, you do not need to specify the administration user or password for subsequent operations on the domain. The `login` subcommand can only be used to specify the administration password. For other passwords that remote subcommands require, use the `--passwordfile` option, or specify the password at the command prompt. You are always prompted for the administration user name and password.

There is no logout subcommand. If you want to log in to another domain, invoke `asadmin login` with new values for `--host` and `--port`.

1 Determine the name of the domain that you are logging in to.

To list the existing domains:

```
asadmin list-domains
```

2 Log in to the domain by using the `login(1)` command.

Example 3–3 Logging In To a Domain on a Remote Machine

This example logs into a domain located on another machine. Options are specified before the `login` subcommand.

```
asadmin> --host foo --port 8282 login
Please enter the admin user name>admin Please enter the admin password>
Trying to authenticate for administration of server at host [foo] and port [8282] ...
Login information relevant to admin user name [admin]
for host [foo] and admin port [8282] stored at [/.asadminpass] successfully.
Make sure that this file remains protected. Information stored in this
file will be used by asadmin commands to manage associated domain.
```

Example 3-4 Logging In to a Domain on the Default Port of Localhost

This example logs into a domain on myhost on the default port. Options are specified before the login subcommand.

```
asadmin> --host myhost login
Please enter the admin user name>admin Please enter the admin password>
Trying to authenticate for administration of server at host [myhost] and port [4848] ...
An entry for login exists for host [myhost] and port [4848], probably from
an earlier login operation.
Do you want to overwrite this entry (y/n)?y
Login information relevant to admin user name [admin] for host [myhost]
and admin port [4848] stored at [/home/joe/.asadminpass] successfully.
Make sure that this file remains protected. Information stored in this file will be used by
asadmin commands to manage associated domain.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help login` at the command line. For additional information about passwords, see “Administering Passwords” in *GlassFish Server Open Source Edition 3.1 Security Guide*.

▼ To Delete a Domain

Use the `delete-domain` subcommand to delete an existing domain from a server. Only the root user or the operating system user who is authorized to administer the domain can run this subcommand.

Before You Begin A domain must be stopped before it can be deleted.

- 1 List domains by using the `list-domains(1)` subcommand.
- 2 If necessary, notify domain users that the domain is being deleted.
- 3 Ensure that the domain you want to delete is stopped.
If needed, see “[To Stop a Domain](#)” on page 116.
- 4 Delete the domain by using the `delete-domain(1)` subcommand.

Example 3-5 Deleting a Domain

This example deletes a domain named `domain1` from the location specified.

```
asadmin> delete-domain --domaindir ../domains domain1
Domain domain1 deleted.
Command delete-domain executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-domain` at the command line.

Starting and Stopping a Domain

The following topics are addressed here:

- [“To Start a Domain” on page 115](#)
- [“To Stop a Domain” on page 116](#)
- [“To Restart a Domain” on page 116](#)

▼ To Start a Domain

When you start a domain or server, the domain administration server (DAS) is started. After startup, the DAS runs constantly, listening for and accepting requests.

If the domain directory is not specified, the domain in the default *as-install/domains* directory is started. If there are two or more domains, the `domain_name` operand must be specified. Each domain must be started separately.

Note – For Microsoft Windows, you can use an alternate method to start a domain. From the Windows Start menu, select the command for your distribution of GlassFish Server:

- If you are using the Full Platform, select Programs → Oracle GlassFish Server → Start Admin Server.
 - If you are using the Web Profile, select Programs → Oracle GlassFish Server Web Profile → Start Admin Server.
-

This subcommand is supported in local mode only.

- **Start a domain by using the `start-domain(1)` subcommand.**

Example 3–6 Starting a Domain

This example starts `domain2` in the default domain directory.

```
asadmin> start-domain domain2
```

If there is only one domain, you can omit the domain name. If you do not include the password, you might be prompted to supply it.

```
Name of the domain started: [domain1] and its location:
[C:\prelude\v3_prelude_release\distributions\web\target\glassfish
domains\domain1].
Admin port for the domain: [4848].
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help start-domain` at the command line.

▼ To Stop a Domain

Stopping a domain or server shuts down its domain administration server (DAS). When stopping a domain, the DAS stops accepting new connections and then waits for all outstanding connections to complete. This shutdown process takes a few seconds. While the domain is stopped, the Administration Console and most of the `asadmin` subcommands cannot be used. This subcommand is particularly useful in stopping a runaway server. For more controlled situations, you can use the `restart-domain(1)` subcommand.

Note – For Microsoft Windows, you can use an alternate method to stop a domain. From the Start menu, select the command for your distribution of GlassFish Server:

- If you are using the Full Platform, select Programs → Oracle GlassFish Server → Stop Admin Server.
 - If you are using the Web Profile, select Programs → Oracle GlassFish Server Web Profile → Stop Admin Server.
-

- 1 If necessary, notify users that you are going to stop the domain.
- 2 Stop the domain by using the `stop-domain(1)` subcommand.

Example 3–7 Stopping a Domain (or Server)

This example stops `domain1` in the default directory, where `domain1` is the only domain present in the directory.

```
asadmin> stop-domain
Waiting for the domain to stop .....
Command stop-domain executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help stop-domain` at the command line.

▼ To Restart a Domain

Use the `restart-domain` subcommand in remote mode to restart the Domain Administration Server (DAS) of the specified host. When restarting a domain, the DAS stops accepting new connections and then waits for all outstanding connections to complete. This shutdown process takes a few seconds. Until the domain has restarted, the Administration Console and most of the `asadmin` subcommands cannot be used.

This subcommand is particularly useful for environments where the server machine is secured and difficult to get to. With the right credentials, you can restart the server from a remote location as well as from the same machine.

If the server will not restart, use the `stop-domain(1)` subcommand followed by the `start-domain(1)` subcommand.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Restart the domain by using the `restart-domain(1)` subcommand.**

Example 3–8 Restarting a Domain (or Server)

This example restarts `mydomain4` in the default directory.

```
asadmin> restart-domain mydomain4
Waiting for the domain to restart .....
Command restart-domain executed successfully.
```

Example 3–9 Restarting a Domain in a Browser

This example invokes the `restart-domain` subcommand in a browser.

```
http://yourhost:4848/__asadmin/restart-domain
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help restart-domain` at the command line.

Configuring a DAS or a GlassFish Server Instance for Automatic Restart

Use the `create-service` subcommand in local mode to configure your system to automatically restart a domain administration server (DAS) or a GlassFish Server instance. GlassFish Server enables you to configure a DAS or an instance for automatic restart on the following operating systems:

- Windows
- Linux
- Oracle Solaris

To ensure that automatic restart functions correctly on Windows, you must prevent service shutdown when a user logs out.

The following topics are addressed here:

- [“To Configure a DAS or an Instance for Automatic Restart on Windows” on page 118](#)
- [“To Configure a DAS or an Instance for Automatic Restart on Linux” on page 119](#)

- [“To Configure a DAS or an Instance for Automatic Restart on Oracle Solaris” on page 120](#)
- [“To Prevent Service Shutdown When a User Logs Out on Windows” on page 122](#)

▼ To Configure a DAS or an Instance for Automatic Restart on Windows

On Windows systems, the `create-service` subcommand creates a Windows service to represent the DAS or instance. The service is created in the disabled state. After this subcommand creates the service, you must use the Windows Services Manager or the Windows Services Wrapper to start, stop, uninstall, or install the service. To administer the service from the Windows command line, use the `sc.exe` tool.

This subcommand must be run as the OS-level administrator user.

- 1 **Create the service by using the `create-service(1)` subcommand.**
- 2 **After the service is created, start the service by using the Windows Services Manager or the Windows Services Wrapper.**

For example, to start the service for the default domain by using the `sc.exe` tool, type:

```
C:\> sc start domain1
```

If you are using the `sc.exe` tool to administer the service, use the tool as follows:

- To obtain information about the service, use the `sc query` command.
- To stop the service, use the `sc stop` command.
- To uninstall the service, use the `sc delete` command.

Example 3–10 Creating a Service to Restart a DAS Automatically on Windows

This example creates a service for the default domain on a system that is running Windows.

```
asadmin> create-service
Found the Windows Service and successfully uninstalled it.
The Windows Service was created successfully. It is ready to be started. Here are
the details:
ID of the service: domain1
Display Name of the service:domain1 GlassFish Server
Domain Directory: C:\glassfishv3\glassfish\domains\domain1
Configuration file for Windows Services Wrapper: C:\glassfishv3\glassfish\domains\
domain1\bin\domain1Service.xml
The service can be controlled using the Windows Services Manager or you can use the
Windows Services Wrapper instead:
Start Command: C:\glassfishv3\glassfish\domains\domain1\bin\domain1Service.exe start
Stop Command: C:\glassfishv3\glassfish\domains\domain1\bin\domain1Service.exe stop
Uninstall Command: C:\glassfishv3\glassfish\domains\domain1\bin\domain1Service.exe
uninstall
Install Command: C:\glassfishv3\glassfish\domains\domain1\bin\domain1Service.exe
```

```
install
```

This message is also available in a file named PlatformServices.log in the domain's root directory
Command create-service executed successfully.

Example 3–11 Querying the Service to Restart a DAS Automatically on Windows

This obtains information about the service for the default domain on a system that is running Windows.

```
C:\> sc query domain1

SERVICE_NAME: domain1
        TYPE               : 10  WIN32_OWN_PROCESS
        STATE                : 1   STOPPED
        WIN32_EXIT_CODE       : 1077 (0x435)
        SERVICE_EXIT_CODE    : 0   (0x0)
        CHECKPOINT           : 0x0
        WAIT_HINT            : 0x0
```

▼ To Configure a DAS or an Instance for Automatic Restart on Linux

On Linux systems, the create-service subcommand creates a System-V-style initialization script /etc/init.d/GlassFish_*domain-or-instance-name* and installs a link to this script in any /etc/rcN.d directory that is present, where *N* is 0, 1, 2, 3, 4, 5, 6, and S. After this subcommand creates the script, you must use this script to start, stop, or restart the domain or instance.

The script automatically restarts the domain or instance only during a reboot. If the domain or instance is stopped, but the host remains running, the domain or instance is not restarted automatically. To restart the domain or instance, you must run the script manually.

You might no longer require the domain or instance to be automatically restarted during a reboot. In this situation, use the operating system to delete the initialization script and the link to the script that the create-service subcommand creates.

The create-service subcommand must be run as the OS-level root user.

- Create the service by using the create-service(1) subcommand.

Example 3–12 Creating a Service to Restart a DAS Automatically on Linux

This example creates a service for the default domain on a system that is running Linux.

```
asadmin> create-service
Found the Linux Service and successfully uninstalled it.
The Service was created successfully. Here are the details:
```

```
Name of the service:domain1
Type of the service:Domain
Configuration location of the service:/etc/init.d/GlassFish_domain1
User account that will run the service: root
You have created the service but you need to start it yourself.
Here are the most typical Linux commands of interest:
```

```
* /etc/init.d/GlassFish_domain1 start
* /etc/init.d/GlassFish_domain1 stop
* /etc/init.d/GlassFish_domain1 restart
```

For your convenience this message has also been saved to this file:
/export/glassfish3/glassfish/domains/domain1/PlatformServices.log
Command create-service executed successfully.

▼ To Configure a DAS or an Instance for Automatic Restart on Oracle Solaris

On Oracle Solaris systems, the `create-service` subcommand creates an Oracle Solaris Service Management Facility (SMF) service that restarts a DAS or an instance. The service grants to the process the privileges of the user that runs the process. When you create an SMF service, the default user is the superuser. If you require a different user to run the process, specify the user in `method_credential`.

If your process is to bind to a privileged port of Oracle Solaris, the process requires the `net_privaddr` privilege. The privileged ports of the Oracle Solaris operating system have port numbers less than 1024.

To determine if a user has the `net_privaddr` privilege, log in as that user and type the command `ppriv -l | grep net_privaddr`.

After you create and enable the SMF service, if the domain or instance is stopped, SMF restarts it.

Before You Begin To run the `create-service` subcommand, you must have `solaris.smf.*` authorization. For information about how to set the authorizations, see the `useradd(1M)` man page and the `usermod(1M)` man page. You must also have write permission in the directory tree: `/var/svc/manifest/application/SUNWappserver`. Usually, the superuser has both of these permissions. Additionally, Oracle Solaris administration commands such as `svccfg(1M)`, `svcs(1)`, and `auths(1)` must be available in the `PATH`.

If a particular GlassFish Server domain or instance should not have default user privileges, modify the manifest of the service and reimport the service.

1 Create the service by using the `create-service(1)` subcommand.

2 After the service is created, enable the service by using the `svcadm enable` command.

For example, to enable the SMF service for the default domain, type:

```
svcadm enable /appserver/domains/domain1
```

Example 3–13 Creating a Service to Restart a Domain Automatically on Oracle Solaris

This example creates a service for the default domain on a system that is running Oracle Solaris.

```
asadmin> create-service
The Service was created successfully. Here are the details:
Name of the service:application/GlassFish/domain1
Type of the service:Domain
Configuration location of the service:/home/gfuser/glassfish-installations
/glassfishv3/glassfish/domains
Manifest file location on the system:/var/svc/manifest/application
/GlassFish/domain1_home_gfuser_glassfish-installations_glassfishv3
_glassfish_domains/Domain-service-smf.xml.
You have created the service but you need to start it yourself.
Here are the most typical Solaris commands of interest:
* /usr/bin/svcs -a | grep domain1 // status
* /usr/sbin/svcadm enable domain1 // start
* /usr/sbin/svcadm disable domain1 // stop
* /usr/sbin/svccfg delete domain1 // uninstall
Command create-service executed successfully
```

See Also For information about administering the service, see the following Oracle Solaris documentation:

- Chapter 18, “Managing Services (Overview),” in *System Administration Guide: Basic Administration*
- Chapter 19, “Managing Services (Tasks),” in *System Administration Guide: Basic Administration*
- `auths(1)`
- `svcs(1)`
- `svcadm(1M)`
- `svccfg(1M)`
- `useradd(1M)`
- `usermod(1M)`
- `rbac(5)`
- `smf_security(5)`

▼ To Prevent Service Shutdown When a User Logs Out on Windows

By default, the Java Virtual Machine (VM) receives signals from Windows that indicate that Windows is shutting down, or that a user is logging out of Windows, which causes the system to shut itself down cleanly. This behavior causes the GlassFish Server service to shut down. To prevent the service from shutting down when a user logs out, you must set the `-Xrs` Java VM option (http://download.oracle.com/docs/cd/E17409_01/javase/6/docs/technotes/tools/solaris/java.html).

1 Ensure that the DAS is running.

2 Set the `-Xrs` Java VM option for the DAS.

Use the `create-jvm-options(1)` subcommand for this purpose.

```
asadmin> create-jvm-options -Xrs
```

3 Set the `-Xrs` Java VM option for the Java VM within which the `asadmin` utility runs.

To set this option, edit the `asadmin.bat` file to add the `-Xrs` option to the line that runs the `admin-cli.jar` file.

- **In the `as-install\bin\asadmin.bat` file, edit the line to read as follows:**

```
%JAVA% -Xrs -jar "%~dp0..\modules\admin-cli.jar" %*
```

- **In the `as-install-parent\bin\asadmin.bat` file, edit the line to read as follows:**

```
%JAVA% -Xrs -jar "%~dp0..\glassfish\modules\admin-cli.jar" %*
```

4 If the GlassFish Server service is running, restart the service for your changes to take effect.

Backing Up and Restoring a Domain

The following topics are addressed here:

- [“To Back Up a Domain” on page 122](#)
- [“To Restore a Domain” on page 123](#)
- [“To List Domain Backups” on page 124](#)

▼ To Back Up a Domain

Use the `backup-domain` subcommand in local mode to make a backup of a specified domain.

When you use the `backup-domain` subcommand, GlassFish Server creates a ZIP file backup of all the files and subdirectories in the domain's directory, *domain-root-dir/domain-name*, except for the `backups` subdirectory.

The `backup-domain` subcommand provides several options to meet particular needs, including:

- `--backupdir` to specify a directory in which to store the backup instead of the default *domain-root-dir/domain-name/backups*.
- `--description` to provide a description of the backup to be stored in the backup itself.

1 Ensure that the domain is stopped.

The `backup-domain` subcommand operates only when the domain is stopped.

2 Back up the domain by using the `backup-domain(1)` subcommand.

3 Restore the domain to its previous state, if necessary.

Start the domain.

Example 3–14 Backing Up the Default Domain

This example makes a backup of the default domain, `domain1`, storing the backup file in `/net/backups.example.com/glassfish`:

```
asadmin> backup-domain --backupdir /net/backups.example.com/glassfish domain1
Backed up domain1 at Mon Jan 17 08:16:22 PST 2011.
Command backup-domain executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help backup-domain` at the command line.

▼ To Restore a Domain

Use the `restore-domain` subcommand in local mode to use a backup file to restore the files and subdirectories in a specified domain's directory.

The `restore-domain` subcommand can use backup files created by the `backup-domain` subcommand and by automatic backup configurations, both full backups and configuration-only backups. Automatic backup configurations are available only in Oracle GlassFish Server.

1 If necessary, notify domain users that the domain is being restored from backup.

2 Ensure that the domain is stopped.

The `restore-domain` subcommand operates only when the domain is stopped.

To determine whether the domain is running, use the `list-domains(1)` subcommand, as described in [“To List Domains” on page 112](#).

To stop the domain, use the `stop-domain(1)` subcommand as described in [“To Stop a Domain” on page 116](#).

- 3 **Restore backup files for a domain by using the `restore-domain(1)` subcommand.**
- 4 **Verify that the restore has succeeded.**
- 5 **If necessary, notify users that the domain has been restored and is available.**

Example 3–15 Restoring the Default Domain

This example restores files for the default domain, `domain1`, from the most recent backup stored in a specified backup directory:

```
asadmin> restore-domain --backupdir /net/backups.example.com/glassfish domain1
Restored the domain (domain1) to /home/user1/glassfish3/glassfish/domains/domain1
Command restore-domain executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin restore-domain --help` at the command line.

▼ To List Domain Backups

Use the `list-backups` subcommand in local mode to display information about backups of a specified domain stored in a specified backup directory.

The `list-backups` subcommand provides several options to meet particular needs, including:

- `--backupdir` to specify a directory where backups are stored instead of the default *domain-root-dir/domain-name/backups*.

- **List backups by using the `list-backups(1)` subcommand.**

Example 3–16 Listing Backups of the Default Domain

This example lists the backups of the default domain, `domain1`, that are stored in the `/net/backups.example.com/glassfish` directory:

```
asadmin> list-backups --backupdir /net/backups.example.com/glassfish domain1
CONFIG      USER  BACKUP DATE      FILENAME
          user1 Mon Jan 17 08:16:22 PST 2011 domain1_2011_01_17_v00001.zip
monthly-full user1 Wed Dec 01 00:00:00 PST 2010 domain1_2010_12_01_v00001.zip
```

```
monthly-full user1 Sat Jan 01 00:00:03 PST 2011 domain1_2011_01_01_v00001.zip
monthly-full user1 Tue Feb 01 00:00:01 PST 2011 domain1_2011_02_01_v00001.zip
Command list-backups executed successfully.
```

Note that this listing includes backups created automatically by a backup configuration. This feature is available only in Oracle GlassFish Server.

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-backups` at the command line.

Re-Creating the Domain Administration Server (DAS)

For mirroring purposes, and to provide a working copy of the DAS, you must have:

- One host (olddashost) that contains the original DAS.
- A second host (apphost) that contains a cluster with server instances running applications and catering to clients. The cluster is configured using the DAS on the first host.
- A third host (newdashost) where the DAS needs to be re-created in a situation where the first host crashes or is being taken out of service.

Note – You must maintain a backup of the DAS from the first host using the `backup-domain(1)` subcommand as described in [“To Back Up a Domain” on page 122](#). You can automatically maintain a backup of the DAS using the automatic backups feature of Oracle GlassFish Server.

Note – Oracle GlassFish Server includes `asadmin` subcommands that simplify this procedure. If you are using Oracle GlassFish Server, see [“To Migrate the DAS,” in *Oracle GlassFish Server 3.1 Administration Guide*](#).

▼ To Migrate the DAS

The following steps are required to migrate the DAS from the first host (olddashost) to the third host (newdashost).

1 Install GlassFish Server on newdashost just as it was installed on olddashost.

This is required so that the DAS can be properly restored on newdashost without causing path conflicts.

2 Use the `restore-domain` subcommand to restore the latest backup file onto newdashost.

For example:

```
asadmin> restore-domain --backupdir /net/backups.example.com/glassfish
```

This example assumes that backups are stored in a network-accessible location. If this is not the case, manually copy the latest backup file from offline storage to a directory on newdashost.

You can backup any domain. However, while re-creating the domain, the domain name should be same as the original.

3 Stop the domain on olddashost, if it is running.

4 Start the domain on newdashost by using the `start-domain(1)` subcommand.

For example:

```
asadmin> start-domain domain1
```

5 If the domain on olddashost was centrally administered, set up centralized administration on newdashost.

See Chapter 2, “Setting Up SSH for Centralized Administration,” in *GlassFish Server Open Source Edition 3.1 High Availability Administration Guide* for instructions.

6 Verify that instances on other hosts are visible to the new DAS on newdashost:

```
asadmin> list-instances --long
```

7 Change the DAS host values for properties under the node on apphost.

In the file `as-install/nodes/node-name/agent/config/das.properties` file, change the `agent.das.host` property value to refer to newdashost instead of olddashost.

8 Use the new DAS to restart clusters and standalone instances on apphost:

Restarting the clustered and standalone instances on apphost triggers their recognition of the new DAS on newdashost.

a. Use the `list-clusters` subcommand to list the clusters in the domain.

b. Use the `stop-cluster` subcommand to stop each cluster.

c. Use the `list-instances` subcommand to list the instances in the domain.

d. Use the `restart-instance` subcommand to restart each standalone instance.

e. Use the `start-cluster` subcommand to start each cluster.

If the domain does not use centralized administration, use the `start-local-instance` subcommand to start the cluster instances on apphost.

9 Verify that instances on apphost are running:

```
asadmin> list-instances --long
```

10 Decommission and discontinue use of the DAS on olddashost.

Additional Domain Tasks

The following topics are addressed here:

- [“To Display Domain Uptime” on page 127](#)
- [“To Switch a Domain to Another Supported Java Version” on page 127](#)
- [“To Change the Administration Port of a Domain” on page 128](#)

▼ To Display Domain Uptime

Use the `uptime` subcommand in remote mode to display the length of time that the domain administration server (DAS) has been running since it was last started.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Display uptime by using the `uptime(1)` subcommand.**

Example 3–17 Displaying the DAS Uptime

This example displays the length of time that the DAS has been running.

```
asadmin> uptime
Uptime: 1 Weeks, 4 days, 0 hours, 17 minutes, 14 seconds, Total milliseconds: 951434595
Command uptime executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help uptime` at the command line.

▼ To Switch a Domain to Another Supported Java Version

GlassFish Server 3.1 requires Version 6 Java SE platform as the underlying virtual machine for the Java platform (Java Virtual Machine or JVM machine).

Note – Do not downgrade to an earlier Java version after a domain has been created with a newer JVM machine. If you must downgrade your JVM machine, downgrade it only for individual domains.

- 1 **If you have not already done so, download the desired Java SDK (not the JRE) and install it on your system.**

The Java SDK can be downloaded from the [Java SE Downloads page \(http://www.oracle.com/technetwork/java/javase/downloads/index.html\)](http://www.oracle.com/technetwork/java/javase/downloads/index.html).

- 2 **Start the domain for which you are changing the JDK.**

Use the following format:

```
as-install/bin/asadmin start-domain domain-name
```

For a valid JVM installation, locations are checked in the following order:

- a. **domain.xml (java-home inside java-config)**
- b. **asenv.conf (setting AS_JAVA="path to java home")**

If a legal JDK is not found, a fatal error occurs and the problem is reported back to you.

- 3 **If necessary, change the JVM machine attributes for the domain.**

In particular, you might need to change the JAVA_HOME environment variable. For example, to change the JAVA_HOME variable, type:

```
as-install/bin/asadmin set "server.java-config.java-home=path-to-java-home"
```

▼ To Change the Administration Port of a Domain

Use the set subcommand in remote mode to change the administration port of a domain.

The HTTP port or the HTTPS port for administration of a domain is defined by the --adminport option of the create-domain(1) subcommand when the domain is created. If this port must be reallocated for another purpose, change the port on which the DAS listens for administration requests.

- 1 **Ensure that the server is running.**

Remote subcommands require a running server.

- 2 **Set the port number to its new value.**

Use the set(1) subcommand for this purpose.

```
$ asadmin set  
server-config.network-config.network-listeners.network-listener.admin-listener.port=new-port-number  
new-port-number
```

The new value that you are setting for the port number.

Note – After you set the port number to its new value, running the `list-domains` subcommand incorrectly reports that the DAS is not running. The `list-domains` subcommand reports the correct state again only after you stop and restart the domain as explained in the steps that follow.

3 Stop the domain, specifying the host on which the DAS is running and the old administration port number of the domain.

You must specify the old port number because the DAS is still listening for administration requests on this port. If you omit the port number, the command fails because the `stop-domain` subcommand attempts to contact the DAS through the new port number.

Note – Only the options that are required to complete this task are provided in this step. For information about all the options for controlling the behavior of the domain, see the `stop-domain(1)` help page.

```
$ asadmin --host host-name --port old-port-number stop-domain
```

host-name

The name of the host on which the DAS is running. If you run the `stop-domain` subcommand on the host where the DAS is running, you must specify the actual host name and not `localhost`. If you specify `localhost`, the `stop-domain` subcommand fails.

old-port-number

The value of administration port number of the domain *before* you changed it in the preceding step.

4 Start the domain.

Note – Only the options that are required to complete this task are provided in this step. For information about all the options for controlling the behavior of the domain, see the `start-domain(1)` help page.

```
$ start-domain [domain-name]
```

domain-name

The name of the domain to start. If only one domain subdirectory is contained in the `domains` directory, you may omit this option.

Example 3–18 Changing the Administration Port of a Domain

This example changes the administration port of the domain `domain1` from 4848 to 4849. The DAS is running on the host `xk01.example.com`.

```
$ asadmin set
server-config.network-config.network-listeners.network-listener.admin-listener.port=4849
server-config.network-config.network-listeners.network-listener.admin-listener.port=4849
Command set executed successfully.
$ asadmin --host xk01.example.com --port 4848 stop-domain
Waiting for the domain to stop ....
Command stop-domain executed successfully.
$ asadmin start-domain
Waiting for domain1 to start .....
Successfully started the domain : domain1
domain Location: /export/glassfish3/glassfish/domains/domain1
Log File: /export/glassfish3/glassfish/domains/domain1/logs/server.log
Admin Port: 4849
Command start-domain executed successfully.
```

- See Also**
- create-domain(1)
 - set(1)
 - start-domain(1)
 - stop-domain(1)

You can also view the full syntax and options of the subcommands by typing the following commands at the command line:

- asadmin help create-domain
- asadmin help set
- asadmin help start-domain
- asadmin help stop-domain

Administering the Virtual Machine for the Java Platform

This chapter provides procedures for administering the Virtual Machine for the Java platform (Java Virtual Machine) or JVM machine) in the GlassFish Server Open Source Edition 3.1 environment by using the `asadmin` command-line utility.

The following topics are addressed here:

- [“Administering JVM Options” on page 131](#)
- [“Administering the Profiler” on page 135](#)

Instructions for accomplishing these tasks by using the Administration Console are contained in the Administration Console online help.

Administering JVM Options

The Java Virtual Machine is an interpretive computing engine responsible for running the byte codes in a compiled Java program. The virtual machine translates the Java byte codes into the native instructions of the host machine. GlassFish Server, being a Java process, requires a virtual machine to run and support the Java applications running on it. JVM settings are part of an GlassFish Server configuration.

The following topics are addressed here:

- [“To Create JVM Options” on page 132](#)
- [“To List JVM Options” on page 132](#)
- [“To Delete JVM Options” on page 133](#)
- [“To Generate a JVM Report” on page 134](#)

▼ To Create JVM Options

Use the `create-jvm-options` subcommand in remote mode to create JVM options in the Java configuration or the profiler elements of the `domain.xml` file. If JVM options are created for a profiler, these options are used to record the settings that initiate the profiler.

- 1 **Ensure that the server is running.**

Remote subcommands require a running server.

- 2 **Create JVM options by using the `create-jvm-options(1)` subcommand.**

To create more than one JVM option, use a colon (:) to separate the options. If the JVM option itself contains a colon (:), use the backslash (\) to offset the colon delimiter.

Information about properties for the subcommand is included in this help page.

- 3 **To apply your changes, restart GlassFish Server. See [“To Restart a Domain” on page 116](#).**

Example 4–1 Creating JVM Options

This example sets multiple Java system properties.

```
asadmin> create-jvm-options -Dunixlocation=/root/example:
-Dvariable=$HOME:
-Dwindowslocation=d\\:\\sun\\appserver:
-Doption1=-value1
created 4 option(s)
Command create-jvm-options executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-jvm-options` at the command line.

▼ To List JVM Options

Use the `list-jvm-options` subcommand in remote mode to list the existing JVM options.

- 1 **Ensure that the server is running.**

Remote subcommands require a running server.

- 2 **List JVM options by using the `list-jvm-options(1)` subcommand.**

Example 4–2 Listing JVM Options

This example lists all JVM options.

```

asadmin> list-jvm-options
-Djava.security.auth.login.config=${com.sun.aas.instanceRoot}/config/login.conf
-XX: LogVMOutput
-XX: UnlockDiagnosticVMOptions
-Dcom.sun.enterprise.config.config_environment_factory_class=com.sun.enterprise.
config.serverbeans.AppserverConfigEnvironmentFactory
-Djavax.net.ssl.keyStore=${com.sun.aas.instanceRoot}/config/keystore.jks
-XX:NewRatio=2
-Djava.security.policy=${com.sun.aas.instanceRoot}/config/server.policy
-Djdbc.drivers=org.apache.derby.jdbc.ClientDriver
-Djavax.net.ssl.trustStore=${com.sun.aas.instanceRoot}/config/cacerts.jks
-client
-Djava.ext.dirs=${com.sun.aas.javaRoot}/lib/ext${path.separator}${com.sun.aas.javaRoot}/jre/lib/ext${path.separator}${com.sun.aas.instanceRoot}/lib/ext${path.separator}${com.sun.aas.derbyRoot}/lib
-Xmx512m
-XX:LogFile=${com.sun.aas.instanceRoot}/logs/jvm.log
-Djava.endorsed.dirs=${com.sun.aas.installRoot}/lib/endorsed
Command list-jvm-options executed successfully.

```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-jvm-options` at the command line.

▼ To Delete JVM Options

Use the `delete-jvm-options` subcommand in remote mode to delete JVM options from the Java configuration or profiler elements of the `domain.xml` file.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List JVM options by using the `list-jvm-options(1)` subcommand.

3 If necessary, notify users that the JVM option is being deleted.

4 Delete JVM options by using the `delete-jvm-options(1)` subcommand.

To remove more than one JVM option, use a colon (:) to separate the options. If the JVM option itself contains a colon, use the backslash (\) to offset the colon delimiter.

5 To apply your changes, restart GlassFish Server. See [“To Restart a Domain” on page 116](#).

Example 4–3 Deleting a JVM Option

This example removes a single JVM option.

```

asadmin> delete-jvm-options -Dopt1=A
deleted 1 option(s)
Command delete-jvm-options executed successfully.

```

Example 4-4 Deleting Multiple JVM Options

This example removes multiple JVM options.

```
asadmin> delete-jvm-options -Doption1=-value1:-Dvariable=\$HOME
deleted 2 option(s)
Command delete-jvm-options executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-jvm-options` at the command line.

▼ To Generate a JVM Report

Use the `generate-jvm-report` subcommand in remote mode to generate a JVM report showing the threads (dump of a stack trace), classes, memory, and loggers for a specified domain administration server (DAS). You can generate the following types of reports: summary (default), class, thread, log.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Generate the report by using the `generate-jvm-report(1)` subcommand.**

Example 4-5 Generating a JVM Report

This example displays summary information about the threads, classes, and memory.

```
asadmin> generate-jvm-report --type summary
Operating System Information:
Name of the Operating System: Windows XP
Binary Architecture name of the Operating System: x86, Version: 5.1
Number of processors available on the Operating System: 2
System load on the available processors for the last minute: NOT_AVAILABLE.
(Sum of running and queued runnable entities per minute).
.
,
.
user.home = C:\Documents and Settings\Jennifer
user.language = en
user.name = Jennifer
user.timezone = America/New_York
user.variant =
variable = \$HOME
web.home = C:\Preview\v3_Preview_release\distributions\web\target\
glassfish\modules\web
Command generate-jvm-report executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help generate-jvm-report` at the command line.

Administering the Profiler

A *profiler* generates information used to analyze server performance.

The following topics are addressed here:

- [“To Create a Profiler” on page 135](#)
- [“To Delete a Profiler” on page 136](#)

▼ To Create a Profiler

A server instance is tied to a particular profiler by the profiler element in the Java configuration. If JVM options are created for a profiler, the options are used to record the settings needed to activate a particular profiler. Use the `create-profiler` subcommand in remote mode to create the profiler element in the Java configuration.

Only one profiler can exist. If a profiler already exists, you receive an error message that directs you to delete the existing profiler before creating a new one.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Create a profiler by using the `create-profiler(1)` subcommand.

Information about properties for the subcommand is included in this help page.

3 To apply your changes, restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

Example 4–6 Creating a Profiler

This example creates a profiler named `sample_profiler`.

```
asadmin> create-profiler --classpath=/home/appserver/ --nativelibrarypath=/u/home/lib
--enabled=false --property=defaultuser=admin:password=adminadmin sample_profiler
Command create-profiler executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-profiler` at the command line.

▼ To Delete a Profiler

Use the `delete-profiler` subcommand in remote mode to delete the profiler element from the Java configuration. You can then create a new profiler.

- 1 Ensure that the server is running.**

Remote subcommands require a running server.

- 2 Delete the profiler by using the `delete-profiler(1)` subcommand.**

- 3 To apply your changes, restart GlassFish Server.**

See [“To Restart a Domain” on page 116](#).

Example 4-7 Deleting a Profiler

This example deletes the profiler named `sample_profiler`.

```
asadmin> delete-profiler sample_profiler
Command delete-profiler executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-profiler` at the command line.

Administering Thread Pools

This chapter provides procedures for administering thread pools in the GlassFish Server Open Source Edition 3.1 environment by using the `asadmin` command-line utility.

The following topics are addressed here:

- [“About Thread Pools” on page 137](#)
- [“Configuring Thread Pools” on page 138](#)

Instructions for accomplishing these tasks by using the Administration Console are contained in the Administration Console online help.

About Thread Pools

The Virtual Machine for the Java platform (Java Virtual Machine) or JVM machine) can support many threads of execution simultaneously. To help performance, GlassFish Server maintains one or more thread pools. It is possible to assign specific thread pools to connector modules, to network listeners, or to the Object Request Broker (ORB).

One thread pool can serve multiple connector modules and enterprise beans. *Request threads* handle user requests for application components. When GlassFish Server receives a request, it assigns the request to a free thread from the thread pool. The thread executes the client's requests and returns results. For example, if the request needs to use a system resource that is currently busy, the thread waits until that resource is free before allowing the request to use that resource.

Configuring Thread Pools

You can specify the minimum and maximum number of threads that are reserved for requests from applications. The thread pool is dynamically adjusted between these two values.

The following topics are addressed here:

- [“To Create a Thread Pool” on page 138](#)
- [“To List Thread Pools” on page 139](#)
- [“To Update a Thread Pool” on page 139](#)
- [“To Delete a Thread Pool” on page 140](#)

▼ To Create a Thread Pool

Use the `create-threadpool` subcommand in remote mode to create a thread pool.

The minimum thread pool size that is specified signals the server to allocate at least that many threads in reserve for application requests. That number is increased up to the maximum thread pool size that is specified. Increasing the number of threads available to a process allows the process to respond to more application requests simultaneously.

If one resource adapter or application occupies all the GlassFish Server threads, thread starvation might occur. You can avoid this by dividing the GlassFish Server threads into different thread pools.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Create a new thread pool by using the `create-threadpool(1)` subcommand.

Information about options for the subcommand is included in this help page.

3 To apply your changes, restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

Note – Restart is not necessary for thread pools used by the web container.

Example 5–1 Creating a Thread Pool

This example creates `threadpool-1`.

```
asadmin> create-threadpool --maxthreadpoolsize 100
--minthreadpoolsize 20 --idletimeout 2 --workqueues 100 threadpool-1
Command create-threadpool executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-threadpool` at the command line.

▼ To List Thread Pools

Use the `list-threadpools` subcommand in remote mode to list the existing thread pools.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the existing thread pools by using the `list-threadpools(1)` subcommand.**

Example 5-2 Listing Thread Pools

This example lists the existing thread pools.

```
asadmin> list-threadpools
threadpool-1
Command list-threadpools executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-threadpools` at the command line.

▼ To Update a Thread Pool

Use the `set` subcommand to update the values for a specified thread pool.

- 1 **List the existing thread pools by using the `list-threadpools(1)` subcommand.**
- 2 **Modify the values for a thread pool by using the `set(1)` subcommand.**
The thread pool is identified by its dotted name.
- 3 **To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Note – Restart is not necessary for thread pools used by the web container.

Example 5-3 Updating a Thread Pool

This example sets the `max-thread-pool-size` from its previous value to 8.

```
asadmin> set server.thread-pools.thread-pool.http-thread-pool.max-thread-pool-size=8
Command set executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help set` at the command line.

▼ To Delete a Thread Pool

Use the `delete-threadpool` subcommand in remote mode to delete an existing thread pool. Deleting a thread pool will fail if that pool is referenced by a network listener.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the existing thread pools by using the `list-threadpools(1)` subcommand.**
- 3 **Delete the specified thread pool by using the `delete-threadpool(1)` subcommand.**
- 4 **To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Note – Restart is not necessary for thread pools used by the web container.

Example 5–4 Deleting a Thread Pool

This example deletes `threadpool-1`.

```
asadmin> delete-threadpool threadpool-1
Command delete-threadpool executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-threadpool` at the command line.

Administering Web Applications

This chapter explains how to administer web applications in the GlassFish Server Open Source Edition 3.1 environment.

The following topics are addressed here:

- “Invoking a Servlet by Alternate Means” on page 141
- “Changing Log Output for a Servlet” on page 142
- “Defining Global Features for Web Applications” on page 142
- “Redirecting a URL” on page 143
- “Administering mod_jk” on page 144

Instructions for accomplishing some of these tasks by using the Administration Console are contained in the Administration Console online help.

Invoking a Servlet by Alternate Means

You can call a servlet deployed to GlassFish Server by using a URL in a browser or embedded as a link in an HTML or JSP file. The format of a servlet invocation URL is as follows:

`http://server:port/context-root/servlet-mapping?name=value`

The following table describes each URL section.

TABLE 6-1 URL Fields for Servlets Within an Application

URL element	Description
<i>server:port</i>	<p>The IP address (or host name) and optional port number.</p> <p>To access the default web module for a virtual server, specify only this URL section. You do not need to specify the <i>context-root</i> or <i>servlet-name</i> unless you also wish to specify name-value parameters.</p>

TABLE 6-1 URL Fields for Servlets Within an Application (Continued)

URL element	Description
<i>context-root</i>	For an application, the context root is defined in the <code>context-root</code> element of the <code>application.xml</code> , <code>sun-application.xml</code> , or <code>sun-web.xml</code> file. For an individually deployed web module, the context root is specified during deployment. For both applications and individually deployed web modules, the default context root is the name of the WAR file minus the <code>.war</code> suffix.
<i>servlet-mapping</i>	The <code>servlet-mapping</code> as configured in the <code>web.xml</code> file.
<i>?name=value...</i>	Optional request parameters.

EXAMPLE 6-1 Invoking a Servlet With a URL

In this example, `localhost` is the host name, `MortPages` is the context root, and `calcMortgage` is the servlet mapping.

```
http://localhost:8080/MortPages/calcMortgage?rate=8.0&per=360&bal=180000
```

EXAMPLE 6-2 Invoking a Servlet From Within a JSP File

To invoke a servlet from within a JSP file, you can use a relative path. For example:

```
<jsp:forward page="TestServlet"/><jsp:include page="TestServlet"/>
```

Changing Log Output for a Servlet

`ServletContext.log` messages are sent to the server log. By default, the `System.out` and `System.err` output of servlets are sent to the server log. During startup, server log messages are echoed to the `System.err` output. Also by default, there is no Windows-only console for the `System.err` output.

You can change these defaults using the Administration Console Write to System Log box. If this box is checked, `System.out` output is sent to the server log. If it is unchecked, `System.out` output is sent to the system default location only.

Defining Global Features for Web Applications

You can use the `default-web.xml` file to define features such as filters and security constraints that apply to all web applications.

For example, directory listings are disabled by default for added security. To enable directory listings in your domain's `default-web.xml` file, search for the definition of the servlet whose `servlet-name` is equal to `default`, and set the value of the `init-param` named `listings` to `true`. Then restart the server.

```
<init-param>
  <param-name>listings</param-name>
  <param-value>true</param-value>
</init-param>
```

If `listings` is set to `true`, you can also determine how directory listings are sorted. Set the value of the `init-param` named `sortedBy` to `NAME`, `SIZE`, or `LAST_MODIFIED`. Then restart the server.

```
<init-param>
  <param-name>sortedBy</param-name>
  <param-value>LAST_MODIFIED</param-value>
</init-param>
```

The `mime-mapping` elements in `default-web.xml` are global and inherited by all web applications. You can override these mappings or define your own using `mime-mapping` elements in your web application's `web.xml` file. For more information about `mime-mapping` elements, see the Servlet specification.

You can use the Administration Console to edit the `default-web.xml` file, or edit the file directly using the following steps.

▼ To Use the default-web.xml File

- 1 Place the JAR file for the filter, security constraint, or other feature in the *domain-dir/lib* directory.
- 2 Edit the *domain-dir/config/default-web.xml* file to refer to the JAR file.
- 3 To apply your changes, restart GlassFish Server.
See [“To Restart a Domain” on page 116](#).

Redirecting a URL

You can specify that a request for an old URL be treated as a request for a new URL. This is called *redirecting* a URL.

To specify a redirected URL for a virtual server, use the `redirect_n` property, where *n* is a positive integer that allows specification of more than one. Each of these `redirect_n` properties is inherited by all web applications deployed on the virtual server.

The value of each `redirect_n` property has two components which can be specified in any order:

- The first component, `from`, specifies the prefix of the requested URI to match.
- The second component, `url-prefix`, specifies the new URL prefix to return to the client. The `from` prefix is replaced by this URL prefix.

EXAMPLE 6-3 Redirecting a URL

This example redirects from `dummy` to `etude`:

```
<property name="redirect_1" value="from=/dummy url-prefix=http://etude"/>
```

Administering mod_jk

The Apache Tomcat Connector `mod_jk` can be used to connect the web container with web servers such as Apache HTTP Server. By using `mod_jk`, which comes with GlassFish Server, you can front GlassFish Server with Apache HTTP Server.

You can also use `mod_jk` directly at the JSP/servlet engine for load balancing. For more information about configuring `mod_jk` and Apache HTTP Server for load balancing with GlassFish Server 3.1 refer to Chapter 7, “Configuring HTTP Load Balancing,” in *GlassFish Server Open Source Edition 3.1 High Availability Administration Guide*.

The following topics are addressed here:

- [“To Enable `mod_jk`” on page 144](#)
- [“To Load Balance Using `mod_jk` and GlassFish Server” on page 146](#)
- [“To Enable SSL Between the `mod_jk` Load Balancer and the Browser” on page 148](#)
- [“To Enable SSL Between the `mod_jk` Load Balancer and GlassFish Server” on page 149](#)

▼ To Enable mod_jk

You can front GlassFish Server with Apache HTTP Server by enabling the `mod_jk` protocol for one of GlassFish Server's network listeners, as described in this procedure. A typical use for `mod_jk` would be to have Apache HTTP Server handle requests for static resources, while having requests for dynamic resources, such as servlets and JavaServer Pages (JSPs), forwarded to, and handled by the GlassFish Server back-end instance.

When you use the `jk-enabled` attribute of the network listener, you do not need to copy any additional JAR files into the `/lib` directory. You can also create JK connectors under different virtual servers by using the network listener attribute `jk-enabled`.

1 Install Apache HTTP Server and `mod_jk`.

- For information on installing Apache HTTP Server, see <http://httpd.apache.org/docs/2.2/install.html>.
- For information on installing mod_jk, see http://tomcat.apache.org/connectors-doc/webserver_howto/apache.html.

2 Configure the following files:

- `apache2/conf/httpd.conf`, the main Apache configuration file
- `apache2/conf/workers.properties` or `domain-dir/conf/glassfish-jk.properties` (to use non-default values of attributes described at <http://tomcat.apache.org/tomcat-5.5-doc/config/ajp.html>)

If you use both the `workers.properties` file and the `glassfish-jk.properties` file, the file referenced by `httpd.conf` first takes precedence.

3 Start Apache HTTP Server (`httpd`).

4 Start GlassFish Server with at least one web application deployed.

In order for the `mod_jk`-enabled network listener to start listening for requests, the web container must be started. Normally, this is achieved by deploying a web application.

5 Create an HTTP listener by using the `create-http-listener(1)` subcommand.

Use the following format:

```
asadmin> create-http-listener --listenerport 8009
--listeneraddress 0.0.0.0 --defaultvs server listener-name
```

where *listener-name* is the name of the new listener.

6 Enable `mod_jk` by using the `set(1)` subcommand.

```
asadmin> create-network-listener --protocol http-listener-1 \
--listenerport 8009 --jkenabled true jk-connector
```

```
asadmin> set server-config.network-config.network-listeners.network-listener.\
jk-connector.jk-configuration-file=domain-dir/config/glassfish-jk.properties
```

7 If you are using the `glassfish-jk.properties` file and not referencing it in the `httpd.conf` file, point to the properties file by using the `create-jvm-options(1)` subcommand.

Use the following format:

```
asadmin> create-jvm-options -Dcom.sun.enterprise.web.connector.enableJK.propertyFile=
domain-dir/config/glassfish-jk.properties
```

8 To apply your changes, restart GlassFish Server.

See “To Restart a Domain” on page 116.

Example 6-4 httpd.conf File for mod_jk

This example shows an httpd.conf file that is set for mod_jk. In this example, mod_jk used as a simple pass-through.

```
LoadModule jk_module /usr/lib/httpd/modules/mod_jk.so
JkWorkersFile /etc/httpd/conf/worker.properties
# Where to put jk logs
JkLogFile /var/log/httpd/mod_jk.log
# Set the jk log level [debug/error/info]
JkLogLevel debug
# Select the log format
JkLogStampFormat "[%a %b %d %H:%M:%S %Y] "
# JkOptions indicate to send SSL KEY SIZE,
JkOptions +ForwardKeySize +ForwardURICompat -ForwardDirectories
# JkRequestLogFormat set the request format
JkRequestLogFormat "%w %V %T"
# Send all jsp requests to GlassFish
JkMount /*.jsp worker1
# Send all glassfish-test requests to GlassFish
JkMount /glassfish-test/* worker1
```

Example 6-5 workers.properties File for mod_jk

This example shows a workers.properties or glassfish-jk.properties file that is set for mod_jk. This workers.properties file is referenced in Example [Example 6-4](#).

```
# Define 1 real worker using ajp13
worker.list=worker1
# Set properties for worker1 (ajp13)
worker.worker1.type=ajp13
worker.worker1.host=localhost
worker.worker1.port=8009
```

See Also For more information on Apache, see <http://httpd.apache.org/>.

For more information on Apache Tomcat Connector, see <http://tomcat.apache.org/connectors-doc/index.html>.

▼ To Load Balance Using mod_jk and GlassFish Server

Load balancing is the process of dividing the amount of work that a computer has to do between two or more computers so that more work gets done in the same amount of time. Load balancing can be configured with or without security.

In order to support stickiness, the Apache mod_jk load balancer relies on a jvmRoute system property that is included in any JSESSIONID received by the load balancer. This means that every GlassFish Server instance that is front-ended by the Apache load balancer must be configured with a unique jvmRoute system property.

1 On each of the instances, perform the steps in “To Enable mod_jk” on page 144.

If your instances run on the same machine, you must choose different JK ports. The ports must match `worker.worker*.port` in your `workers.properties` file. See the properties file in [Example 6–5](#).

2 On each of the instances, create the `jvmRoute` system property of GlassFish Server by using the `create-jvm-options(1)` subcommand.

Use the following format:

```
asadmin> create-jvm-options "-DjvmRoute=/instance-worker-name"/
```

where *instance-worker-name* is the name of the worker that you defined to represent the instance in the `workers.properties` file.

3 To apply your changes, restart Apache HTTP Server and GlassFish Server.

Example 6–6 `httpd.conf` File for Load Balancing

This example shows an `httpd.conf` file that is set for load balancing.

```
LoadModule jk_module /usr/lib/httpd/modules/mod_jk.so
JkWorkersFile /etc/httpd/conf/worker.properties
# Where to put jk logs
JkLogFile /var/log/httpd/mod_jk.log
# Set the jk log level [debug/error/info]
JkLogLevel debug
# Select the log format
JkLogStampFormat "[%a %b %d %H:%M:%S %Y] "
# JkOptions indicate to send SSL KEY SIZE,
JkOptions +ForwardKeySize +ForwardURICompat -ForwardDirectories
# JkRequestLogFormat set the request format
JkRequestLogFormat "%w %V %T"
# Send all jsp requests to GlassFish
JkMount /*.jsp worker1
# Send all glassfish-test requests to GlassFish
JkMount /glassfish-test/* loadbalancer
```

Example 6–7 `workers.properties` File for Load Balancing

This example shows a `workers.properties` or `glassfish-jk.properties` file that is set for load balancing. The `worker.worker*.port` should match with JK ports you created.

```
worker.list=worker1,worker2,loadbalancer
worker.worker1.type=ajp13
worker.worker1.host=localhost
worker.worker1.port=8009
worker.worker1.lbfactor=1
worker.worker1.socket_keepalive=1
worker.worker1.socket_timeout=300
worker.worker2.type=ajp13
worker.worker2.host=localhost
```

```
worker.worker2.port=8010
worker.worker2.lbfactor=1
worker.worker2.socket_keepalive=1
worker.worker2.socket_timeout=300
worker.loadbalancer.type=lb
worker.loadbalancer.balance_workers=worker1,worker2
```

▼ To Enable SSL Between the mod_jk Load Balancer and the Browser

To activate security for mod_jk on GlassFish Server, you must first generate a Secure Socket Layer (SSL) self-signed certificate on the Apache HTTP Server with the mod_ssl module. The tasks include generating a private key, a Certificate Signing Request (CSR), a self-signed certificate, and configuring SSL-enabled virtual hosts.

Before You Begin The mod_jk connector must be enabled.

1 Generate the private key as follows:

```
openssl genrsa -des3 -rand file1:file2:file3:file4:file5 -out server.key 1024
```

where file1:file2: and so on represents the random compressed files.

2 Remove the pass-phrase from the key as follows:

```
openssl rsa -in server.key -out server.pem
```

3 Generate the CSR as follows:

```
openssl req -new -key server.pem -out server.csr
```

Enter the information you are prompted for.

4 Generate a temporary certificate as follows:

```
openssl x509 -req -days 60 -in server.csr -signkey server.pem -out server.crt
```

This temporary certificate is good for 60 days.

5 Create the http-ssl.conf file under the /etc/apache2/conf.d directory.

6 In the http-ssl.conf file, add one of the following redirects:

- Redirect a web application, for example, JkMount /hello/* worker1.
- Redirect all requests, for example, JkMount /* worker1.

```
# Send all jsp requests to GlassFish
JkMount /*.jsp worker1
# Send all glassfish-test requests to GlassFish
JkMount /glassfish-test/* loadbalancer
```

Example 6–8 http-ssl.conf File for mod_jk Security

A basic SSL-enabled virtual host will appear in the http-ssl.conf file. In this example, all requests are redirected.

```
Listen 443
<VirtualHost _default_:443>
SSLEngine on
SSLCipherSuite ALL:!ADH:!EXP56:RC4+RSA:+HIGH:+MEDIUM:+LOW:+SSLv2:+EXP:+eNULL
SSLCertificateFile "/etc/apache2/2.2/server.crt"
SSLCertificateKeyFile "/etc/apache2/2.2/server.pem"
JkMount /* worker1
</VirtualHost>
```

▼ To Enable SSL Between the mod_jk Load Balancer and GlassFish Server

Before You Begin The self-signed certificate must be configured.

- 1 Perform the steps in [“To Enable mod_jk” on page 144](#).

- 2 Start another GlassFish Server with at least one web application deployed.

In order for the mod_jk-enabled network listener to start listening for requests, the web container must be started. Normally, this is achieved by deploying a web application.

- 3 Follow instructions from [“To Configure an HTTP Listener for SSL” on page 304](#) on the mod_jk connector.

Use the following format:

```
asadmin> create-ssl --type http-listener --certname sampleCert new-listener
```

- 4 Add the following directives in the httpd.conf file under the /etc/apache2/conf.d directory:

```
# Should mod_jk send SSL information (default is On)
JkExtractSSL On
# What is the indicator for SSL (default is HTTPS)
JkHTTPSIndicator HTTPS
# What is the indicator for SSL session (default is SSL_SESSION_ID)
JkSESSIONIndicator SSL_SESSION_ID
# What is the indicator for client SSL cipher suit (default is SSL_CIPHER)
JkCIPHERIndicator SSL_CIPHER
# What is the indicator for the client SSL certificated? (default is SSL_CLIENT_CERT)
JkCERTSIndicator SSL_CLIENT_CERT
```

- 5 To apply your changes, restart Apache HTTP Server and GlassFish Server.

Administering the Logging Service

This chapter provides instructions on how to configure logging and how to view log information in the GlassFish Server Open Source Edition 3.1 environment.

The following topics are addressed here:

- [“About Logging” on page 151](#)
- [“Configuring the Logging Service” on page 156](#)
- [“Viewing Log Records” on page 167](#)

Instructions for accomplishing these tasks and editing logging service properties in the Administration Console are available from the Administration Console online help.

About Logging

Logging is the process by which GlassFish Server Open Source Edition captures information about events that occur, such as configuration errors, security failures, or server malfunction. This data is recorded in log files and is usually the first source of information when problems occur. Analyzing the log files can help you to determine the health of the server.

Although application components can use the Apache Commons Logging Library to record messages, the platform standard JSR 047 API is recommended for better log configuration.

The following topics are addressed here:

- [“Log Files” on page 152](#)
- [“Logger Namespaces” on page 154](#)
- [“Logging Targets” on page 155](#)
- [“Logging Properties” on page 155](#)

Log Files

GlassFish Server Open Source Edition log records are captured in one of two general types of log files:

- Server log files, which capture information about the operation of a server instance running in the domain. Each instance, managed server instance (that is, each cluster member), and the domain administration server (DAS) has an individual server log file.
- Cluster log files, which capture information about the operation of a cluster instance, if one or more are configured in the domain. Each managed server instance that is a member of a cluster has a cluster log file in addition to a server log file. However, the contents of the cluster log file may differ from one instance to another depending on factors such as how instances are apportioned in the cluster, applications running on them, how load balancing is configured, and failover state.

The following topics are addressed here:

- [“Log File Names and Locations” on page 152](#)
- [“Log Records” on page 153](#)
- [“Log Rotation” on page 154](#)

Log File Names and Locations

In an GlassFish Server Open Source Edition domain, log files have the following names and locations by default:

Instance	Default Log File Name and Location
DAS	<i>domain-dir</i> /logs/server.log
Each server instance	<i>instance-dir</i> /logs/server.log
Cluster instance	<i>instance-dir</i> /logs/cluster.log

For example, in a domain hosted on a given machine that includes a cluster with two managed servers (ClusterServer1 and ClusterServer1) and a standalone instance (StandaloneServer), the log files might be arranged in the following directory structure. In this directory structure, the server.log file for the DAS is located in *domain-dir*/logs.

```
as-install-parent directory
  glassfish/
    domains/
      domain-name/
        logs/
          server.log
    nodes/
      hostname/
        ClusterServer1/
```



```

        logs/
        server.log
        cluster.log
ClusterServer2/
    logs/
    server.log
    cluster.log
StandaloneServer/
    logs/
    server.log

```

You can change the default name or location of a log file by modifying the logging properties file for the corresponding instance, described in [“To Change the Name and Location of the Log File” on page 157](#).

Log Records

GlassFish Server Open Source Edition log records follow a uniform format:

```
[#|yyyy-mm-ddThh:mm:ss.SSS-Z|Log Level|ProductName-Version|LoggerName|Key Value Pairs|Message|#]
```

- [# and #] mark the beginning and end of the record.
- The vertical bar (|) separates the fields of the record.
- *yyyy-mm-ddThh:mm:ss.SSS-Z* represents the date and time that the record was created. For example: `2006-10-21T13:25:53.852-0400`
- *Log Level* represents the log level. You can set any of the following values: SEVERE, WARNING, INFO, CONFIG, FINE, FINER, and FINEST. The default is INFO.
- *ProductName-Version* represents the current version of the GlassFish Server Open Source Edition. For example: `glassfish`
- *LoggerName* represents a hierarchical logger namespace that identifies the source of the log module. For example: `javax.enterprise.system.core`
- *Key Value Pairs* represents pairs of key names and values, typically a thread ID. For example: `_ThreadId=14;`
- *Message* represents the text of the log message. For all GlassFish Server Open Source Edition SEVERE and WARNING messages and for many INFO messages, the message begins with a message ID that consists of a module code and a numerical value. For example: `CORE5004`

The following is an example of a log record:

```
[#|2006-10-21T13:25:53.852-0400|INFO|GlassFish10.0|javax.enterprise.
system.core|_ThreadId=13;|CORE5004: Resource Deployed:
[cr:jms/DurableConnectionFactory]|#]
```

The Administration Console presents log records in a more readable display.

Log Rotation

By default, when a log file grows to 2 MB, GlassFish Server Open Source Edition renames (rotates) the file to incorporate a timestamp and creates a new log file. The log file is renamed as *log-type.log_date*, where *log-type* represents either *server* or *cluster*, and *date* represents the time of rotation.

You can configure the logging service to change the default settings for log file rotation, as explained in [“Setting Log File Rotation” on page 162](#).

Logger Namespaces

GlassFish Server Open Source Edition provides a logger for each of its modules. The following list is an example of the logger namespaces in a server instance as they appear when using the `list-log-levels` subcommand.

```
java.util.logging.ConsoleHandler      <FINEST>
javax.enterprise.resource.corba        <INFO>
javax.enterprise.resource.javamail     <INFO>
javax.enterprise.resource.jdo          <INFO>
javax.enterprise.resource.jms          <INFO>
javax.enterprise.resource.jta          <INFO>
javax.enterprise.resource.resourceadapter <INFO>
javax.enterprise.resource.sqltrace     <INFO>
javax.enterprise.resource.webcontainer.jsf.application <INFO>
javax.enterprise.resource.webcontainer.jsf.config      <INFO>
javax.enterprise.resource.webcontainer.jsf.context     <INFO>
javax.enterprise.resource.webcontainer.jsf.facelets    <INFO>
javax.enterprise.resource.webcontainer.jsf.lifecycle   <INFO>
javax.enterprise.resource.webcontainer.jsf.managedbean <INFO>
javax.enterprise.resource.webcontainer.jsf.renderkit   <INFO>
javax.enterprise.resource.webcontainer.jsf.resource    <INFO>
javax.enterprise.resource.webcontainer.jsf.taglib       <INFO>
javax.enterprise.resource.webcontainer.jsf.timing      <INFO>
javax.enterprise.system.container.cmp      <INFO>
javax.enterprise.system.container.ejb      <INFO>
javax.enterprise.system.container.ejb.mdb  <INFO>
javax.enterprise.system.container.web      <INFO>
javax.enterprise.system.core.classloading  <INFO>
javax.enterprise.system.core.config        <INFO>
javax.enterprise.system.core.naming        <INFO>
javax.enterprise.system.core.security      <INFO>
javax.enterprise.system.core.selfmanagement <INFO>
javax.enterprise.system.core.transaction   <INFO>
javax.enterprise.system                   <INFO>
javax.enterprise.system.tools.admin        <INFO>
javax.enterprise.system.tools.backup       <INFO>
javax.enterprise.system.tools.deployment   <INFO>
javax.enterprise.system.util               <INFO>
javax.enterprise.system.webservices.registry <INFO>
javax.enterprise.system.webservices.rpc    <INFO>
javax.enterprise.system.webservices.saaj   <INFO>
javax                                     <INFO>
```

```
org.apache.catalina      <INFO>
org.apache.coyote        <INFO>
org.apache.jasper        <INFO>
org.jvnet.hk2.osgiadapter <INFO>
```

For information about how to display logger namespaces and log levels, see [“To List Log Levels” on page 159](#).

Logging Targets

Each instance in an GlassFish Server Open Source Edition domain has a dedicated log file, and each instance and cluster has its own logging properties file. To configure logging for an instance or a cluster, GlassFish Server Open Source Edition allows you *target* specific log files or logging properties files when you do the following:

- Set global or module-specific log levels
- Rotate log files or compress them into a ZIP archive
- Change logging property attributes
- List log levels or log attributes

The following subcommands optionally accept a target specification. A target can be a configuration name, server name, cluster name, or instance name, and is specified as either an operand or as a value passed using the `--target` option. If no target is specified when using any of these subcommands, the default target is the DAS.

Subcommand	Description	Target Specification
<code>collect-log-files(1)</code>	Collects all available log files into a ZIP archive.	<code>--target=target-name</code>
<code>list-log-attributes(1)</code>	Lists logging attributes in the logging properties file.	<i>target-name</i> operand
<code>list-log-levels(1)</code>	Lists the loggers in the logging properties file and their log levels.	<i>target-name</i> operand
<code>rotate-log(1)</code>	Rotates the log file by renaming it and creating a new log file to store new messages.	<code>--target=target-name</code>
<code>set-log-attributes(1)</code>	Sets the specified logging attributes in the logging properties file.	<code>--target=target-name</code>
<code>set-log-levels(1)</code>	Sets the log level for one or more loggers listed in the logging properties file.	<code>--target=target-name</code>

Logging Properties

The DAS as well as each configuration, instance, and cluster has its own set of logging properties that are maintained in individual configuration files. A logging properties file is named `logging.properties` and includes the following information:

- Log file name and location
- Logger names and levels
- Properties for custom handlers
- Log rotation and logger format properties

By default in an GlassFish Server Open Source Edition domain, logging properties files are created in the following locations:

Target	Default Location of Logging Properties File
DAS	<i>domain-dir/config/logging.properties</i>
A configuration	<i>domain-dir/config/config-name/logging.properties</i> , where <i>config-name</i> represents the name of a configuration that is shared by one or more instances or clusters.
An instance	<i>domain-dir/config/instance-name-config/logging.properties</i> , where <i>instance-name</i> represents the name of the instance.
A cluster	<i>domain-dir/config/cluster-name-config/logging.properties</i> , where <i>cluster-name</i> represents the name of the cluster.

For information about configuring logging properties, see [“Configuring the Logging Service” on page 156](#).

Configuring the Logging Service

This section contains the following topics:

- [“Changing the Name and Location of Logging Service Files” on page 156](#)
- [“Setting Log Levels” on page 159](#)
- [“Setting Log File Rotation” on page 162](#)
- [“Adding a Custom Logging Handler” on page 166](#)

Changing the Name and Location of Logging Service Files

This section explains how to change the name and location of the following logging service files:

- Log file
- Logging properties file

▼ To Change the Name and Location of the Log File

To change the name and location of the log file, first use the `list-log-attributes` subcommand to obtain the current log attribute setting for the log file name and location. Then use the `set-log-attributes` subcommand to specify the new name or location. The default target for these two subcommands is the DAS. However, you can optionally specify one of the following targets:

- Configuration name — to target all instances or clusters that share a specific configuration name.
- Server name — to target only a specific server.
- Instance name — to target only a specific instance.
- Cluster name — to target only a specific cluster.

1 Ensure that the target server or cluster is running.

Remote subcommands require a running server.

2 Use the `list-log-attributes(1)` subcommand in remote mode to obtain the current log attribute settings.

The name and location of the log file is set with the `com.sun.enterprise.server.logging.GFFileHandler.file` attribute of the logging properties file. Optionally you can target a configuration, server, instance, or cluster. If you do not specify a target, the log attribute settings for the DAS are displayed.

3 Use the `set-log-attributes(1)` subcommand in remote mode to define a custom name or location of the log file.

If you do not specify a target, the log file for the DAS is targeted by default. If you target a cluster, the name of the cluster log file for each member instance can be changed (the server log file name cannot).

Example 7-1 Changing the Name and Location of a Cluster's Log File

This example changes the name of the cluster log file for Cluster1 to `cluster1.log`. Cluster1 has two server instances: `ClusterServer1` and `ClusterServer2`.

```
asadmin> list-log-attributes Cluster1
com.sun.enterprise.server.logging.GFFileHandler.alarms <false>
com.sun.enterprise.server.logging.GFFileHandler.file
<${com.sun.aas.instanceRoot}/logs/server.log>
com.sun.enterprise.server.logging.GFFileHandler.flushFrequency <1>
.
.
.
log4j.logger.org.hibernate.validator.util.Version <warn>
Command list-log-attributes executed successfully.
asadmin> set-log-attributes --target Cluster1
```

```
com.sun.enterprise.server.logging.GFFileHandler.file=
${com.sun.aas.instanceRoot}/logs/cluster1.log
com.sun.enterprise.server.logging.GFFileHandler.file
logging attribute set with value ${com.sun.aas.instanceRoot}/logs/cluster1.log
These logging attributes are set for Cluster1.
ClusterServer1 :
com.sun.enterprise.server.logging.GFFileHandler.file
logging attribute set with value ${com.sun.aas.instanceRoot}/logs/cluster1.log
These logging attributes are set for Cluster1.

ClusterServer2 :
com.sun.enterprise.server.logging.GFFileHandler.file
logging attribute set with value ${com.sun.aas.instanceRoot}/logs/cluster1.log
These logging attributes are set for Cluster1.

Command set-log-attributes executed successfully.
```

See Also You can view the full syntax and options of these subcommands by typing `asadmin help list-log-levels` and `asadmin help set-log-attributes` at the command line.

▼ To Change the Name and Location of the Logging Properties File

You can set the name and location of the logging properties file by setting the `java.util.logging.config.file` system property. By setting this system property, you can have a single logging properties file that is used by all instances running on the same host.

Note – Setting the `java.util.logging.config.file` system property causes all other GlassFish Server Open Source Edition logging properties files on the host to be overridden.

1 Set the `java.util.logging.config.file` system property.

For example, you can use the following `java` command:

```
java -Djava.util.logging.config.file=properties_file
```

Alternatively, you can use the Administration Console to set this system property.

2 To apply your change, restart GlassFish Server Open Source Edition.

Example 7–2 Setting the `java.util.logging.config.file` System Property

The following example changes the location of the logging properties file to `/space/mylogging/logging.properties`:

```
java -Djava.util.logging.config.file=/space/mylogging/logging.properties
```

Setting Log Levels

The *log level* determines the granularity of the message that is logged, from error only (SEVERE) to detailed debug (FINEST). The following values apply: SEVERE, WARNING, INFO, CONFIG, FINE, FINER, and FINEST. These log levels are hierarchically inclusive, which means that if you set a particular log level, such as INFO, the messages that have log levels above that level (SEVERE and WARNING) are also included. If you set the log level to the lowest level, FINEST, your output includes all the messages in the file. The default setting is INFO.

You can list current log levels of all loggers specified in the logging properties file. In some cases, loggers that have not been created by the respective containers will also appear in the list.

You can set log levels that are global or logger-specific. When you set a global log level, the log level goes into effect for all loggers. If you set the log level for a specific logger that is different from the global log level, the logger-specific setting takes precedence. In addition, when setting log levels, you can target a configuration, server, instance, or cluster.

Because setting log levels is a dynamic operation, you do not need to restart GlassFish Server Open Source Edition for changes to take effect.

Setting either global or logger-specific log levels is done by using the `set -log -levels` subcommand. Listing log levels is done by using the `list -log -levels` subcommand.

The following topics are addressed here:

- [“To List Log Levels” on page 159](#)
- [“To Set the Global Log Level” on page 160](#)
- [“To Set Module Log Levels” on page 161](#)

▼ To List Log Levels

GlassFish Server Open Source Edition provides the means to list all loggers and their log levels. Listing the loggers provides a convenient means to view current loggers and log levels either prior to or after making log level changes.

Use the `list -log -levels` subcommand in remote mode to list the modules and their current log levels. The default target for this subcommand is the DAS. However, you can optionally specify one of the following targets:

- Configuration name — to target all instances or clusters that share a specific configuration name.
- Server name — to target a specific server.
- Instance name — to target a specific instance.
- Cluster name — to target a specific cluster.

1 Ensure that the DAS is running.

Remote subcommands require a running server.

2 List the existing module loggers and log levels by using the `list-log-levels(1)` subcommand.

Example 7-3 Listing Logger Levels for Modules

This example shows a partial list of the existing loggers and their log levels in the DAS.

```
asadmin> list-log-levels
javax.enterprise.system.container.cmp <INFO>
javax.enterprise.system.tools.admin <INFO>
java.util.logging.ConsoleHandler <FINEST>
javax.enterprise.system.container.web <INFO>
javax.enterprise.system.util <INFO>
javax.enterprise.resource.webcontainer.jsf.timing <INFO>
javax <INFO>
javax.enterprise.resource.corba <INFO>
...
Command list-log-levels executed successfully.
```

Example 7-4 Listing Log Levels for an Instance

This example shows a partial list of the loggers and log levels for the instance `MyServer2`.

```
asadmin> list-log-levels MyServer2
java.util.logging.ConsoleHandler <FINEST>
javax.enterprise.resource.corba <INFO>
javax.enterprise.resource.javamail <INFO>
javax.enterprise.resource.jdo <INFO>
javax.enterprise.resource.jms <INFO>
javax.enterprise.resource.jta <INFO>
javax.enterprise.resource.resourceadapter <INFO>
javax.enterprise.resource.sqltrace <FINE>
...
Command list-log-levels executed successfully.
```

See Also You can view the full syntax and options of the subcommand by typing `asadmin help list-log-levels` at the command line.

▼ To Set the Global Log Level

The *global log level* specifies the events that are logged across all loggers. The default level for messages output to the console is `INFO` (which also includes `SEVERE` and `WARNING` messages).

Use the `set-log-levels` subcommand in remote mode to set the global log level. The default target for this subcommand is the DAS. However, you can optionally specify one of the following targets using the `--target` option:

- Configuration name — to target all instances or clusters that share a specific configuration name.
- Server name — to target a specific server.
- Instance name — to target a specific instance.

- Cluster name — to target a specific cluster.

- 1 **Ensure that the target server or cluster is running.**
- 2 **Set the global log level by using the `set-log-levels(1)` subcommand, specifying the log level of the `java.util.logging.ConsoleHandler` logger.**

The `ConsoleHandler` has a separate log level setting that limits the messages that are displayed. For example:

```
java.util.logging.ConsoleHandler <FINEST>
```

Example 7-5 Changing the Global Log Level for All Module Loggers

By setting the log level of the `ConsoleHandler`, you set the global log level for all loggers. This example sets the global log level in the DAS to `INFO`:

```
asadmin> set-log-levels java.util.logging.ConsoleHandler=INFO
java.util.logging.ConsoleHandler package set with log level INFO.
These logging levels are set for server.
```

Command `set-log-levels` executed successfully.

See Also You can view the full syntax and options of the subcommand by typing `asadmin help set-log-levels` at the command line.

▼ To Set Module Log Levels

A *module log level* specifies the events that are logged for a particular logger. The default level for messages output to the console is `INFO` (which also includes `SEVERE` and `WARNING` messages). The global log level is overridden by a module-specific log level.

By default, the module log level is set to `FINE`. The lines for the loggers in the logging properties file might look like this (the modules are indicated in **bold**):

```
javax.enterprise.system.tools.level=FINE
javax.enterprise.system.container.ejb.level=FINE
javax.enterprise.system.core.security.level=FINE
javax.enterprise.system.tools.admin.level=FINE
javax.enterprise.level=FINE
javax.enterprise.system.container.web.level=FINE
```

Because setting log levels is a dynamic operation, you do not need to restart GlassFish Server Open Source Edition for changes to take effect.

- 1 **Ensure that the target server or cluster is running.**
Remote subcommands require a running server.
- 2 **List the existing module loggers and their log levels by using the `list-log-levels(1)` subcommand.**

3 Set the log level for a module by using the `set-log-levels(1)` subcommand.

Your choices are SEVERE, WARNING, INFO, CONFIG, FINE, FINER, and FINEST.

Example 7-6 Setting the Log Level for a Module Logger

This example sets the log level for the web container logger to WARNING on the target instance `ManagedServer1`:

```
asadmin> set-log-levels --target ManagedServer1
javax.enterprise.system.container.web=WARNING
javax.enterprise.system.container.web package set with log level WARNING.
These logging levels are set for ManagedServer1.
ManagedServer1 :
javax.enterprise.system.container.web package set with log level WARNING.
These logging levels are set for ManagedServer1.
```

Command `set-log-levels` executed successfully.

Example 7-7 Setting Log Levels for Multiple Loggers

The following example sets the log level for security and web container loggers in the DAS.

```
asadmin> set-log-levels javax.enterprise.system.core.security=FINE:
javax.enterprise.system.container.web=WARNING
javax.enterprise.system.container.web package set with log level WARNING.
javax.enterprise.system.core.security package set with log level FINE.
These logging levels are set for server.
```

Command `set-log-levels` executed successfully.

See Also You can view the full syntax and options of the subcommand by typing `asadmin help set-log-levels` at the command line.

Setting Log File Rotation

As explained in “[Log Files](#)” on [page 152](#), GlassFish Server Open Source Edition by default rotates log files when they reach 2 MB in size. However, you can change the default rotation settings. For example, you can change the file size at which the server rotates the log file or you can configure a server to rotate log files based on a time interval. In addition to changing when rotation occurs, you can also:

- Specify the maximum number of rotated files that can accumulate.
By default, GlassFish Server Open Source Edition does not limit the number of rotated log files that are retained. However, you can set a limit. After the number of log files reaches this limit, subsequent file rotations delete the oldest rotated log file.
- Rotate the log file manually.

A *manual rotation* forces the immediate rotation of the target log file.

Changing the default log rotation settings is done using the `set-log-attributes` subcommand, and rotating log files manually is done using the `rotate-log` subcommand, as explained in the following sections:

- [“To Change the Rotation File Size” on page 163](#)
- [“To Change the File Rotation Interval” on page 164](#)
- [“To Change the Limit Number of Retained Files” on page 164](#)
- [“To Rotate Log Files Manually” on page 165](#)

▼ To Change the Rotation File Size

Use the `set-log-attributes` subcommand in remote mode to change the log rotation file size. The default target of this subcommand is the DAS. Optionally, you can target a configuration, server, instance, or cluster. The minimum size that can be set is 500 KB.

- 1 **Ensure that the target server or cluster is running.**
- 2 **Change the rotation file size limit by using the `set-log-attributes(1)` subcommand, specifying the following attribute and the desired limit in bytes:**
`com.sun.enterprise.server.logging.GFFileHandler.rotationLimitInBytes=bytes`
- 3 **To apply your change, restart GlassFish Server Open Source Edition.**

Example 7-8 Changing the Rotation Size

The following example sets the log file rotation size to 1 MB for the standalone instance `ManagedServer1`:

```
asadmin> set-log-attributes --target ManagedServer1
com.sun.enterprise.server.logging.GFFileHandler.rotationLimitInBytes=1000000
com.sun.enterprise.server.logging.GFFileHandler.rotationLimitInBytes
logging attribute set with value 1000000.
These logging attributes are set for ManagedServer1.
ManagedServer1 :
com.sun.enterprise.server.logging.GFFileHandler.rotationLimitInBytes
logging attribute set with value 1000000.
These logging attributes are set for ManagedServer1.

Command set-log-attributes executed successfully.
```

See Also You can view the full syntax and options of the subcommand by typing `asadmin help set-log-attributes` at the command line.

▼ To Change the File Rotation Interval

Use the `set-log-attributes` subcommand in remote mode to change the log file rotation time limit interval. The default target of this subcommand is the DAS. Optionally, you can target a configuration, server, instance, or cluster. The default value is 0.

- 1 Ensure that the target server or cluster is running.
- 2 Change the rotation time limit by using the `set-log-attributes(1)` subcommand, specifying the following attribute and the desired limit in minutes:

```
com.sun.enterprise.server.logging.GFFileHandler.rotationTimelimitInMinutes=minutes
```

- 3 To apply your change, restart GlassFish Server Open Source Edition.

Example 7–9 Changing the Rotation Interval

The following example sets the log file rotation time limit for the cluster `Cluster1`, which has the instances `ClusterServer1` and `ClusterServer2`.

```
asadmin> set-log-attributes --target Cluster1
com.sun.enterprise.server.logging.GFFileHandler.rotationTimelimitInMinutes=10
com.sun.enterprise.server.logging.GFFileHandler.rotationTimelimitInMinutes
logging attribute set with value 10.
These logging attributes are set for Cluster1.
ClusterServer1 :
com.sun.enterprise.server.logging.GFFileHandler.rotationTimelimitInMinutes
logging attribute set with value 10.
These logging attributes are set for Cluster1.

ClusterServer2 :
com.sun.enterprise.server.logging.GFFileHandler.rotationTimelimitInMinutes
logging attribute set with value 10.
These logging attributes are set for Cluster1.

Command set-log-attributes executed successfully.
```

See Also You can view the full syntax and options of the subcommand by typing `asadmin help set-log-attributes` at the command line.

▼ To Change the Limit Number of Retained Files

Use the `set-log-attributes` subcommand in remote mode to change the limit on the number of log files that the server creates to store old log messages. The default target of this subcommand is the DAS. Optionally, you can target a configuration, server, instance, or cluster. The default limit value is 0, which results in no limit placed on the number of rotated log files that are retained.

- 1 Ensure that the target server or cluster is running.

- 2 **Change the limit number of retained log files by using the `set-log-attributes(1)` subcommand, specifying the following attribute and the desired file limit number:**

```
com.sun.enterprise.server.logging.GFFileHandler.maxHistoryFiles=minutes
```

The behavior of the

`com.sun.enterprise.server.logging.GFFileHandler.maxHistoryFiles` attribute is as follows:

- If the property is not set, GlassFish Server Open Source Edition keeps a maximum of 10 rotated log files.
- If the property is set to an invalid number or null, GlassFish Server Open Source Edition keeps a maximum of 10 rotated log files.
- If the property is set to 0, GlassFish Server Open Source Edition retains all rotated log files (that is, no sets no maximum).

- 3 **To apply your change, restart GlassFish Server Open Source Edition.**

Example 7–10 Changing the Limit Number of Retained Files

The following example sets the log limit number of retained log files for the DAS to 10.

```
asadmin> set-log-attributes
com.sun.enterprise.server.logging.GFFileHandler.maxHistoryFiles=10
com.sun.enterprise.server.logging.GFFileHandler.maxHistoryFiles
logging attribute set with value 10.
These logging attributes are set for server.
Command set-log-attributes executed successfully.
```

See Also You can view the full syntax and options of the subcommand by typing `asadmin help set-log-attributes` at the command line.

▼ To Rotate Log Files Manually

You can rotate log files manually by using the `rotate-log` subcommand in remote mode. The default target of this subcommand is the DAS. Optionally, you can target a configuration, server, instance, or cluster. When you use this subcommand, the target log file is immediately moved to a new time-stamped file and a new log file is created.

Because log rotation is a dynamic operation, you do not need to restart GlassFish Server Open Source Edition for changes to take effect.

- 1 **Ensure that the target server or cluster is running.**
- 2 **Rotate log files by using the `rotate-log(1)` subcommand.**

Example 7–11 Rotating Log Files Manually

The following example rotates the `server.log` file for `ManagedServer2` to `server.log_yyyy-mm-ddThh-mm-ss`, where `yyyy-mm-ddThh-mm-ss` represents the time when the file is rotated, and creates a new `server.log` file in the default location.

```
asadmin> rotate-log --target ManagedServer2
Command rotate-log executed successfully.
```

See Also You can view the full syntax and options of the subcommand by typing `asadmin help rotate-log` at the command line.

Adding a Custom Logging Handler

By default, GlassFish Server Open Source Edition log records are captured in a server log file using the format described in “[Log Records](#)” on [page 153](#). However, you may find that you want to log messages to a different location, such as a database or a remote server, or log messages from specific loggers to your own file. This can be done by implementing a custom log handler. This section explains how to add a custom log handler to the GlassFish Server Open Source Edition logging service.

▼ To Add a Custom Log Handler

A comma-separated list of log handlers is installed during startup of the Java Virtual Machine (JVM) host. The default log handler that is provided in the `logging.properties` file, `ConsoleHandler`, is configured as follows:

```
handlers=java.util.logging.ConsoleHandler
```

In GlassFish Server Open Source Edition, the best approach to developing a custom handler is to define a Hundred-Kilobyte Kernel (HK2) component that implements the handler contract. GlassFish Server Open Source Edition registers this handler automatically because it is an HK2 component. There is no task required of the administrator.

To configure a custom handler that is not developed as an HK2 component, add the new handler to the `logging.properties` file after the developer has put the custom handler JAR file into the `domain-dir/lib/ext` directory.

Before You Begin If you set a handler by setting the `handlers` attribute in the logging properties file, the class that extends `java.util.logging.Handler` must be in the server classpath.

1 Ensure that the target server or cluster is running.

Remote subcommands require a running server.

- 2 **Use the `set-log-attributes(1)` subcommand to add the handler to the `handlers` attribute.**
The default target of this subcommand is the DAS. Optionally you can target a configuration, server, instance, or cluster.
- 3 **To apply your changes, restart GlassFish Server Open Source Edition.**
See [“To Restart a Domain” on page 116](#).

Example 7–12 Adding a New Log Handler

This example adds the custom logger `com.example.logging.MyHandler` to the logging properties file of the DAS.

```
asadmin> set-log-attributes
handlers=java.util.logging.ConsoleHandler,com.example.logging.MyHandler
handlers logging attribute set with value
java.util.logging.ConsoleHandler,com.example.logging.MyHandler.
These logging attributes are set for server.
Command set-log-attributes executed successfully.
```

See Also You can view the full syntax and options of the subcommand by typing `asadmin help set-log-attributes` at the command line.

Viewing Log Records

The recommended means for general viewing of logging information is to use the Log Viewer in the Administration Console. The Log Viewer simplifies reading, searching, and filtering log file contents. For instructions, see the Administration Console online help.

GlassFish Server Open Source Edition also allows you to collect log files into a ZIP archive, which provides the means to obtain and view log files for an instance or cluster even when it is not currently running. The following section explains how to collect all available log files for an instance or cluster and compile them into a single ZIP archive, which is done by using the `collect-log-files` subcommand.

▼ To Collect Log Files into a ZIP Archive

Use the `collect-log-files` subcommand in remote mode to collect log files into a ZIP archive. The default target of this subcommand is the DAS. Optionally you can target a configuration, server, instance, or cluster.

- 1 **Ensure that the target server or cluster is running.**
Remote subcommands require a running server.

2 Use the `collect-log-files(1)` subcommand to create the ZIP archive.

The default location in which the ZIP archive is created is the *domain-dir/collected-logs* directory. The `collect-log-files` subcommand allows you to specify a nondefault directory in which the ZIP archive is to be created by using the `--retrieve` option set to `true`, followed by the directory name.

The name of the ZIP file contains the timestamp, as follows:

```
log_yyyy-mm-dd_hh-min-sec.zip
```

Example 7-13 Creating a ZIP Archive

This example shows collecting the log files for the cluster `MyCluster` and compiling them into a ZIP archive in the `/space/output` directory.

```
asadmin> collect-log-files --target MyCluster
--retrieve true /space/output
Log files are downloaded for ClusterServer1.
Log files are downloaded for ClusterServer2.
Created Zip file under /space/output/log_2011-02-10_13-35-25.zip.
Command collect-log-files executed successfully.
```

When the ZIP file created by the preceding command is uncompressed, the following directory structure is created:

```
as-install-parent/
  glassfish/
    domains/
      domain-name/
        collected_logs/
          logs/
            ClusterServer1/
              server.log
            ClusterServer2/
              server.log
```

See Also You can view the full syntax and options of the subcommand by typing `asadmin help collect-log-files` at the command line.

Administering the Monitoring Service

This chapter explains how to monitor the GlassFish Server Open Source Edition 3.1 components and services by using the `asadmin` command-line utility. Instructions for configuring JConsole to monitor GlassFish Server resources are also provided.

The following topics are addressed here:

- “About Monitoring” on page 169
- “Configuring Monitoring” on page 176
- “Viewing Common Monitoring Data” on page 179
- “Viewing Comprehensive Monitoring Data” on page 181
- “Configuring JConsole to View GlassFish Server Monitoring Data” on page 208

Instructions for monitoring by using the Administration Console are contained in the Administration Console online help.

For information on using REST interfaces for monitoring, see “[Using REST Interfaces to Administer GlassFish Server](#)” on page 67.

About Monitoring

Monitoring is the process of reviewing the statistics of a system to improve performance or solve problems. The monitoring service can track and display operational statistics, such as the number of requests per second, the average response time, and the throughput. By monitoring the state of various components and services deployed in GlassFish Server, you can identify performance bottlenecks, predict failures, perform root cause analysis, and ensure that everything is functioning as expected. Data gathered by monitoring can also be useful in performance tuning and capacity planning.

For this release of GlassFish Server, monitoring is exposed in a modular way so that many client modules can access and display the monitoring statistics. These clients include the Administration Console, the `asadmin` utility, AMX, and REST interfaces.

The following topics are addressed here:

- [“How the Monitoring Tree Structure Works” on page 170](#)
- [“About Monitoring for Add-on Components” on page 175](#)
- [“Tools for Monitoring GlassFish Server” on page 176](#)

How the Monitoring Tree Structure Works

A *monitorable object* is a component, subcomponent, or service that can be monitored. GlassFish Server uses a tree structure to track monitorable objects. Because the tree is dynamic, the tree changes as GlassFish Server components are added or removed.

In the tree, a monitorable object can have child objects (nodes) that represent exactly what can be monitored for that object. All child objects are addressed using the dot (.) character as a separator. These constructed names are referred to as *dotted names*. Detailed information on dotted names is available in the `dotted-names(5ASC)` help page.

The following command lists the monitorable child objects of the instance server:

```
asadmin> list --monitor "server.*"
```

```
server.applications
server.connector-service
server.http-service
server.jms-service
server.jvm
server.network
server.orb
server.resources
server.security
server.thread-pool
server.transaction-service
server.web
```

Each object is represented by a dotted name. Dotted names can also address specific attributes in monitorable objects. For example, the `jvm` object has a `memory` attribute with a statistic called `maxheapsize`. The following dotted name addresses the attribute:

```
server.jvm.memory.maxheapsize
```

Although an object is monitorable, it is not necessarily being actively monitored. For instructions on activating monitoring, see [“Configuring Monitoring” on page 176](#).

Tree Structure of Monitorable Objects

Each monitorable object has a hierarchical tree structure. In the tree, a replaceable such as **statistics* represents the name of the attribute that you can show statistics for.

The following node tree hierarchies are addressed here:

- “Applications Tree Hierarchy” on page 171
- “Connector Service Tree Hierarchy” on page 172
- “HTTP Service Tree Hierarchy” on page 172
- “JMS/Container Service Tree Hierarchy” on page 173
- “JVM Tree Hierarchy” on page 173
- “Network Tree Hierarchy” on page 173
- “ORB Tree Hierarchy” on page 174
- “Resources Tree Hierarchy” on page 174
- “Security Tree Hierarchy” on page 174
- “Thread Pool Tree Hierarchy” on page 174
- “Transactions Service Tree Hierarchy” on page 175
- “Web Tree Hierarchy” on page 175

Applications Tree Hierarchy

The applications tree contains the following nodes:

```
server.applications
|--- application1
|   |--- ejb-module-1
|   |   |--- ejb1 *
|   |       |--- bean-cache (for entity/sfsb) *
|   |       |--- bean-pool (for slsb/mdb/entity) *
|   |       |--- bean-methods
|   |           |--- method1 *
|   |           |--- method2 *
|   |           |--- timers (for slsb/entity/mdb) *
|   |   |--- web-module-1
|   |       |--- virtual-server-1 *
|   |           |--- servlet1 *
|   |           |--- servlet2 *
|   |--- standalone-web-module-1
|   |   |--- virtual-server-2 *
|   |       |--- servlet3 *
|   |       |--- servlet4 *
|   |   |--- virtual-server-3 *
|   |       |--- servlet3 *(same servlet on different vs)
|   |       |--- servlet5 *
|   |--- standalone-ejb-module-1
|   |   |--- ejb2 *
|   |       |--- bean-cache (for entity/sfsb) *
|   |       |--- bean-pool (for slsb/mdb/entity) *
|   |       |--- bean-methods
|   |           |--- method1 *
|   |           |--- method2 *
|   |           |--- timers (for slsb/entity/mdb) *
|   |--- jersey-application-1
|   |   |--- jersey
|   |       |--- resources
|   |           resource-0
|   |               hitcount
```

```
                                *statistic  
|--- application2
```

An example dotted name might be:

```
server.applications.hello.server.request.maxtime
```

An example dotted name under the EJB method node might be:

```
server.applications.ejbsfapp1.ejbsfapp1ejbmod1\..jar.SFApp1EJB1
```

An example Jersey dotted name might be:

```
server.applications.helloworld-webapp.jersey.resources.resource-0.hitcount.resourcehitcount-count
```

For available statistics, see [“EJB Statistics” on page 185](#), [“Jersey Statistics” on page 190](#), and [“Web Statistics” on page 205](#).

Connector Service Tree Hierarchy

The connector-service tree holds monitorable attributes for pools such as the connector connection pool. The connector-service tree contains the following nodes:

```
server.connector-service  
    resource-adapter-1  
        connection-pools  
            pool-1  
                work-management
```

An example dotted name might be

```
server.connector-service.resource-adapter-1.connection-pools.pool-1.
```

For available statistics, see [“JMS/Connector Service Statistics” on page 190](#).

HTTP Service Tree Hierarchy

The http-service tree contains the following nodes:

```
server.http-service  
    virtual-server  
        request  
            *statistic  
    _asadmin  
        request  
            *statistic
```

An example dotted name under the *virtual-server* node might be

```
server.http-service.virtual-server1.request.requestcount.
```

For available statistics, see [“HTTP Service Statistics” on page 188](#).

JMS/Container Service Tree Hierarchy

The `jms-service` tree holds monitorable attributes for connection factories (connection pools for resource adapters) and work management (for Message Queue resource adapters). The `jms-service` tree contains the following nodes:

```
server.jms-service
  connection-factories
    connection-factory-1
  work-management
```

An example dotted name under the `connection-factories` node might be `server.jms-service.connection-factories.connection-factory-1` which shows all the statistics for this connection factory. For available statistics, see [“JMS/Connector Service Statistics” on page 190](#).

JVM Tree Hierarchy

The `jvm` tree contains the following nodes:

```
server.jvm
  class-loading-system
  compilation-system
  garbage-collectors
  memory
  operating-system
  runtime
```

An example dotted name under the `memory` node might be `server.jvm.memory.maxheapsize`. For available statistics, see [“JVM Statistics” on page 192](#).

Network Tree Hierarchy

The network statistics apply to the network listener, such as `admin-listener`, `http-listener-1`, `ttp-listener-2`. The network tree contains the following nodes:

```
server.network
  type-of-listener
  keep-alive
    *statistic
  file-cache
    *statistic
  thread-pool
    *statistic
  connection-queue
    *statistic
```

An example dotted name under the `network` node might be `server.network.admin-listener.keep-alive.maxrequests-count`. For available statistics, see [“Network Statistics” on page 196](#).

ORB Tree Hierarchy

The orb tree holds monitorable attributes for connection managers. The orb tree contains the following nodes:

```
server.orb
  transport
    connectioncache
      inbound
        *statistic
      outbound
        *statistic
```

An example dotted name might be `server.orb.transport.connectioncache.inbound.connectionsidle-count`. For available statistics, see [“ORB Statistics \(Connection Manager\)” on page 199](#).

Resources Tree Hierarchy

The resources tree holds monitorable attributes for pools such as the JDBC connection pool and connector connection pool. The resources tree contains the following nodes:

```
server.resources
  connection-pool
    request
      *statistic
```

An example dotted name might be `server.resources.jdbc-connection-pool1.numconnfree.count`. For available statistics, see [“Resource Statistics \(Connection Pool\)” on page 200](#).

Security Tree Hierarchy

The security tree contains the following nodes:

```
server.security
  ejb
    *statistic
  web
    *statistic
  realm
    *statistic
```

An example dotted name might be `server.security.realm.realmcount-starttime`. For available statistics, see [“Security Statistics” on page 202](#).

Thread Pool Tree Hierarchy

The thread-pool tree holds monitorable attributes for connection managers, and contains the following nodes:

```

server.thread-pool
    orb
        threadpool
            thread-pool-1
                *statistic

```

An example dotted name might be `server.thread-pool.ORB.threadpool.thread-pool-1.averagetimeinqueue-current`. For available statistics, see [“Thread Pool Statistics” on page 203](#).

Transactions Service Tree Hierarchy

The transaction-service tree holds monitorable attributes for the transaction subsystem for the purpose of rolling back transactions. The transaction-service tree contains the following nodes:

```

server.transaction-service
    statistic

```

An example dotted name might be `server.transaction-service.activeids`. For available statistics, see [“Transaction Service Statistics” on page 205](#).

Web Tree Hierarchy

The web tree contains the following nodes:

```

server.web
    jsp
        *statistic
    servlet
        *statistic
    session
        *statistic
    request
        *statistic

```

An example dotted name for the servlet node might be `server.web.servlet.activeservletsloadedcount`. For available statistics, see [“Web Module Common Statistics” on page 180](#).

About Monitoring for Add-on Components

An add-on component typically generates statistics that GlassFish Server can gather at runtime. Adding monitoring capabilities enables an add-on component to provide statistics to GlassFish Server in the same way as components that are supplied in the GlassFish Server distributions. As a result, you can use the same administrative interfaces to monitor statistics from any installed GlassFish Server component, regardless of the origin of the component.

Tools for Monitoring GlassFish Server

The following `asadmin` subcommands are provided for monitoring the services and components of GlassFish Server:

- The `enable-monitoring`, `disable-monitoring`, or the `get` and `set` subcommands are used to turn monitoring on or off. For instructions, see [“Configuring Monitoring” on page 176](#).
- The `monitor --type` subcommand is used to display basic data for a particular type of monitorable object. For instructions, see [“Viewing Common Monitoring Data” on page 179](#).
- The `list --monitor` subcommand is used to display the objects that can be monitored with the `monitor` subcommand. For guidelines and instructions, see [“Guidelines for Using the `list` and `get` Subcommands for Monitoring” on page 181](#).
- The `get` subcommand is used to display comprehensive data, such as the attributes and values for a dotted name. The `get` subcommand used with a wildcard parameter displays all available attributes for any monitorable object. For additional information, see [“Guidelines for Using the `list` and `get` Subcommands for Monitoring” on page 181](#).

Configuring Monitoring

By default, the monitoring service is enabled for GlassFish Server, but monitoring for the individual modules is not. To enable monitoring for a module, you change the monitoring level for that module to **LOW** or **HIGH**. You can choose to leave monitoring **OFF** for objects that do not need to be monitored.

- **LOW**. Simple statistics, such as create count, byte count, and so on
- **HIGH**. Simple statistics plus method statistics, such as method count, duration, and so on
- **OFF**. No monitoring, no impact on performance

The following tasks are addressed here:

- [“To Enable Monitoring” on page 176](#)
- [“To Disable Monitoring” on page 177](#)

▼ To Enable Monitoring

Use the `enable-monitoring` subcommand to enable the monitoring service itself, or to enable monitoring for individual modules. Monitoring is immediately activated, without restarting GlassFish Server.

You can also use the `set(1)` subcommand to enable monitoring for a module. Using the `set` command is not a dynamic procedure, so you need to restart GlassFish Server for your changes to take effect.

1 Determine which services and components are currently enabled for monitoring.

```
asadmin> get server.monitoring-service.module-monitoring-levels.*
```

This example output shows that the HTTP service is not enabled (OFF for monitoring), but other objects are enabled:

```
configs.config.server-config.monitoring-service.module-monitoring-levels.web-container=HIGH
configs.config.server-config.monitoring-service.module-monitoring-levels.http-service=OFF
configs.config.server-config.monitoring-service.module-monitoring-levels.jvm=HIGH
```

2 Enable monitoring by using the enable-monitoring(1) subcommand.

Server restart is not required.

Example 8–1 Enabling the Monitoring Service Dynamically

This example enables the monitoring service without affecting monitoring for individual modules.

```
asadmin> enable-monitoring
Command enable-monitoring executed successfully
```

Example 8–2 Enabling Monitoring for Modules Dynamically

This example enables monitoring for the ejb-container module.

```
asadmin> enable-monitoring --level ejb-container=HIGH
Command enable-monitoring executed successfully
```

Example 8–3 Enabling Monitoring for Modules by Using the set Subcommand

This example enables monitoring for the HTTP service by setting the monitoring level to HIGH (you must restart the server for changes to take effect).

```
asadmin> set server.monitoring-service.module-monitoring-levels.http-service=HIGH
Command set executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help enable-monitoring` at the command line.

▼ To Disable Monitoring

Use the `disable-monitoring` subcommand to disable the monitoring service itself, or to disable monitoring for individual modules. Monitoring is immediately stopped, without restarting GlassFish Server.

You can also use the `set(1)` subcommand to disable monitoring for a module. Using the `set` command is not a dynamic procedure, so you need to restart GlassFish Server for your changes to take effect.

1 Determine which services and components currently are enabled for monitoring.

```
asadmin get server.monitoring-service.module-monitoring-levels.*
```

This example output shows that monitoring is enabled for web-container, http-service, and jvm:

```
configs.config.server-config.monitoring-service.module-monitoring-levels.web-container=HIGH
configs.config.server-config.monitoring-service.module-monitoring-levels.http-service=HIGH
configs.config.server-config.monitoring-service.module-monitoring-levels.jvm=HIGH
```

2 Disable monitoring for a service or module by using the `disable-monitoring(1)` subcommand.

Server restart is not required.

Example 8-4 Disabling the Monitoring Service Dynamically

This example disables the monitoring service without changing the monitoring levels for individual modules.

```
asadmin> disable-monitoring
Command disable-monitoring executed successfully
```

Example 8-5 Disabling Monitoring for Modules Dynamically

This example disables monitoring for specific modules. Their monitoring levels are set to OFF.

```
asadmin> disable-monitoring --modules web-container,ejb-container
Command disable-monitoring executed successfully
```

Example 8-6 Disabling Monitoring by Using the `set` Subcommand

This example disables monitoring for the HTTP service (you must restart the server for changes to take effect).

```
asadmin> set server.monitoring-service.module-monitoring-levels.http-service=OFF
Command set executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help disable-monitoring` at the command line.

Viewing Common Monitoring Data

Use the `monitor` subcommand to display basic data on commonly-monitored objects.

- “To View Common Monitoring Data” on page 179
- “Common Monitoring Statistics” on page 180

▼ To View Common Monitoring Data

Use the `--type` option of the `monitor` subcommand to specify the object for which you want to display data, such as `httpListener`, `jvm`, `webmodule`. If you use the `monitor` subcommand without specifying a type, an error message is displayed.

Output from the subcommand is displayed continuously in a tabular format. The `--interval` option can be used to display output at a particular interval (the default is 30 seconds).

Before You Begin A monitorable object must be configured for monitoring before you can display data on the object. See “To Enable Monitoring” on page 176.

- 1 **Determine which type of monitorable object you want to monitor.**
Your choices for 3.1 are `jvm`, `httpListener`, and `webmodule`.
- 2 **Request the monitoring data by using the `monitor(1)` subcommand.**

Example 8-7 Viewing Common Monitoring Data

This example requests common data for type `jvm` on instance `server`.

```
asadmin> monitor --type jvm server
```

UpTime(ms)		Heap and NonHeap Memory(bytes)			
current	min	max	low	high	count
9437266	8585216	619642880	0	0	93093888
9467250	8585216	619642880	0	0	93093888

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help monitor` at the command line.

Common Monitoring Statistics

Common monitoring statistics are described in the following sections:

- [“HTTP Listener Common Statistics” on page 180](#)
- [“JVM Common Statistics” on page 180](#)
- [“Web Module Common Statistics” on page 180](#)

HTTP Listener Common Statistics

The statistics available for the `httpListener` type are shown in the following table.

TABLE 8-1 HTTP Listener Common Monitoring Statistics

Statistic	Description
ec	Error count. Cumulative value of the error count
mt	Maximum time. Longest response time for a request; not a cumulative value, but the largest response time from among the response times
pt	Processing time. Cumulative value of the times taken to process each request, with processing time being the average of request processing times over request
rc	Request count. Cumulative number of requests processed so far

JVM Common Statistics

The statistics available for the `jvm` type are shown in the following table.

TABLE 8-2 JVM Common Monitoring Statistics

Statistic	Description
count	Amount of memory (in bytes) that is guaranteed to be available for use by the JVM machine
high	Retained for compatibility with other releases
low	Retained for compatibility with other releases
max	The maximum amount of memory that can be used for memory management.
min	Initial amount of memory (in bytes) that the JVM machine requests from the operating system for memory management during startup
UpTime	Number of milliseconds that the JVM machine has been running since it was last started

Web Module Common Statistics

The statistics available for the `webmodule` type are shown in the following table.

TABLE 8-3 Web Module Common Monitoring Statistics

Statistic	Description
ajlc	Number of active JavaServer Pages (JSP) technology pages that are loaded
asc	Current active sessions
aslc	Number of active servlets that are loaded
ast	Total active sessions
mjlc	Maximum number of JSP pages that are loaded
mslc	Maximum number of servlets that are loaded
rst	Total rejected sessions
st	Total sessions
tjlc	Total number of JSP pages that are loaded
tslc	Total number of servlets that are loaded

Viewing Comprehensive Monitoring Data

By applying the `list` and `get` subcommands against the tree structure using dotted names, you can display more comprehensive monitoring data, such as a description of each of the statistics and its unit of measurement.

The following topics are addressed here:

- [“Guidelines for Using the `list` and `get` Subcommands for Monitoring” on page 181](#)
- [“To View Comprehensive Monitoring Data” on page 182](#)
- [“Comprehensive Monitoring Statistics” on page 184](#)

Guidelines for Using the `list` and `get` Subcommands for Monitoring

The underlying assumptions for using the `list` and `get` subcommands with dotted names are:

- A `list` subcommand that specifies a dotted name that is *not* followed by a wildcard (*) lists the current node’s immediate children. For example, the following subcommand lists all immediate children belonging to the server node:

```
list --monitor server
```

- A `list` subcommand that specifies a dotted name followed by a wildcard of the form `.*` lists a hierarchical tree of child nodes from the specified node. For example, the following subcommand lists all children of the `applications` node, their subsequent child nodes, and so on:

```
list --monitor server.applications.*
```
- A `list` subcommand that specifies a dotted name preceded or followed by a wildcard of the form `*dottedname` or `dotted *name` or `dottedname *` lists all nodes and their children that match the regular expression created by the specified matching pattern.
- A `get` subcommand followed by a `.*` or a `*` gets the set of attributes and their values that belong to the node specified.

For example, the following table explains the output of the `list` and `get` subcommands used with the dotted name for the `resources` node.

TABLE 8-4 Example Resources Level Dotted Names

Subcommand	Dotted Name	Output
<code>list --monitor</code>	<code>server.resources</code>	List of pool names.
<code>list --monitor</code>	<code>server.resources.connection-pool1</code>	No attributes, but a message saying “Use <code>get</code> subcommand with the <code>--monitor</code> option to view this node’s attributes and values.”
<code>get --monitor</code>	<code>server.resources.connection-pool1.*</code>	List of attributes and values corresponding to connection pool attributes.

For detailed information on dotted names, see the `dotted-names(5ASC)` help page.

▼ To View Comprehensive Monitoring Data

Although the `monitor` subcommand is useful in many situations, it does not offer the complete list of all monitorable objects. To work with comprehensive data for an object type, use the `list --monitor` and the `get --monitor` subcommands followed by the dotted name of a monitorable object.

Before You Begin A monitorable object must be configured for monitoring before you can display information about the object. See [“To Enable Monitoring” on page 176](#) if needed.

1 List the objects that are enabled for monitoring by using the `list(1)` subcommand.

For example, the following subcommand lists all components and services that have monitoring enabled for instance server.

```
asadmin> list --monitor "*"
server.web
server.connector-service
server.orb
server.jms-serviceserver.jvm
server.applications
server.http-service
server.thread-pools
```

2 Get data for a monitored component or service by using the `get(1)` subcommand.

Example 8–8 Viewing Attributes for a Specific Type

This example gets information about all the attributes for object type `jvm` on instance server.

```
asadmin> get --monitor server.jvm.*
server.jvm.class-loading-system.loadedclasscount = 3715
server.jvm.class-loading-system.totalloadedclasscount = 3731
server.jvm.class-loading-system.unloadedclasscount = 16
server.jvm.compilation-system.name-current = HotSpot Client Compiler
server.jvm.compilation-system.totalcompilationtime = 769
server.jvm.garbage-collectors.Copy.collectioncount = 285
server.jvm.garbage-collectors.Copy.collectiontime = 980
server.jvm.garbage-collectors.MarkSweepCompact.collectioncount = 2
server.jvm.garbage-collectors.MarkSweepCompact.collectiontime = 383
server.jvm.memory.committedheapsize = 23498752
server.jvm.memory.committednonheapsize = 13598720
server.jvm.memory.initheapsize = 0
server.jvm.memory.initnonheapsize = 8585216
server.jvm.memory.maxheapsize = 66650112
server.jvm.memory.maxnonheapsize = 100663296
server.jvm.memory.objectpendingfinalizationcount = 0
server.jvm.memory.usedheapsize = 19741184
server.jvm.memory.usednonheapsize = 13398352
server.jvm.operating-system.arch-current = x86
server.jvm.operating-system.availableprocessors = 2
server.jvm.operating-system.name-current = Windows XP
server.jvm.operating-system.version-current = 5.1
server.jvm.runtime.classpath-current = glassfish.jar
server.jvm.runtime.inputarguments-current = []
server.jvm.runtime.managementspecversion-current = 1.0
server.jvm.runtime.name-current = 4372@ABBAGANI_WORK
server.jvm.runtime.specname-current = Java Virtual Machine Specification
server.jvm.runtime.specvendor-current = Sun Microsystems Inc.
server.jvm.runtime.specversion-current = 1.0
server.jvm.runtime.uptime = 84813
server.jvm.runtime.vmmname-current = Java HotSpot(TM) Client VM
server.jvm.runtime.vmvendor-current = Sun Microsystems Inc.
server.jvm.runtime.vmvversion-current = 1.5.0_11-b03
```

Example 8–9 Viewing Monitorable Applications

This example lists all the monitorable applications for instance server.

```
asadmin> list --monitor server.applications.*
server.applications.app1
server.applications.app2
server.applications.app1.virtual-server1
server.applications.app2.virtual-server1
```

Example 8–10 Viewing Attributes for an Application

This example gets information about all the attributes for application hello.

```
asadmin> get --monitor server.applications.hello.*
server.applications.hello.server.activatedsessiontotal = 0
server.applications.hello.server.activejsploadedcount = 1
server.applications.hello.server.activeservletsloadedcount = 1
server.applications.hello.server.activesessionscurrent = 1
server.applications.hello.server.activesessionshigh = 1
server.applications.hello.server.errorcount = 0
server.applications.hello.server.expiredsessiontotal = 0
server.applications.hello.server.maxjsploadedcount = 1
server.applications.hello.server.maxservletsloadedcount = 0
server.applications.hello.server.maxtime = 0
server.applications.hello.server.passivatedsessiontotal = 0
server.applications.hello.server.persistedsessiontotal = 0
server.applications.hello.server.processingtime = 0.0
server.applications.hello.server.rejectedsessiontotal = 0
server.applications.hello.server.requestcount = 0
server.applications.hello.server.sessiontotal =
server.applications.hello.server.totaljsploadedcount = 0
server.applications.hello.server.totalservletsloadedcount = 0
```

Example 8–11 Viewing a Specific Attribute

This example gets information about the jvm attribute runtime.vmversion-current on instance server.

```
asadmin> get --monitor server.jvm.runtime.vmversion-current
server.jvm.runtime.vmversion-current = 10.0-b23
```

Comprehensive Monitoring Statistics

You can get comprehensive monitoring statistics by forming a dotted name that specifies the statistic you are looking for. For example, the following dotted name will display the cumulative number of requests for the HTTP service on virtual-server1:

```
server.http-service.virtual-server1.request.requestcount
```


The tables in the following sections list the statistics that are available for each monitorable object:

- “EJB Statistics” on page 185
- “HTTP Service Statistics” on page 188
- “Jersey Statistics” on page 190
- “JMS/Connector Service Statistics” on page 190
- “JVM Statistics” on page 192
- “Network Statistics” on page 196
- “ORB Statistics (Connection Manager)” on page 199
- “Resource Statistics (Connection Pool)” on page 200
- “Security Statistics” on page 202
- “Thread Pool Statistics” on page 203
- “Transaction Service Statistics” on page 205
- “Web Statistics” on page 205

EJB Statistics

EJBs fit into the tree of objects as shown in “Applications Tree Hierarchy” on page 171. Use the following dotted name pattern to get EJB statistics for an application:

```
server.applications.appname.ejbmodulename.ejbname.bean-cache.statistic
```

Note – EJB statistics for an application are available after the application is executed. If the application is deployed but has not yet been executed, all counts will show default values. When the application is undeployed, all its monitoring data is lost.

Statistics available for applications are shown in the following sections:

- “EJB Cache Statistics” on page 185
- “EJB Container Statistics” on page 186
- “EJB Method Statistics” on page 187
- “EJB Pool Statistics” on page 187
- “Timer Statistics” on page 188

EJB Cache Statistics

Use the following dotted name pattern for EJB cache statistics:

```
server.applications.appname.ejbmodulename.bean-cache.ejbname.statistic
```

The statistics available for EJB caches are listed in the following table.

TABLE 8-5 EJB Cache Monitoring Statistics

Statistic	Data Type	Description
cachemisses	RangeStatistic	The number of times a user request does not find a bean in the cache.
cachehits	RangeStatistic	The number of times a user request found an entry in the cache.
numbeansincache	RangeStatistic	The number of beans in the cache. This is the current size of the cache.
numpassivations	CountStatistic	Number of passivated beans. Applies only to stateful session beans.
numpassivationerrors	CountStatistic	Number of errors during passivation. Applies only to stateful session beans.
numexpiredsessionsremoved	CountStatistic	Number of expired sessions removed by the cleanup thread. Applies only to stateful session beans.
numpassivationsuccess	CountStatistic	Number of times passivation completed successfully. Applies only to stateful session beans.

EJB Container Statistics

Use the following dotted name pattern for EJB container statistics:

`server.applications.appname.ejbmodulename.container.ejbname`

The statistics available for EJB containers are listed in the following table.

TABLE 8-6 EJB Container Monitoring Statistics

Statistic	Data Type	Description
createcount	CountStatistic	Number of times an EJB's create method is called.
messagecount	CountStatistic	Number of messages received for a message-driven bean.
methodreadycount	RangeStatistic	Number of stateful or stateless session beans that are in the MethodReady state.
passivecount	RangeStatistic	Number of stateful session beans that are in Passive state.
pooledcount	RangeStatistic	Number of entity beans in pooled state.

TABLE 8-6 EJB Container Monitoring Statistics *(Continued)*

Statistic	Data Type	Description
readycount	RangeStatistic	Number of entity beans in ready state.
removecount	CountStatistic	Number of times an EJB's remove method is called.

EJB Method Statistics

Use the following dotted name pattern for EJB method statistics:

```
server.applications.appname.ejbmodulename.bean-methods.ejbname.statistic
```

The statistics available for EJB method invocations are listed in the following table.

TABLE 8-7 EJB Method Monitoring Statistics

Statistic	Data Type	Description
executiontime	CountStatistic	Time, in milliseconds, spent executing the method for the last successful/unsuccessful attempt to run the operation. This is collected for stateless and stateful session beans and entity beans if monitoring is enabled on the EJB container.
methodstatistic	TimeStatistic	Number of times an operation is called; the total time that is spent during the invocation, and so on.
totalnumerrors	CountStatistic	Number of times the method execution resulted in an exception. This is collected for stateless and stateful session beans and entity beans if monitoring is enabled for the EJB container.
totalnumsuccess	CountStatistic	Number of times the method successfully executed. This is collected for stateless and stateful session beans and entity beans if monitoring enabled is true for EJB container.

EJB Pool Statistics

Use the following dotted name pattern for EJB pool statistics:

```
server.applications.appname.ejbmodulename.bean-pool.ejbname.statistic
```

The statistics available for EJB pools are listed in the following table.

TABLE 8-8 EJB Pool Monitoring Statistics

Statistic	Data Type	Description
jmsmaxmessagesload	CountStatistic	The maximum number of messages to load into a JMS session at one time for a message-driven bean to serve. Default is 1. Applies only to pools for message driven beans.
numbeansinpool	RangeStatistic	Number of EJBs in the associated pool, providing information about how the pool is changing.
numthreadswaiting	RangeStatistic	Number of threads waiting for free beans, giving an indication of possible congestion of requests.
totalbeanscreated	CountStatistic	Number of beans created in associated pool since the gathering of data started.
totalbeansdestroyed	CountStatistic	Number of beans destroyed from associated pool since the gathering of data started.

Timer Statistics

Use the following dotted name pattern for timer statistics:

```
server.applications.appname.ejbmodulename.timers.ejbname.statistic
```

The statistics available for timers are listed in the following table.

TABLE 8-9 Timer Monitoring Statistics

Statistic	Data Type	Description
numtimerscreated	CountStatistic	Number of timers created in the system.
numtimersdelivered	CountStatistic	Number of timers delivered by the system.
numtimersremoved	CountStatistic	Number of timers removed from the system.

HTTP Service Statistics

The HTTP service fits into the tree of objects as shown in [“HTTP Service Tree Hierarchy” on page 172](#).

HTTP Service Virtual Server Statistics

Use the following dotted name pattern for HTTP service virtual server statistics:

```
server.http-service.virtual-server.request.statistic
```

The HTTP service statistics for virtual servers are shown in the following table.

TABLE 8-10 HTTP Service Virtual Server Monitoring Statistics

Statistic	Data Type	Description
count200	CountStatistic	Number of responses with a status code equal to 200
count2xx	CountStatistic	Number of responses with a status code in the 2xx range
count302	CountStatistic	Number of responses with a status code equal to 302
count304	CountStatistic	Number of responses with a status code equal to 304
count3xx	CountStatistic	Number of responses with a status code equal in the 3xx range
count400	CountStatistic	Number of responses with a status code equal to 400
count401	CountStatistic	Number of responses with a status code equal to 401
count403	CountStatistic	Number of responses with a status code equal to 403
count404	CountStatistic	Number of responses with a status code equal to 404
count4xx	CountStatistic	Number of responses with a status code equal in the 4xx range
count503	CountStatistic	Number of responses with a status code equal to 503
count5xx	CountStatistic	Number of responses with a status code equal in the 5xx range
countother	CountStatistic	Number of responses with a status code outside the 2xx, 3xx, 4xx, and 5xx range
errorcount	CountStatistic	Cumulative value of the error count, with error count representing the number of cases where the response code was greater than or equal to 400
hosts	StringStatistic	The host (alias) names of the virtual server
maxtime	CountStatistic	Longest response time for a request; not a cumulative value, but the largest response time from among the response times

TABLE 8-10 HTTP Service Virtual Server Monitoring Statistics (Continued)

Statistic	Data Type	Description
processingtime	CountStatistic	Cumulative value of the times taken to process each request, with processing time being the average of request processing times over the request count
requestcount	CountStatistic	Cumulative number of requests processed so far
state	StringStatistic	The state of the virtual server

Jersey Statistics

Jersey fits into the tree of objects as shown in “[Applications Tree Hierarchy](#)” on page 171.

Use the following dotted name pattern for Jersey statistics:

`server.applications.jersey-application.jersey.resources.resource-0.hitcount.statistic`

The statistics available for Jersey are shown in the following table.

TABLE 8-11 Jersey Statistics

Statistic	Data Type	Description
resourcehitcount	CountStatistic	Number of hits on this resource class
rootresourcehitcount	CountStatistic	Number of hits on this root resource class

JMS/Connector Service Statistics

The JMS/Connector Service fits into the tree of objects as shown in “[JMS/Container Service Tree Hierarchy](#)” on page 173.

JMS/Connector Service statistics are shown in the following sections:

- “[Connector Connection Pool Statistics \(JMS\)](#)” on page 190
- “[Connector Work Management Statistics \(JMS\)](#)” on page 192

Connector Connection Pool Statistics (JMS)

Use the following dotted name pattern for JMS/Connector Service connection pool statistics:

`server.connector-service.resource-adapter-1.connection-pool.statistic`

JMS/Connector Service statistics available for the connector connection pools are shown in the following table.

Note – In order to improve system performance, connection pools are initialized lazily; that is, a pool is not initialized until an application first uses the pool or the pool is explicitly pinged. Monitoring statistics for a connection pool are not available until the pool is initialized.

TABLE 8-12 Connector Connection Pool Monitoring Statistics (JMS)

Statistic	Data Type	Description
averageconnwaittime	CountStatistic	Average wait time of connections before they are serviced by the connection pool.
connectionrequestwaittime	RangeStatistic	The longest and shortest wait times of connection requests. The current value indicates the wait time of the last request that was serviced by the pool.
numconnfailedvalidation	CountStatistic	Total number of connections in the connection pool that failed validation from the start time until the last sample time.
numconnused	RangeStatistic	Total number of connections that are currently being used, as well as information about the maximum number of connections that were used (the high water mark).
numconnfree	RangeStatistic	Total number of free connections in the pool as of the last sampling.
numconn timedout	CountStatistic	Total number of connections in the pool that timed out between the start time and the last sample time.
numconncreated	CountStatistic	Number of physical connections, in milliseconds, that were created since the last reset.
numconndestroyed	CountStatistic	Number of physical connections that were destroyed since the last reset.
numconnacquired	CountStatistic	Number of logical connections acquired from the pool.
numconnreleased	CountStatistic	Number of logical connections released to the pool.
waitqueuelength	CountStatistic	Number of connection requests in the queue waiting to be serviced.

Connector Work Management Statistics (JMS)

Use the following dotted name pattern for JMS/Connector Service work management statistics:

`server.connector-service.resource-adapter-1.work-management.statistic`

JMS/Connector Service statistics available for connector work management are listed in the following table.

TABLE 8-13 Connector Work Management Monitoring Statistics (JMS)

Statistic	Data Type	Description
activeworkcount	RangeStatistic	Number of work objects executed by the connector.
completedworkcount	CountStatistic	Number of work objects that were completed.
rejectedworkcount	CountStatistic	Number of work objects rejected by the GlassFish Server.
submittedworkcount	CountStatistic	Number of work objects submitted by a connector module.
waitqueuelength	RangeStatistic	Number of work objects waiting in the queue before executing.
workrequestwaittime	RangeStatistic	Longest and shortest wait of a work object before it gets executed.

JVM Statistics

The JVM fits into the tree of objects as show in [“JVM Tree Hierarchy” on page 173](#).

The statistics that are available for the Virtual Machine for Java platform (Java Virtual Machine) or JVM machine are shown in the following sections:

- [“JVM Class Loading System Statistics” on page 192](#)
- [“JVM Compilation System Statistics” on page 194](#)
- [“JVM Garbage Collectors Statistics” on page 194](#)
- [“JVM Memory Statistics” on page 194](#)
- [“JVM Operating System Statistics” on page 195](#)
- [“JVM Runtime Statistics” on page 196](#)

JVM Class Loading System Statistics

Use the following dotted name pattern for JVM class loading system statistics:

`server.jvm.class-loading-system.statistic`

With Java SE, additional monitoring information can be obtained from the JVM. Set the monitoring level to LOW to enable the display of this additional information. Set the monitoring level to HIGH to also view information pertaining to each live thread in the system. More information about the additional monitoring features for Java SE is available in *Monitoring and Management for the Java Platform* (http://download.oracle.com/docs/cd/E17409_01/javase/6/docs/technotes/guides/management/).

The Java SE monitoring tools are discussed at http://download.oracle.com/docs/cd/E17409_01/javase/6/docs/technotes/tools/.

The statistics that are available for class loading in the JVM for Java SE are shown in the following table.

TABLE 8-14 JVM Monitoring Statistics for Java SE Class Loading

Statistic	Data Type	Description
loadedclasscount	CountStatistic	Number of classes that are currently loaded in the JVM
totalloadedclasscount	CountStatistic	Total number of classes that have been loaded since the JVM began execution
unloadedclasscount	CountStatistic	Number of classes that have been unloaded from the JVM since the JVM began execution

The statistics available for threads in the JVM in Java SE are shown in the following table.

TABLE 8-15 JVM Monitoring Statistics for Java SE - Threads

Statistic	Data Type	Description
allthreadids	StringStatistic	List of all live thread ids.
currentthreadcputime	CountStatistic	CPU time for the current thread (in nanoseconds) if CPU time measurement is enabled. If CPU time measurement is disabled, returns -1.
daemonthreadcount	CountStatistic	Current number of live daemon threads.
monitordeadlockedthreads	StringStatistic	List of thread ids that are monitor deadlocked.
peakthreadcount	CountStatistic	Peak live thread count since the JVM started or the peak was reset.
threadcount	CountStatistic	Current number of live daemon and non-daemon threads.
totalstartedthreadcount	CountStatistic	Total number of threads created and/or started since the JVM started.

JVM Compilation System Statistics

Use the following dotted name pattern for JVM compilation system statistics:

```
server.jvm.compilation-system.statistic
```

The statistics that are available for compilation in the JVM for Java SE are shown in the following table.

TABLE 8-16 JVM Monitoring Statistics for Java SE Compilation

Statistic	Data Type	Description
name-current	StringStatistic	Name of the current compiler
totalcompilationtime	CountStatistic	Accumulated time (in milliseconds) spent in compilation

JVM Garbage Collectors Statistics

Use the following dotted name pattern for JVM garbage collectors statistics:

```
server.jvm.garbage-collectors.statistic
```

The statistics that are available for garbage collection in the JVM for Java SE are shown in the following table.

TABLE 8-17 JVM Monitoring Statistics for Java SE Garbage Collectors

Statistic	Data Type	Description
collectioncount	CountStatistic	Total number of collections that have occurred
collectiontime	CountStatistic	Accumulated time (in milliseconds) spent in collection

JVM Memory Statistics

Use the following dotted name pattern for JVM memory statistics:

```
server.jvm.memory.statistic
```

The statistics that are available for memory in the JVM for Java SE are shown in the following table.

TABLE 8-18 JVM Monitoring Statistics for Java SE Memory

Statistic	Data Type	Description
committedheapsize	CountStatistic	Amount of heap memory (in bytes) that is committed for the JVM to use
committednonheapsize	CountStatistic	Amount of non-heap memory (in bytes) that is committed for the JVM to use
initheapsize	CountStatistic	Size of the heap initially requested by the JVM
initnonheapsize	CountStatistic	Size of the non-heap area initially requested by the JVM
maxheapsize	CountStatistic	Maximum amount of heap memory (in bytes) that can be used for memory management
maxnonheapsize	CountStatistic	Maximum amount of non-heap memory (in bytes) that can be used for memory management
objectpendingfinalizationcount	CountStatistic	Approximate number of objects that are pending finalization
usedheapsize	CountStatistic	Size of the heap currently in use
usednonheapsize	CountStatistic	Size of the non-heap area currently in use

JVM Operating System Statistics

Use the following dotted name pattern for JVM operating system statistics:

```
server.jvm.operating-system.statistic
```

The statistics that are available for the operating system for the JVM machine in Java SE are shown in the following table.

TABLE 8-19 JVM Statistics for the Java SE Operating System

Statistic	Data Type	Description
arch-current	StringStatistic	Operating system architecture
availableprocessors	CountStatistic	Number of processors available to the JVM
name-current	StringStatistic	Operating system name
version-current	StringStatistic	Operating system version

JVM Runtime Statistics

Use the following dotted name pattern for JVM runtime statistics:

```
server.jvm.runtime.statistic
```

The statistics that are available for the runtime in the JVM runtime for Java SE are shown in the following table.

TABLE 8–20 JVM Monitoring Statistics for Java SE Runtime

Statistic	Data Type	Description
classpath-current	StringStatistic	Classpath that is used by the system class loader to search for class files
inputarguments-current	StringStatistic	Input arguments passed to the JVM; not including arguments to the main method
managementspecversion-current	StringStatistic	Management specification version implemented by the JVM
name-current	StringStatistic	Name representing the running JVM
specname-current	StringStatistic	JVM specification name
specvendor-current	StringStatistic	JVM specification vendor
specversion-current	StringStatistic	JVM specification version
uptime	CountStatistic	Uptime of the JVM (in milliseconds)
vmname-current	StringStatistic	JVM implementation name
vmvendor-current	StringStatistic	JVM implementation vendor
vmversion-current	StringStatistic	JVM implementation version

Network Statistics

Network fits into the tree of objects as shown in [“Network Tree Hierarchy” on page 173](#).

Network statistics are described in the following sections:

- [“Network Keep Alive Statistics” on page 197](#)
- [“Network Connection Queue Statistics” on page 197](#)
- [“Network File Cache Statistics” on page 198](#)
- [“Network Thread Pool Statistics” on page 199](#)

Network Keep Alive Statistics

Use the following dotted name pattern for network keep alive statistics:

`server.network.type-of-listener.keep-alive.statistic`

Statistics available for network keep alive are shown in the following table.

TABLE 8–21 Network Keep Alive Statistics

Statistic	Data Type	Description
countconnections	CountStatistic	Number of connections in keep-alive mode.
counttimeouts	CountStatistic	Number of keep-alive connections that timed out.
secondstimeouts	CountStatistic	Keep-alive timeout value in seconds.
maxrequests	CountStatistic	Maximum number of requests allowed on a single keep-alive connection.
countflushes	CountStatistic	Number of keep-alive connections that were closed.
counthits	CountStatistic	Number of requests received by connections in keep-alive mode.
countrefusals	CountStatistic	Number of keep-alive connections that were rejected.

Network Connection Queue Statistics

Use the following dotted name pattern for network connection queue statistics:

`server.network.type-of-listener.connection-queue.statistic`

Statistics available for network connection queue are shown in the following table.

TABLE 8–22 Network Connection Queue Statistics

Statistic	Data Type	Description
countopenconnections	CountStatistic	The number of open/active connections
countoverflows	CountStatistic	Number of times the queue has been too full to accommodate a connection
countqueued	CountStatistic	Number of connections currently in the queue
countqueued15minutesaverage	CountStatistic	Average number of connections queued in the last 15 minutes

TABLE 8–22 Network Connection Queue Statistics *(Continued)*

Statistic	Data Type	Description
countqueued1minuteaverage	CountStatistic	Average number of connections queued in the last 1 minute
countqueued5minutesaverage	CountStatistic	Average number of connections queued in the last 5 minutes
counttotalconnections	CountStatistic	Total number of connections that have been accepted
counttotalqueued	CountStatistic	Total number of connections that have been queued
maxqueued	CountStatistic	Maximum size of the connection queue
peakqueued	CountStatistic	Largest number of connections that were in the queue simultaneously
ticktotalqueued	CountStatistic	(Unsupported) Total number of ticks that connections have spent in the queue

Network File Cache Statistics

Use the following dotted name pattern for network file cache statistics:

`server.network.type-of-listener.file-cache.statistic`

Statistics available for network file cache are shown in the following table.

TABLE 8–23 Network File Cache Statistics

Statistic	Data Type	Description
contenthits	CountStatistic	Number of hits on cached file content
contentmisses	CountStatistic	Number of misses on cached file content
heapsize	CountStatistic	Current cache size in bytes
hits	CountStatistic	Number of cache lookup hits
infohits	CountStatistic	Number of hits on cached file info
infomisses	CountStatistic	Number of misses on cached file info
mappedmemorysize	CountStatistic	Size of mapped memory used for caching in bytes
maxheapsize	CountStatistic	Maximum heap space used for cache in bytes
maxmappedmemorysize	CountStatistic	Maximum memory map size used for caching in bytes

TABLE 8–23 Network File Cache Statistics (Continued)

Statistic	Data Type	Description
misses	CountStatistic	Number of cache lookup misses data type
opencacheentries	CountStatistic	Number of current open cache entries

Network Thread Pool Statistics

Use the following dotted name pattern for network thread pool statistics:

`server.network.type-of-listener.thread-pool.statistic`

Statistics available for network thread pool are shown in the following table.

TABLE 8–24 Network Thread Pool Statistics

Statistic	Data Type	Description
corethreads	CountStatistic	Core number of threads in the thread pool
currentthreadcount	CountStatistic	Provides the number of request processing threads currently in the listener thread pool
currentthreadsbusy	CountStatistic	Provides the number of request processing threads currently in use in the listener thread pool serving requests
maxthreads	CountStatistic	Maximum number of threads allowed in the thread pool
totalexecutedtasks	CountStatistic	Provides the total number of tasks, which were executed by the thread pool

ORB Statistics (Connection Manager)

The ORB fits into the tree of objects as shown in [“ORB Tree Hierarchy” on page 174](#).

Use the following dotted name patterns for ORB statistics:

`server.orb.transport.connectioncache.inbound.statistic`
`server.orb.transport.connectioncache.outbound.statistic`

The statistics available for the connection manager in an ORB are listed in the following table.

TABLE 8–25 ORB Monitoring Statistics (Connection Manager)

Statistic	Data Type	Description
connectionsidle	CountStatistic	Total number of connections that are idle to the ORB

TABLE 8–25 ORB Monitoring Statistics (Connection Manager) *(Continued)*

Statistic	Data Type	Description
connectionsinuse	CountStatistic	Total number of connections in use to the ORB
totalconnections	BoundedRangeStatistic	Total number of connections to the ORB

Resource Statistics (Connection Pool)

By monitoring connection pool resources you can measure performance and capture resource usage at runtime. Connections are expensive and frequently cause performance bottlenecks in applications. It is important to monitor how a connection pool is releasing and creating new connections and how many threads are waiting to retrieve a connection from a particular pool.

The connection pool resources fit into the tree of objects as shown in [“Resources Tree Hierarchy” on page 174](#).

Use the following dotted name pattern for general connection pool statistics:

```
server.resources.pool-name.statistic
```

Use the following dotted name pattern for application-scoped connection pool statistics:

```
server.applications.application-name.resources.pool-name.statistic
```

Use the following dotted name pattern for module-scoped connection pool statistics:

```
server.applications.application-name.module-name.resources.pool-name.statistic
```

The connection pool statistics are shown in the following tables.

Note – In order to improve system performance, connection pools are initialized lazily; that is, a pool is not initialized until an application first uses the pool or the pool is explicitly pinged. Monitoring statistics for a connection pool are not available until the pool is initialized.

TABLE 8–26 General Resource Monitoring Statistics (Connection Pool)

Statistic	Data Type	Description
averageconnwaittime	CountStatistic	Average wait-time-duration per successful connection request
connrequestwaittime	RangeStatistic	Longest and shortest wait times, in milliseconds, of connection requests since the last sampling. current value indicates the wait time of the last request that was serviced by the pool

TABLE 8–26 General Resource Monitoring Statistics (Connection Pool) *(Continued)*

Statistic	Data Type	Description
numconnacquired	CountStatistic	Number of logical connections acquired from the pool since the last sampling
numconncreated	CountStatistic	Number of physical connections that were created by the pool since the last reset
numconndestroyed	CountStatistic	Number of physical connections that were destroyed since the last reset
numconnfailedvalidation	CountStatistic	Number of connections in the connection pool that failed validation from the start time until the last sampling time
numconnfree	RangeStatistic	Number of free connections in the pool as of the last sampling
numconnnotsuccessfullymatched	CountStatistic	Number of connections rejected during matching
numconnreleased	CountStatistic	Number of connections released back to the pool since the last sampling
numconnsuccessfullymatched	CountStatistic	Number of connections successfully matched
numconntimedout	CountStatistic	Number of connections in the pool that timed out between the start time and the last sampling time
numconnused	RangeStatistic	Number of connections that are currently being used, as well as information about the maximum number of connections that were used (high water mark)
frequedsqlqueries	StringStatistic	List of the most frequently used SQL queries (Available only when SQL Tracing is enabled)
numpotentialconnleak	CountStatistic	Number of potential connection leaks
numpotentialstatementleak	CountStatistic	Number of potential statement leaks (Available only when Statement Leak Detection is enabled)
numstatementcachehit	CountStatistic	Number of statements that were found in the statement cache (Available only when the Statement Cache is enabled)
numstatementcachemiss	CountStatistic	Number of statements that were not found in the statement cache (Available only when the Statement Cache is enabled)

TABLE 8–26 General Resource Monitoring Statistics (Connection Pool) *(Continued)*

Statistic	Data Type	Description
waitqueuelength	CountStatistic	Number of connection requests in the queue waiting to be serviced

TABLE 8–27 Application Specific Resource Monitoring Statistics (Connection Pool)

Statistic	Data Type	Description
numconnacquired	CountStatistic	Number of logical connections acquired from the pool since the last sampling
numconnreleased	CountStatistic	Number of connections released back to the pool since the last sampling
numconnused	RangeStatistic	Number of connections that are currently being used, as well as information about the maximum number of connections that were used (high water mark)

Security Statistics

Security fits into the tree of objects as shown in [“Security Tree Hierarchy” on page 174](#).

Statistics available for security are shown in the following sections:

- [“EJB Security Statistics” on page 202](#)
- [“Web Security Statistics” on page 203](#)
- [“Realm Security Statistics” on page 203](#)

EJB Security Statistics

Use the following dotted name pattern for EJB security statistics:

```
server.security.ejb.statistic
```

The statistics available for EJB security are listed in the following table.

TABLE 8–28 EJB Security Monitoring Statistics

Statistic	Data Type	Description
policyconfigurationcount	CountStatistic	Number of policy configuration
securitymanagercount	CountStatistic	Number of EJB security managers

Web Security Statistics

Use the following dotted name pattern for web security statistics:

`server.security.web.statistic`

The statistics available for web security are listed in the following table.

TABLE 8–29 Web Security Monitoring Statistics

Statistic	Data Type	Description
websecuritymanagercount	CountStatistic	Number of security managers
webpolicyconfigurationcount	CountStatistic	Number of policy configuration objects

Realm Security Statistics

Use the following dotted name pattern for realm security statistics:

`server.security.realm.statistic`

The statistics available for realm security are listed in the following table.

TABLE 8–30 Realm Security Monitoring Statistics

Statistic	Data Type	Description
realmcount	CountStatistic	Number of realms

Thread Pool Statistics

The thread pool fits into the tree of objects as shown in [“Thread Pool Tree Hierarchy” on page 174](#).

The statistics available for thread pools are shown in the following sections:

- [“Thread Pool Monitoring Statistics” on page 203](#)
- [“JVM Statistics for Java SE-Thread Information” on page 204](#)

Thread Pool Monitoring Statistics

Use the following dotted name pattern for thread pool statistics:

`server.thread-pool.thread-pool.statistic`

The statistics available for the thread pool are shown in the following table.

TABLE 8-31 Thread Pool Monitoring Statistics

Statistic	Data Type	Description
averagetimeinqueue	BoundedRangeStatistic	Average amount of time (in milliseconds) a request waited in the queue before being processed
averageworkcompletiontime	BoundedRangeStatistic	Average amount of time (in milliseconds) taken to complete an assignment
currentbusythreads	CountStatistic	Number of busy threads
currentnumberofthreads	BoundedRangeStatistic	Current number of request processing threads
numberofavailablethreads	CountStatistic	Number of available threads
numberofworkitemsinqueue	BoundedRangeStatistic	Current number of work items waiting in queue
totalworkitemsadded	CountStatistic	Total number of work items added to the work queue as of last sampling

JVM Statistics for Java SE-Thread Information

The statistics available for ThreadInfo in the JVM in Java SE are shown in the following table.

TABLE 8-32 JVM Monitoring Statistics for Java SE - Thread Info

Statistic	Data Type	Description
blockedcount	CountStatistic	Total number of times that the thread entered the BLOCKED state.
blockedtime	CountStatistic	Time elapsed (in milliseconds) since the thread entered the BLOCKED state. Returns -1 if thread contention monitoring is disabled.
lockname	StringStatistic	String representation of the monitor lock that the thread is blocked to enter or waiting to be notified through the Object.wait method.
lockownerid	CountStatistic	ID of the thread that holds the monitor lock of an object on which this thread is blocking.
lockownername	StringStatistic	Name of the thread that holds the monitor lock of the object this thread is blocking on.
stacktrace	StringStatistic	Stack trace associated with this thread.
threadid	CountStatistic	ID of the thread.
threadname	StringStatistic	Name of the thread.

TABLE 8–32 JVM Monitoring Statistics for Java SE - Thread Info (Continued)

Statistic	Data Type	Description
threadstate	StringStatistic	State of the thread.
waitedtime	CountStatistic	Elapsed time (in milliseconds) that the thread has been in a WAITING state. Returns -1 if thread contention monitoring is disabled.
waitedcount	CountStatistic	Total number of times the thread was in WAITING or TIMED_WAITING states.

Transaction Service Statistics

The transaction service allows the client to freeze the transaction subsystem in order to roll back transactions and determine which transactions are in process at the time of the freeze. The transaction service fits into the tree of objects as shown in [“Transactions Service Tree Hierarchy” on page 175](#).

Use the following dotted name pattern for transaction service statistics:

```
server.transaction-service.statistic
```

The statistics available for the transaction service are shown in the following table.

TABLE 8–33 Transaction Service Monitoring Statistics

Statistic	Data Type	Description
activecount	CountStatistic	Number of transactions currently active.
activeids	StringStatistic	The ID's of the transactions that are currently active. Every such transaction can be rolled back after freezing the transaction service.
committedcount	CountStatistic	Number of transactions that have been committed.
rolledbackcount	CountStatistic	Number of transactions that have been rolled back.
state	StringStatistic	Indicates whether or not the transaction has been frozen.

Web Statistics

The web module fits into the tree of objects as shown in [“Web Tree Hierarchy” on page 175](#).

The available web statistics shown in the following sections:

- [“Web Module Servlet Statistics” on page 206](#)
- [“Web JSP Statistics” on page 206](#)

- “Web Request Statistics” on page 207
- “Web Servlet Statistics” on page 207
- “Web Session Statistics” on page 208

Web Module Servlet Statistics

Use the following dotted name pattern for web module servlet statistics:

```
server.applications.web-module.virtual-server.servlet.statistic
server.applications.application.web-module.virtual-server.servlet.statistic
```

The available web module servlet statistics are shown in the following table.

TABLE 8-34 Web Module Servlet Statistics

Statistic	Data Type	Description
errorcount	CountStatistic	Cumulative number of cases where the response code is greater than or equal to 400.
maxtime	CountStatistic	Maximum amount of time the web container waits for requests.
processingtime	CountStatistic	Cumulative value of the amount of time required to process each request. The processing time is the average of request processing times divided by the request count.
requestcount	CountStatistic	The total number of requests processed so far.
servicetime	CountStatistic	Aggregate response time in milliseconds.

Web JSP Statistics

Use the following dotted name pattern for web JSP statistics:

```
server.applications.web-module.virtual-server.statistic
server.applications.application.web-module.virtual-server.statistic
```

The available web JSP statistics are shown in the following table.

TABLE 8-35 Web JSP Monitoring Statistics

Statistic	Data Type	Description
jspcount-current	RangeStatistic	Number of active JSP pages
jsperrorcount	CountStatistic	Total number of errors triggered by JSP page invocations
jspreloadedcount	CountStatistic	Total number of JSP pages that were reloaded

TABLE 8–35 Web JSP Monitoring Statistics (Continued)

Statistic	Data Type	Description
totaljspcount	CountStatistic	Total number of JSP pages ever loaded

Web Request Statistics

Use the following dotted name pattern for web request statistics:

```
server.applications.web-module.virtual-server.statistic
server.applications.application.web-module.virtual-server.statistic
```

The available web request statistics are shown in the following table.

TABLE 8–36 Web Request Monitoring Statistics

Statistic	Data Type	Description
errorcount	CountStatistic	Cumulative value of the error count, with error count representing the number of cases where the response code was greater than or equal to 400
maxtime	CountStatistic	Longest response time for a request; not a cumulative value, but the largest response time from among the response times
processingtime	CountStatistic	Average request processing time, in milliseconds
requestcount	CountStatistic	Cumulative number of the requests processed so far

Web Servlet Statistics

Use the following dotted name pattern for web servlet statistics:

```
server.applications.web-module.virtual-server.statistic
server.applications.application.web-module.virtual-server.statistic
```

The available web servlet statistics are shown in the following table.

TABLE 8–37 Web Servlet Monitoring Statistics

Statistic	Data Type	Description
activeservletsloadedcount	RangeStatistic	Number of currently loaded servlets
servletprocessingtimes	CountStatistic	Cumulative servlet processing times, in milliseconds
totalservletsloadedcount	CountStatistic	Cumulative number of servlets that have been loaded into the web module

Web Session Statistics

Use the following dotted name pattern for web session statistics:

```
server.applications.web-module.virtual-server.statistic
server.applications.application.web-module.virtual-server.statistic
```

The available web session statistics are shown in the following table.

TABLE 8–38 Web Session Monitoring Statistics

Statistic	Data Type	Description
activatedsessiontotal	CountStatistic	Total number of activated sessions
activesessionscurrent	RangeStatistic	Number of currently active sessions
activesessionshigh	CountStatistic	Maximum number of concurrently active sessions
expiredsessiontotal	CountStatistic	Total number of expired sessions
passivatedsessiontotal	CountStatistic	Total number of passivated sessions
persistedsessiontotal	CountStatistic	Total number of persisted sessions
rejectedsessiontotal	CountStatistic	Total number of rejected sessions
sessiontotal	CountStatistic	Total number of sessions created

Configuring JConsole to View GlassFish Server Monitoring Data

Java SE provides tools to connect to an MBean Server and view the MBeans registered with the server. JConsole is one such popular JMX Connector Client and is available as part of the standard Java SE distribution. When you configure JConsole for use with GlassFish Server, GlassFish Server becomes the JMX Connector's server end and JConsole becomes the JMX connector's client end.

▼ To Connect JConsole to GlassFish Server

Java SE 6 enhances management and monitoring of the virtual machine by including a Platform MBean Server and by including managed beans (MBeans) to configure the virtual machine.

To view all MBeans, GlassFish Server provides a configuration of the standard JMX connector server called System JMX Connector Server. As part of GlassFish Server startup, an instance of this JMX Connector Server is started. Any compliant JMX connector client can connect to the server using the JMX Connector Server.

By default, GlassFish Server is configured with a non-secure System JMX Connector Server. If this is an issue, the JMX connector can be removed. However, access can be restricted to a specific IP address (for example, the loopback address) by setting address to localhost.

- 1 Start the domain.**

For instructions, see [“To Start a Domain” on page 115](#).

- 2 Start JConsole using this format: `JDK_HOME/bin/jconsole`**

For example:

```
/usr/java/bin/jconsole
```

The JConsole Connect to Agent window is displayed.

- 3 Click the Remote tab and type the host name and port.**

Always connect remotely with JConsole, otherwise MBeans will not load automatically.

- 4 Click Connect.**

- 5 In the Remote Process text box, specify the JMX Service URL.**

For example:

```
service:jmx:rmi:///jndi/rmi://localhost:8686/jmxrmi
```

The JMX Service URL is emitted by the server at startup, looking something like this:

```
[#|2009-12-03T10:25:17.737-0800|INFO|glassfishv3.0|
x..system.tools.admin.org.glassfish.server|_ThreadID=20;
_ThreadName=Thread-26;|JMXStartupService: Started JMXConnector, JMXService
URL = service:jmx:rmi://localhost:8686/jndi/rmi://localhost:8686/jmxrmi|#]
```

However, in most cases, simply entering host:port is fine, such as 192.168.1.150:8686. The long Service URL is not needed.

Note – Another host name can be substituted for localhost. The default port number (8686) could change if the jmx-connector configuration has been modified.

- 6 Click Connect.**

In the JConsole window you will see all your MBeans, JVM information, and so on, in various tabs. Most of the useful MBeans are to be found in the `amx` and `java.lang` domains.

See Also For more information about JConsole, see http://download.oracle.com/docs/cd/E17409_01/javase/6/docs/technotes/guides/management/jconsole.html.

Administering Life Cycle Modules

This chapter provides procedures for administering life cycle modules in the GlassFish Server Open Source Edition 3.1 environment.

The following topics are addressed here:

- [“About Life Cycle Modules” on page 211](#)
- [“Configuring Life Cycle Modules” on page 212](#)

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

About Life Cycle Modules

Life cycle modules, also known as initialization services, provide a means of running short or long duration Java-based tasks within the GlassFish Server environment. These modules are automatically initiated at server startup and are notified at various phases of the server life cycle. Configured properties for a life cycle module are passed as properties during server initialization.

All life cycle module classes and interfaces are in the `as-install/glassfish/modules/glassfish-api.jar` file.

A life cycle module listens for and performs its tasks in response to the following GlassFish Server sequence of events:

1. **Initialization.** The server reads the configuration, initializes built-in subsystems (such as security and logging services), and creates the containers.
2. **Startup.** The server loads and initializes deployed applications.
3. **Ready.** The server begins servicing requests.
4. **Shutdown.** The server shuts down the applications and stops.

5. **Termination.** The server closes the containers, the built-in subsystems, and the server runtime environment.

These events are defined in the `LifecycleEvent` class. For information on creating life cycle modules, see Chapter 12, “Developing Lifecycle Listeners,” in *GlassFish Server Open Source Edition 3.1 Application Development Guide*.

Note – If the `is-failure-fatal` setting is set to true (the default is false), life cycle module failure prevents server initialization or startup, but not shutdown or termination.

Configuring Life Cycle Modules

The following topics are addressed here:

- “To Create a Life Cycle Module” on page 212
- “To List Life Cycle Modules” on page 213
- “To Update a Life Cycle Module” on page 213
- “To Delete a Life Cycle Module” on page 214

▼ To Create a Life Cycle Module

Use the `create-lifecycle-module` subcommand in remote mode to create a life cycle module.

- 1 **Ensure that the server is running.**

Remote subcommands require a running server.

- 2 **Create a new life cycle modules by using the `create-lifecycle-module(1)` subcommand.**

Information about options and properties for the subcommand are included in this help page.

- 3 **Restart the server for your changes to take effect.**

See “To Restart a Domain” on page 116.

Example 9–1 Creating a Life Cycle Module

This example creates the `customSetup` life cycle module :

```
asadmin> create-lifecycle-module --classname "com.acme.CustomSetup"
--classpath "/export/customSetup" --loadorder 1 --failurefatal=true
--description "this is a sample customSetup"
--property rmi="Server\=acme1\7070":timeout=30 customSetup
Command create-lifecycle-module executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-lifecycle-module` at the command line.

▼ To List Life Cycle Modules

Use the `list-lifecycle-modules` subcommand in remote mode to list the existing life cycle modules.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List life cycle modules by using the `list-lifecycle-modules(1)` subcommand.**

Example 9–2 Listing Life Cycle Modules

This example lists the existing life cycle modules.

```
asadmin> list-lifecycle-modules
WSTCPConnectorLCModule
Command list-lifecycle-modules executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-lifecycle-modules` at the command line.

▼ To Update a Life Cycle Module

Use the `set` subcommand to update an existing life cycle module.

- 1 **List the properties that can be updated for a life cycle module by using the `get(1)` subcommand.**

For example (single mode):

```
asadmin get "*" | grep sampleLCM
applications.application.sampleLCModule.availability-enabled=false
applications.application.sampleLCModule.directory-deployed=false
applications.application.sampleLCModule.enabled=true
applications.application.sampleLCModule.name=sampleLCModule
applications.application.sampleLCModule.object-type=user
applications.application.sampleLCModule.property.class-name=example.lc.SampleModule
applications.application.sampleLCModule.property.classpath=/build/lcm.jar
applications.application.sampleLCModule.property.is-failure-fatal=false
applications.application.sampleLCModule.property.isLifecycle=true
```

- 2 **Update a life cycle module by using the `set(1)` subcommand.**
- 3 **Restart the server for your changes to take effect.**

See [“To Restart a Domain” on page 116](#).

Example 9–3 Updating a Life Cycle Module

This example updates the classpath property.

```
sadmin> set applications.application.sampleLCModule.  
property.classpath=/build/lcm_new.jarapplications.application.  
sampleLCModule.property.classpath=/build/lcm_new.jar  
Command set executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help set` at the command line.

▼ To Delete a Life Cycle Module

Use the `delete-lifecycle-module` subcommand in remote mode to delete a life cycle module.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the current life cycle modules by using the `list-lifecycle-modules(1)` subcommand.**
- 3 **Delete a life cycle module by using the `delete-lifecycle-module(1)` subcommand.**

Example 9–4 Deleting a Life Cycle Module

This example deletes the `customSetup` life cycle module.

```
asadmin> delete-lifecycle-module customSetup  
Command delete-lifecycle-module executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-lifecycle-module` at the command line.

Extending and Updating GlassFish Server

This chapter explains how to extend and update a deployed GlassFish Server Open Source Edition 3.1 installation.

The following topics are addressed here:

- “About Add-On Components” on page 215
- “Preconfigured Repositories for GlassFish Server” on page 216
- “Tools for Extending and Updating GlassFish Server” on page 219
- “Adding Components” on page 221
- “Updating Installed Components” on page 224
- “Removing Installed Components” on page 227
- “Upgrading to Oracle GlassFish Server From GlassFish Server Open Source Edition” on page 230
- “Extending and Updating GlassFish Server Inside a Closed Network” on page 234

About Add-On Components

GlassFish Server is designed to provide its functionality in a modular form so that you can choose to include the functionality that you need and leave out the functionality that is not needed. *OSGi modules*, also called bundles, provide add-on functionality for your deployed GlassFish Server. As new add-on components are developed and existing components are modified, you can extend and update GlassFish Server by installing these components. You can add components during runtime, without stopping the server. But you must stop the server before updating or removing an installed component.

Preconfigured Repositories for GlassFish Server

Image Packaging System (IPS) tools for updating GlassFish Server software obtain updates from repositories that contain the OSGi modules and other content for GlassFish Server.

Oracle GlassFish Server and GlassFish Server Open Source Edition each have their own set of repositories, as explained in the following sections:

- “Oracle GlassFish Server Repositories” on page 216
- “GlassFish Server Open Source Edition Repositories” on page 219

Oracle GlassFish Server Repositories

Table 10–1 lists the preconfigured repositories for Oracle GlassFish Server.

TABLE 10–1 Oracle GlassFish Server Preconfigured Repositories

Publisher	URL	Description
release.glassfish.oracle.com	pkg.oracle.com/glassfish/v3/release/	Commercial, production quality versions of the core components and add-on components of Oracle GlassFish Server
contrib.glassfish.oracle.com	pkg.oracle.com/glassfish/v3/contrib/	Additional add-on components that are contributed by Oracle partners
contrib.glassfish.org	pkg.glassfish.org/v3/contrib/	Additional add-on components that are contributed by the GlassFish community
dev.glassfish.oracle.com	pkg.oracle.com/glassfish/v3/dev/	Developmental, beta, and prerelease versions of the components in the pkg.oracle.com/glassfish/v3/release/repository

For Oracle GlassFish Server installations, the `release.glassfish.oracle.com` publisher is designated as the *preferred publisher*. To ensure that installations contain only commercial, production quality version of components by default, the preferred publisher is treated specially by the tools for updating GlassFish Server software:

- If an add-on component is available from the preferred publisher and from other publishers, the Update Tool GUI and the pkg CLI list and install the component from the preferred publisher.
- After a component has been installed from the preferred publisher, the Update Tool, Software Update, and desktop notifier GUIs search for updates to that component only from the preferred publisher.

If you have support for Oracle GlassFish Server, you can change the preferred publisher's repository URL from the Oracle GlassFish Server release repository to the Oracle GlassFish Server support repository. For more information, see “[Enabling the Oracle GlassFish Server Support Repository](#)” on page 217.

Enabling the Oracle GlassFish Server Support Repository

If you have support for Oracle GlassFish Server, you can change the repository URL for the preferred provider, `release.glassfish.oracle.com`, to refer to the support repository instead of to the release repository. This support repository includes the content provided by the release repository, but also includes commercial, production quality updates that resolve issues reported by Oracle GlassFish Server customers.

Enabling the Oracle GlassFish Server support repository involves two tasks:

1. Your company's technical contact acquires the key and certificate files needed to access the support repository.
2. GlassFish Server administrators use the key and certificate files to change the `release.glassfish.oracle.com` publisher's repository URL to the support repository.

Note – The key and certificate files needed to enable access to the support repository expire. When they expire, you need to acquire new ones and apply them to your Oracle GlassFish Server installations.

▼ To Acquire the Key and Certificate Files for the Support Repository

To acquire the key and certificate files for the Oracle GlassFish Server support repository, your company's technical contact uses the pkg-register.oracle.com Certificate Generator.

Before You Begin Before using the Certificate Generator, you must add your Oracle GlassFish Server Customer Support Identification (CSI) numbers to your My Oracle Support account. If you do not yet have a My Oracle Support account, you can create one at <https://support.oracle.com>.

- 1 **In a web browser, go to `https://pkg-register.oracle.com` and sign in using your My Oracle Support account information.**

After signing in, the Certificate Requests page displays, showing “Oracle GlassFish Server 3 Support” as one of the products for which you can request a certificate.

- 2 **Select “Oracle GlassFish Server 3 Support” and then click Submit.**

The Certificate Requests: Additional Information page displays.

- 3 **Enter an optional comment if desired, and then click Submit.**

The Certificate Information page displays.

4 Note down the expiration date of the certificate.

When the current certificate expires, you will need to repeat this process to acquire new certificates.

5 Click Download Key and save the `Oracle_GlassFish_Server_3_Support.key.pem` file.**6 Click Download Certificate and save the `Oracle_GlassFish_Server_3_Support.certificate.pem` file.****7 Sign out of the Certificate Generator site.****8 Make the key and certificate files you saved available to your company's Oracle GlassFish Server administrators.**

Note – If you accidentally delete or misplace these files, you can sign into <https://pkg-register.oracle.com> using your My Oracle Support account information and get replacement copies of them.

▼ **To Change the `release.glassfish.oracle.com` Publisher's URL to the Support Repository**

Use the `pkg` utility to change the repository URL for the `release.glassfish.oracle.com` publisher to the Oracle GlassFish Server support repository for an Oracle GlassFish Server installation.

Before You Begin Before you use the `pkg` utility, you must copy the `Oracle_GlassFish_Server_3_Support.key.pem` key file and the `Oracle_GlassFish_Server_3_Support.certificate.pem` certificate file to a location accessible from the host where Oracle GlassFish Server is installed.

1 On the host where Oracle GlassFish Server is installed, navigate to the parent installation directory:

```
cd as-install-parent
```

The default parent installation directory is `glassfish3`.

2 Use the `pkg set-publisher` command to change the repository URL:

- On Unix systems (including Mac OS), where backslash (`\`) is the command line continuation character:

```
bin/pkg set-publisher -P \  
-k path-to-key-file/Oracle_GlassFish_Server_3_Support.key.pem \  
-c path-to-certificate-file/Oracle_GlassFish_Server_3_Support.certificate.pem \  
-O https://pkg.oracle.com/glassfish/v3/support release.glassfish.oracle.com
```

- On Windows systems, where caret (^) is the command line continuation character:

```
bin\pkg set-publisher -P ^
-k path-to-key-file\Oracle_GlassFish_Server_3_Support.key.pem ^
-c path-to-certificate-file\Oracle_GlassFish_Server_3_Support.certificate.pem ^
-o https://pkg.oracle.com/glassfish/v3/support release.glassfish.oracle.com
```

GlassFish Server Open Source Edition Repositories

Table 10–2 lists the preconfigured repositories for GlassFish Server Open Source Edition.

TABLE 10–2 GlassFish Server Open Source Edition Preconfigured Repositories

Publisher	URL	Description
release.javaesdk.oracle.com	pkg.sun.com/javaesdk/6/release/	Production quality versions of the core components and add-on components of GlassFish Server Open Source Edition
stable.glassfish.org	pkg.glassfish.org/v3/stable/	Most current stable pre-release build of core and add-on components
contrib.glassfish.oracle.com	pkg.sun.com/glassfish/v3/contrib/	Additional add-on components that are contributed by Oracle partners
contrib.glassfish.org	pkg.glassfish.org/v3/contrib/	Additional add-on components that are contributed by the GlassFish community
dev.glassfish.org	pkg.glassfish.org/v3/dev/	Developmental, beta, and prerelease versions of the components in the pkg.sun.com/javaesdk/6/release/repository

For GlassFish Server Open Source Edition installations, `stable.glassfish.org` is the preferred publisher.

Tools for Extending and Updating GlassFish Server

GlassFish Server provides the following tools for updating software on a deployed server:

- “Update Tool” on page 220
- “The pkg Command” on page 220
- “Administration Console” on page 220

Update Tool

Update Tool is a standalone graphical tool bundled with GlassFish Server that can be used to find and install updates and add-ons on a deployed GlassFish Server instance.

To start Update Tool, type the following command:

```
as-install-parent/bin/updatetool
```

For instructions for using Update Tool, see the Update Tool online help.

For additional information about Update Tool, see the following wikis:

- [Multi-platform Packaging for Layered Distros](#)
- [Toolkit Documentation](#)

The pkg Command

The `pkg` command is the command-line equivalent to Update Tool. Most of the tasks that can be performed with the graphical Update Tool can be performed from a command line using the `pkg` tool.

The `pkg` command is located in the *as-install-parent/bin* directory. To run the `pkg` command without specifying the path, ensure that this directory is in your path.

The `pkg` command enables you to create update scripts and to update software on headless systems. A headless system does not have a monitor, graphics card, or keyboard.

Most of the procedures in this chapter are based on the `pkg` command. A set of reference pages that contain details about using the `pkg` command is included with GlassFish Server in the *as-install-parent/pkg/man* directory.

Administration Console

The Administration Console enables you to perform the following tasks that are related to extending and updating GlassFish Server:

- Installing add-on components
- Viewing available updates to installed components
- Viewing installed components

For more information, see the Administration Console online help.

Note – The Administration Console does *not* enable you to update or remove installed components. Instead, you must stop the GlassFish Server domain and use Update Tool or the `pkg` command.

When the Administration Console starts, it automatically checks the package repositories for updates to installed components. In situations where the GlassFish Server host does not have access to the package repositories, you can disable this automatic check by setting a JVM option:

```
asadmin> create-jvm-options -Dcom.sun.enterprise.tools.admingui.NO_NETWORK=true
```

After setting this JVM option, restart the domain.

Adding Components

This section provides instructions for using the `pkg` command to install GlassFish Server add-on components on your deployed GlassFish Server.

▼ To Install an Add-on Component

The `pkg` command enables you to install an add-on component on your system. If multiple versions of a package are available, the latest one is applied unless you specify otherwise. The `pkg` command, located in the *as-install-parent/bin* directory,

Note – If the `pkg` component, the `update tool` component, or any other valid component that you try to invoke from the command line is not yet installed on your deployed GlassFish Server, you will receive a query asking if you want to install the component. Answer Y to install the component.

Before You Begin GlassFish Server 3.1 must be fully deployed before you can install additional components. If you need installation instructions, see *GlassFish Server Open Source Edition 3.1 Installation Guide*.

- 1 **To ensure that the `pkg` command can locate the application image, change to the base installation directory for GlassFish Server.**

```
cd as-install
```

```
as-install
```

The base installation directory for GlassFish Server.

- 2 **List your installed components:**

```
pkg list
```

Information similar to the following is displayed:

NAME (PUBLISHER)	VERSION	STATE	UFI
felix	2.0.2-0	installed	u---
glassfish-appclient	3.0.1-14	installed	u---
glassfish-cmp	3.0.1-14	installed	u---
glassfish-common	3.0.1-14	installed	u---
glassfish-common-full	3.0.1-14	installed	u---
glassfish-corba	3.0.0-41	installed	u---
glassfish-corba-base	3.0.0-41	installed	u---
glassfish-ejb	3.0.1-14	installed	u---
glassfish-ejb-lite	3.0.1-14	installed	u---
glassfish-full-incorporation	3.0.1-14	installed	u---
glassfish-full-profile	3.0.1-14	installed	u---
glassfish-grizzly	1.9.18-9	installed	u---
glassfish-grizzly-full	1.9.18-9	installed	u---
glassfish-gui	3.0.1-14	installed	u---
glassfish-hk2	3.0.1-14	installed	u---
glassfish-javahelp	2.0.2-0	installed	u---
glassfish-jca	3.0.1-14	installed	u---
glassfish-jcdi	3.0.1-14	installed	u---
glassfish-jdbc	3.0.1-14	installed	u---
glassfish-jms	3.0.1-14	installed	u---
glassfish-jpa	3.0.1-14	installed	u---
glassfish-jsf	2.0.2-10	installed	u---
glassfish-jta	3.0.1-14	installed	u---
glassfish-jts	3.0.1-14	installed	u---
glassfish-management	3.0.1-14	installed	u---
glassfish-nucleus	3.0.1-14	installed	u---
glassfish-registration	3.0.1-14	installed	u---
glassfish-scripting	3.0.1-14	installed	u---
glassfish-upgrade	3.0.1-14	installed	u---
glassfish-web	3.0.1-14	installed	u---
glassfish-web-incorporation	3.0.1-14	installed	u---
glassfish-web-profile	3.0.1-14	installed	u---
javadb-client	10.5.3.0-1	installed	----
javadb-common	10.5.3.0-1	installed	----
javadb-core	10.5.3.0-1	installed	----
jersey	1.1.5-1.0	installed	u---
metro	2.0-29	installed	u---
mq-bin-exe	4.4.2-2.7	installed	----
mq-bin-sh	4.4.2-2.7	installed	----
mq-config-gf	4.4.2-2.7	installed	----
mq-core	4.4.2-2.7	installed	----
mq-server	4.4.2-2.7	installed	----
pkg	1.122.2-38.2493	installed	----
pkg-java	1.122.38.2493	installed	----
pkg-toolkit-incorporation	2.3.0-38.2493	installed	----
python2.4-minimal	2.4.4.0-38.2493	installed	----

3 List all packages that are available:

pkg list -a

Information similar to the following is displayed from the repository. For clarity, some items are omitted from this example.

NAME (PUBLISHER)	VERSION	STATE	UFI
ant (contrib.glassfish.org)	1.7.1-0.6	known	----

felix (dev.glassfish.org)	2.0.2-0	known	----
felix	2.0.2-0	installed	u---
felix (release.glassfish.oracle.com)	2.0.2-0	known	u---
glassfish-appclient (dev.glassfish.org)	3.0.1-15	known	----
glassfish-appclient	3.0.1-14	installed	u---
glassfish-appclient (release.glassfish.oracle.com)	3.0-74.2	known	u---
glassfish-branding (release.glassfish.oracle.com)	3.0-74.2	known	----
glassfish-branding-gui (release.glassfish.oracle.com)	3.0-74.2	known	----
glassfish-cluster-util (contrib.glassfish.org)	1.0-0.0	known	----
glassfish-cmp (dev.glassfish.org)	3.0.1-15	known	----
glassfish-cmp	3.0.1-14	installed	u---
glassfish-cmp (release.glassfish.oracle.com)	3.0-74.2	known	u---
...			
metro (dev.glassfish.org)	2.0.1-3	known	----
metro	2.0-29	installed	u---
metro (release.glassfish.oracle.com)	2.0-29	known	u---
mq-bin-exe	4.4.2-2.7	installed	----
mq-bin-exe (dev.glassfish.org)	4.4.2-2.7	known	----
mq-bin-exe (release.glassfish.oracle.com)	4.4.1-7.2	known	u---
mq-bin-sh	4.4.2-2.7	installed	----
mq-bin-sh (dev.glassfish.org)	4.4.2-2.7	known	----
mq-bin-sh (release.glassfish.oracle.com)	4.4.1-7.2	known	u---
mq-branding (release.glassfish.oracle.com)	4.4.1-7.2	known	----
mq-config-gf	4.4.2-2.7	installed	----
mq-config-gf (dev.glassfish.org)	4.4.2-2.7	known	----
mq-config-gf (release.glassfish.oracle.com)	4.4.1-7.2	known	u---
mq-core	4.4.2-2.7	installed	----
mq-core (dev.glassfish.org)	4.4.2-2.7	known	----
mq-core (release.glassfish.oracle.com)	4.4.1-7.2	known	u---
mq-docs (dev.glassfish.org)	4.4.2-2.7	known	----
mq-docs	4.4.1-7.2	known	u---
mq-docs (release.glassfish.oracle.com)	4.4.1-7.2	known	u---
mq-locale (dev.glassfish.org)	4.4.2-2.7	known	----
mq-locale	4.4.1-7.2	known	u---
mq-locale (release.glassfish.oracle.com)	4.4.1-7.2	known	u---
mq-server	4.4.2-2.7	installed	----
mq-server (dev.glassfish.org)	4.4.2-2.7	known	----
mq-server (release.glassfish.oracle.com)	4.4.1-7.2	known	u---
...			
sdk-branding-full (release.glassfish.oracle.com)	3.0-74.2	known	----
sdk-branding-web (release.glassfish.oracle.com)	3.0-74.2	known	----
sun-javaee-engine (dev.glassfish.org)	3.0.1-15	known	----
sun-javaee-engine	3.0-74.2	known	u---
updatetool	2.3.0-38.2493	known	----
updatetool (dev.glassfish.org)	2.3.0-38.2493	known	----
updatetool (release.glassfish.oracle.com)	2.3.0-38.2493	known	----
wxpython2.8-minimal	2.8.10.1-38.2493	known	----
wxpython2.8-minimal (dev.glassfish.org)	2.8.10.1-38.2493	known	----
wxpython2.8-minimal (release.glassfish.oracle.com)	2.8.10.1-38.2493	known	----
wxpython2.8-minimal	2.8.7.1-8.724	known	----

4 Install a package from the available packages list.

pkg install *package-name*

For example:

pkg install javadb

The most recent version of the component is installed and information similar to the following is displayed:

DOWNLOAD	PKGS	FILES	XFER (MB)
javadb	0/1	61/200	2.10/7.26
PHASE	ACTIONS		
Install Phase	222/222		

5 To apply your changes, restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

See Also For the full syntax and options of the pkg command, see the pkg(1) man page. This man page is installed only after the pkg utilities have been fully installed.

To view this man page on UNIX and Linux systems, type the following command in a terminal window:

```
man -M as-install-parent/pkg/man/ pkg
```

To view this man page on Windows systems, use the type command to view the file *as-install-parent\pkg\man\cat1\pkg.1*.

Updating Installed Components

This section provides the following instructions for updating GlassFish Server components after they have been installed:

- [“To Update an Installed Component” on page 224](#)
- [“To Update All Installed Components in an Image” on page 226](#)

▼ To Update an Installed Component

When you install an updated version of a component, only those files that have been modified are downloaded and installed. Files that have been removed in the updated package are removed during the update process.

1 Stop GlassFish Server.

See [“To Stop a Domain” on page 116](#).

2 To ensure that the pkg command can locate the application image, change to the base installation directory for GlassFish Server.

```
cd as-install
```


as-install

The base installation directory for GlassFish Server.

3 Obtain a list of only the installed packages that have available updates:

pkg list -u

Information similar to the following is displayed:

NAME (AUTHORITY)	VERSION	STATE	UFIX
glassfish-ejb	3.0.1-14	installed	u---
glassfish-hk2	3.0.1-14	installed	u---
glassfish-jca	3.0.1-14	installed	u---
glassfish-jcdi	3.0.1-14	installed	u---
glassfish-web	3.0.1-14	installed	u---
glassfish-web-incorporation	3.0.1-14	installed	u---
glassfish-web-profile	3.0.1-14	installed	u---
jersey	1.1.5-1.0	installed	u---
metro	2.0-29	installed	u---

4 Install a new version of a package.

pkg install package-name

For example:

pkg install metro

Information similar to the following is displayed:

DOWNLOAD	PKGS	FILES	XFER (MB)
Completed	1/1	5/5	0.49/0.49
PHASE	ACTIONS		
Removal Phase	2/2		
Update Phase	7/7		
Install Phase	2/2		

5 Start GlassFish Server.

See [“To Start a Domain” on page 115](#).

See Also For the full syntax and options of the pkg command, see the pkg(1) man page. This man page is installed only after the pkg utilities have been fully installed.

To view this man page on UNIX and Linux systems, type the following command in a terminal window:

```
man -M as-install-parent/pkg/man/ pkg
```

To view this man page on Windows systems, use the type command to view the file *as-install-parent\pkg\man\cat1\pkg.1*.

▼ To Update All Installed Components in an Image

GlassFish Server enables you to maintain multiple installation images on a single system. When you update an installation image, all the components that are present in that image are updated to new versions, if new versions are available. When you install updated versions of components, only those files that have been modified are downloaded and installed. Files that have been removed in the updated package are removed during the update process.

1 Stop GlassFish Server.

See [“To Stop a Domain” on page 116](#).

2 To ensure that the pkg command can locate the application image, change to the base installation directory for GlassFish Server.

`cd as-install`

as-install

The base installation directory for GlassFish Server.

3 Install all packages for the image.

`pkg image-update`

Information similar to the following is displayed:

DOWNLOAD	PKGS	FILES	XFER (MB)
Completed	6/6	729/729	21.59/21.59
PHASE	ACTIONS		
Removal Phase	887/887		
Update Phase	253/253		
Install Phase	584/584		

4 Start GlassFish Server.

See [“To Start a Domain” on page 115](#).

See Also For the full syntax and options of the pkg command, see the pkg(1) man page. This man page is installed only after the pkg utilities have been fully installed.

To view this man page on UNIX and Linux systems, type the following command in a terminal window:

`man -M as-install-parent/pkg/man/ pkg`

To view this man page on Windows systems, use the type command to view the file *as-install-parent\pkg\man\cat1\pkg.1*.

Removing Installed Components

If you are discontinuing use of a component and want to remove it from your system, you can do this by using the `uninstall` command. If you need to revert to a prior version of a component, you will need to uninstall the current version and install the prior version by specifying the version number.

- [“To Uninstall an Installed Component” on page 227](#)
- [“To Uninstall and Revert to an Older Version of a Component” on page 229](#)

▼ To Uninstall an Installed Component

1 Stop GlassFish Server.

See [“To Stop a Domain” on page 116](#).

2 To ensure that the `pkg` command can locate the application image, change to the base installation directory for GlassFish Server.

```
cd as-install
```

```
as-install
```

The base installation directory for GlassFish Server.

3 Obtain a list of all your installed components.

```
pkg list
```

NAME (PUBLISHER)	VERSION	STATE	UFI
felix	2.0.2-0	installed	u---
glassfish-appclient	3.0.1-14	installed	u---
glassfish-cmp	3.0.1-14	installed	u---
glassfish-common	3.0.1-14	installed	u---
glassfish-common-full	3.0.1-14	installed	u---
glassfish-corba	3.0.0-41	installed	u---
glassfish-corba-base	3.0.0-41	installed	u---
glassfish-ejb	3.0.1-14	installed	u---
glassfish-ejb-lite	3.0.1-14	installed	u---
glassfish-full-incorporation	3.0.1-14	installed	u---
glassfish-full-profile	3.0.1-14	installed	u---
glassfish-grizzly	1.9.18-9	installed	u---
glassfish-grizzly-full	1.9.18-9	installed	u---
glassfish-gui	3.0.1-14	installed	u---
glassfish-hk2	3.0.1-14	installed	u---
glassfish-javahelp	2.0.2-0	installed	u---
glassfish-jca	3.0.1-14	installed	u---
glassfish-jcdi	3.0.1-14	installed	u---
glassfish-jdbc	3.0.1-14	installed	u---
glassfish-jms	3.0.1-14	installed	u---
glassfish-jpa	3.0.1-14	installed	u---
glassfish-jsf	2.0.2-10	installed	u---
glassfish-jta	3.0.1-14	installed	u---

glassfish-jts	3.0.1-14	installed	u---
glassfish-management	3.0.1-14	installed	u---
glassfish-nucleus	3.0.1-14	installed	u---
glassfish-registration	3.0.1-14	installed	u---
glassfish-scripting	3.0.1-14	installed	u---
glassfish-upgrade	3.0.1-14	installed	u---
glassfish-web	3.0.1-14	installed	u---
glassfish-web-incorporation	3.0.1-14	installed	u---
glassfish-web-profile	3.0.1-14	installed	u---
javadb-client	10.5.3.0-1	installed	----
javadb-common	10.5.3.0-1	installed	----
javadb-core	10.5.3.0-1	installed	----
jersey	1.1.5-1.0	installed	u---
metro	2.0-29	installed	u---
mq-bin-exe	4.4.2-2.7	installed	----
mq-bin-sh	4.4.2-2.7	installed	----
mq-config-gf	4.4.2-2.7	installed	----
mq-core	4.4.2-2.7	installed	----
mq-server	4.4.2-2.7	installed	----
pkg	1.122.2-38.2493	installed	----
pkg-java	1.122-38.2493	installed	----
pkg-toolkit-incorporation	2.3.0-38.2493	installed	----
python2.4-minimal	2.4.4.0-38.2493	installed	----

4 Uninstall the component that you want to remove from your system.

pkg uninstall *package-name*

For example:

pkg uninstall python2.4-minimal

5 Start GlassFish Server.

See [“To Restart a Domain” on page 116](#).

See Also For the full syntax and options of the pkg command, see the pkg(1) man page. This man page is installed only after the pkg utilities have been fully installed.

To view this man page on UNIX and Linux systems, type the following command in a terminal window:

man -M as-install-parent/pkg/man/ pkg

To view this man page on Windows systems, use the type command to view the file *as-install-parent\pkg\man\cat1\pkg.1*.

▼ To Uninstall and Revert to an Older Version of a Component

If there is a malfunction in an installed component, you might want to revert to an older version of that component. The way to restore an older version of a component is to first uninstall the current version of the component, then install the specific older version that you want to reinstate.

Before You Begin Be sure to verify that the older version of the component is in the repository before you uninstall your current version.

1 Stop GlassFish Server.

See [“To Stop a Domain” on page 116](#).

2 To ensure that the `pkg` command can locate the application image, change to the base installation directory for GlassFish Server.

```
cd as-install
```

```
as-install
```

The base installation directory for GlassFish Server.

3 Verify that the older version of the component is still available:

```
pkg list -fa pkg-name
```

For example:

```
pkg list -fa jersey
NAME (PUBLISHER)          VERSION          STATE          UFIX
jersey                   1.1.5-1.0       installed      ----
jersey                   1.1.4.1-1.0     known         u---
jersey                   1.1.4.1-1.0     known         u---
jersey                   1.1.4.1-1.0     known         u---
```

4 Obtain a list of your installed components:

```
pkg list
```

5 Uninstall the currently-installed component that you want to replace.

```
pkg uninstall package-name
```

For example:

```
pkg uninstall jersey
```

6 Install the older version of the component.

```
pkg install package-name@version
```

For example:

```
pkg install jersey@0.7-0.2
```

7 Verify that the older version is installed:

```
pkg list
```

8 Start GlassFish Server.

See [“To Start a Domain” on page 115](#).

See Also For the full syntax and options of the `pkg` command, see the `pkg(1)` man page. This man page is installed only after the `pkg` utilities have been fully installed.

To view this man page on UNIX and Linux systems, type the following command in a terminal window:

```
man -M as-install-parent/pkg/man/ pkg
```

To view this man page on Windows systems, use the `type` command to view the file `as-install-parent\pkg\man\cat1\pkg.1`.

Upgrading to Oracle GlassFish Server From GlassFish Server Open Source Edition

Oracle provides software support only for Oracle GlassFish Server, not for GlassFish Server Open Source Edition. Additionally, some features of Oracle GlassFish Server are not available in GlassFish Server Open Source Edition.

If you are using GlassFish Server Open Source Edition, you can upgrade to Oracle GlassFish Server by [purchasing a right-to-use](#) and installing the add-on component for upgrading GlassFish Server Open Source Edition. To obtain this component, and to ensure the reliability of your upgraded installation, you must configure your GlassFish Server installation to obtain updates from the appropriate repositories.

Note – To use Oracle GlassFish Server in production after the upgrade, you must obtain a right to use this software from Oracle.

You can upgrade to GlassFish Server Open Source Edition by using either Update Tool or the `pkg` command.

▼ To Upgrade to GlassFish Server Open Source Edition by Using Update Tool

The procedure explains how to use Update Tool to obtain and install the add-on component for upgrading GlassFish Server Open Source Edition to Oracle GlassFish Server. For general instructions for using Update Tool, see the Update Tool online help.

Before You Begin Ensure that GlassFish Server Open Source Edition 3.1 is installed on your machine.

1 Start Update Tool.

as-install-parent/bin/updatetool

2 From the Application Images list, select GlassFish Server Open Source Edition.

3 Click Edit Properties.

The Image Properties window opens.

4 (Optional) In the Image Properties window, change image title to Oracle GlassFish Server.

5 Remove the following publishers from the list of software sources for the image:

- `dev.glassfish.org`
- `stable.glassfish.org`
- `release.javaeejdk.oracle.com`

Remove each publisher as follows:

a. In the Image Properties window, select the publisher that you are removing.

b. Click Remove.

6 Add repositories for GlassFish Server Open Source Edition to the application image.

Add each repository as follows:

a. In the Image Properties window, click Add.

The Publisher Properties window opens.

b. In the Publisher Properties window, specify the properties of the repository that you are adding and click OK.

The properties to specify for each repository are listed in the following table.

Publisher Name	Repository URL
release.glassfish.oracle.com	http://pkg.oracle.com/glassfish/v3/release/
dev.glassfish.oracle.com	http://pkg.oracle.com/glassfish/v3/dev/

For more information about these repositories, see [“Oracle GlassFish Server Repositories” on page 216](#).

The Publisher Properties window closes. The publisher is added to the Software Sources list in the Image Properties window.

- 7 In the Image Properties window, set the Preferred option for the `release.glassfish.oracle.com` publisher and click OK.

The Image Properties window closes.

- 8 Under GlassFish Server Open Source Edition in the Available Images list, select Available Add-ons.
- 9 Select the add-on component for upgrading the distribution of GlassFish Server Open Source Edition that is installed:
 - If the Web Profile distribution is installed, select the Oracle GlassFish Server Web Profile add-on component.
 - If the Full Platform distribution is installed, install the Oracle GlassFish Server Full Platform add-on component.
- 10 Click Install.
- 11 To apply your changes, restart GlassFish Server.
See [“To Restart a Domain” on page 116](#).

▼ To Upgrade to GlassFish Server Open Source Edition by Using the pkg Command

Before You Begin Ensure that GlassFish Server Open Source Edition 3.1 is installed on your machine.

- 1 To ensure that the `pkg` command can locate the application image, change to the base installation directory for GlassFish Server.

```
cd as-install
```

```
as-install
```

The base installation directory for GlassFish Server.

2 Remove the following publishers from the list of publishers for the image:

- `dev.glassfish.org`
- `stable.glassfish.org`
- `release.javaeejdk.oracle.com`

```
pkg unset-publisher dev.glassfish.org stable.glassfish.org \
release.javaeejdk.oracle.com
```

3 Add repositories for GlassFish Server Open Source Edition to the application image.

The properties to specify for each repository are listed in the following table.

Publisher Name	Origin Uniform Resource Identifier (URI)
<code>release.glassfish.oracle.com</code>	<code>http://pkg.oracle.com/glassfish/v3/release/</code>
<code>dev.glassfish.oracle.com</code>	<code>http://pkg.oracle.com/glassfish/v3/dev/</code>

The publisher `release.glassfish.oracle.com` must be the preferred publisher.

For more information about these repositories, see [“Oracle GlassFish Server Repositories” on page 216](#).

a. Add the repository whose publisher is `release.glassfish.oracle.com`, which must be the preferred publisher.

```
pkg set-publisher -P -O http://pkg.oracle.com/glassfish/v3/release/ \
release.glassfish.oracle.com
```

b. Add the repository whose publisher is `dev.glassfish.oracle.com`.

```
pkg set-publisher -O http://pkg.oracle.com/glassfish/v3/dev/ \
dev.glassfish.oracle.com
```

4 Install the add-on component for upgrading the distribution of GlassFish Server Open Source Edition that is installed:

- If the Web Profile distribution is installed, install the Oracle GlassFish Server Web Profile add-on component.

```
pkg install glassfish-enterprise-web-profile
```

- If the Full Platform distribution is installed, install the Oracle GlassFish Server Full Platform add-on component.

```
pkg install glassfish-enterprise-full-profile
```

5 To apply your changes, restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

See Also For the full syntax and options of the `pkg` command, see the `pkg(1)` man page. This man page is installed only after the `pkg` utilities have been fully installed.

To view this man page on UNIX and Linux systems, type the following command in a terminal window:

```
man -M as-install-parent/pkg/man/ pkg
```

To view this man page on Windows systems, use the `type` command to view the file `as-install-parent\pkg\man\cat1\pkg.1`.

Extending and Updating GlassFish Server Inside a Closed Network

GlassFish Server might be installed on a machine without an Internet connection. For example, for security reasons, GlassFish Server might be installed behind a restrictive firewall, or it might be installed on a LAN that is physically isolated from other networks. In such situations, neither the graphical Update Tool nor the `pkg` command-line utility that are included with GlassFish Server can contact a public repository server to download and install updates. Therefore, a local repository server must be configured inside the closed network and the GlassFish Server updates installed from there.

The following topics are addressed here:

1. [Installing the Pre-Installed Toolkit Image inside a closed network](#)

The Pre-Installed Toolkit Image provides the software components that are required to run a local repository server inside a closed network.

2. [Configuring and running a local repository server on a locally accessible host](#)

A local repository server makes it possible for a GlassFish Server installation to obtain packages and updates from inside a closed network rather than from the default public repository servers.

3. [Configuring a GlassFish Server installation to obtain updates from the local repository server](#)

Each GlassFish Server installation that will be updated inside a closed network must be configured to use a local repository server instead of the default public repository servers.

4. [Installing the GlassFish Server updates](#)

The GlassFish Server updates inside the closed network are performed normally, but use the local repository server instead of the public repository servers.

▼ To Install the Pre-Installed Toolkit Image Inside a Closed Network

The Pre-Installed Toolkit Image provides the software components that are required to configure and run a local repository server inside a closed network. Running a local repository server makes it possible for a GlassFish Server installation to obtain packages and updates from within the closed network rather than from the default public GlassFish Server repositories.

- Before You Begin**
- The first three steps of this procedure require access to a machine that is connected to the Internet. This machine must also be able to write to some type of removable medium, such as CD, DVD, USB drive, or flash memory card.
 - The remaining steps in the procedure are performed on the machines that are inside the closed network, and do not require access to an Internet connection.

- 1 In a Web browser on the machine that is connected to the Internet, open the **Pre-installed Toolkit Images and Starter Repositories** (<http://wikis.sun.com/display/IpsBestPractices/Downloads>) page.

- 2 Download the ZIP file that contains the Pre-Installed Toolkit Image that is correct for your server's operating system and save it to the location of your choice.

The ZIP files are named according to operating system and architecture, using the following format:

`pkg-toolkit-2.3.3-platform-arch.zip`

For example, the ZIP file for 32-bit Linux operating systems is named:

`pkg-toolkit-2.3.3-linux-i386.zip`

Download the correct ZIP file for the operating system and architecture on each of the following machines:

- The machine on which the local repository server will be run
 - Each machine on which one or more GlassFish Server installations will be updated inside the closed network
- 3 Copy each Pre-Installed Toolkit Image ZIP file to a removable medium that you can physically transport to the machines inside the closed network.
 - 4 Copy the correct Pre-Installed Toolkit Image ZIP file for each operating system from the removable medium to the directories of your choice on the following machines:
 - The machine on which the local repository server will be run
 - Each machine on which one or more GlassFish Server installations will be updated inside the closed network

- 5 **Unzip the Pre-Installed Toolkit Image ZIP file on each machine to which you copied the ZIP file in the preceding step.**

The size of the expanded Pre-Installed Toolkit Image ZIP file depends on the operating system:

- On Windows systems, the expanded ZIP file is approximately 11 Mbytes.
- On Linux and Solaris systems, the expanded ZIP file is approximately 13 Mbytes.

- 6 **(Optional) On each machine to which you copied the Pre-Installed Toolkit Image, verify that the `pkg` command-line tool is correctly installed.**

- a. **Change to the `pkg/bin` subdirectory of the directory that contains the unzipped Pre-Installed Toolkit Image.**

```
cd toolkit-dir/pkg/bin
```

toolkit-dir The directory that contains the unzipped Pre-Installed Toolkit Image.

- b. **Display the `pkg` version.**

```
./pkg version
```

Output similar to the following is displayed:

```
1.122.2-38.2791
```

▼ **To Configure a Local Repository Server Inside a Closed Network**

A local repository server makes it possible for a GlassFish Server installation to obtain packages and updates from within a closed network, rather than from the default public repository servers.

Before You Begin Ensure that the following conditions are met:

- You have access to a machine that is connected to the Internet.
- The machine that is connected to the Internet can write to some type of removable medium, such as CD, DVD, USB drive, or flash memory card.
- The Pre-Installed Toolkit Image has been installed as described in [“To Install the Pre-Installed Toolkit Image Inside a Closed Network” on page 235](#).

- 1 In a Web browser on the machine that is connected to the Internet, download the ZIP file that contains the GlassFish Server repository for the operating system on which GlassFish Server is running.

The repository ZIP files for GlassFish Server are distributed as patches through the [My Oracle Support](#) Web site.

- a. Log in to the [My Oracle Support \(https://support.oracle.com\)](https://support.oracle.com) site.
- b. Click the Patches & Updates tab.
- c. Enter the desired patch number in the Patch Name or Number field and then click Search.

Operating System	Patch ID
sunos-sparc	145091
sunos-i386	145092
linux-i386	145093
windows-i386	145094
mac-universal	145095

A list of patches appears at the bottom of the page.

- d. Download the ZIP file for the latest version of the desired patch.
- 2 Copy each ZIP file that you downloaded from My Oracle Support onto a removable medium that you can physically transport to the local repository server.

Each My Oracle Support ZIP file is approximately 270 Mbytes in size.

- 3 Copy each My Oracle Support ZIP file from the removable medium to the local repository server machine.

The directory used for the My Oracle Support ZIP files should be different than the directory in which the Pre-Installed Toolkit Image was copied, as described in “[To Install the Pre-Installed Toolkit Image Inside a Closed Network](#)” on page 235.

- 4 Unzip each My Oracle Support ZIP file that you copied in the preceding step.

The My Oracle Support ZIP files are wrappers that contain a GlassFish Server repository ZIP file, a README file, and a license file. For example, the My Oracle Support ZIP file for Linux contains the following files:

```
LEGAL_LICENSE.TXT
README.145093-01
ogs-3.0.1-repo-linux-i386.zip
```

In this example, the GlassFish Server repository ZIP file is named `ogs-3.0.1-repo-linux-i386.zip`.

a. Unzip the My Oracle Support ZIP file.

For example:

```
unzip 145093-01
```

b. Change to the directory that was created when the My Oracle Support ZIP file was unzipped.

For example:

```
cd 145093-01
```

c. Unzip the GlassFish Server repository ZIP file.

For example:

```
unzip ogs-3.0.1-repo-linux-i386.zip
```

5 On the local repository server machine, start the repository server daemon.

a. Change to the Pre-Installed Toolkit Image `pkg/bin` directory.

```
cd toolkit-dir/pkg/bin
```

toolkit-dir The directory that contains the unzipped Pre-Installed Toolkit Image.

b. Start the `pkg.depotd` daemon.

```
./pkg.depotd -d repository-dir -p port
```

repository-dir The directory that contains the unzipped GlassFish Server repository.

port Your choice of port number for requests to the repository server. The default is 80.

Several startup messages are displayed as the repository daemon initializes, as shown in the following example.

Example 10-1 Starting a Local Repository Daemon

This example starts the `pkg.depotd` daemon using the following parameters:

`/opt/toolkit` The name of the Pre-Installed Toolkit Image directory.

`/opt/145093-01/linux-i386/` The GlassFish Server repository directory.

`30000` The port number used by the local repository daemon.

```
./pkg.depotd -d /opt/145093-01/linux-i386/ -p 30000
[ Jun 15 08:06:38 ] ENGINE Listening for SIGHUP.
[ Jun 15 08:06:38 ] ENGINE Listening for SIGTERM.
[ Jun 15 08:06:38 ] ENGINE Listening for SIGUSR1.
```

```
[ Jun 15 08:06:38 ] ENGINE Bus STARTING
[ Jun 15 08:06:38 ] ENGINE Started monitor thread '_TimeoutMonitor'.
[ Jun 15 08:06:38 ] ENGINE Serving on 0.0.0.0:30000
[ Jun 15 08:06:38 ] ENGINE Bus STARTED
```

▼ To Configure a GlassFish Server Installation to Use a Local Repository Server Inside a Closed Network

Each GlassFish Server installation that will be updated inside a closed network must be configured to use a local repository server instead of the default public repository servers.

Before You Begin This procedure must be completed on each GlassFish Server installation on which updates will be performed inside the closed network.

Ensure that the following conditions are met:

- The Pre-Installed Toolkit Image is installed on each machine on which one or more GlassFish Server installations will be upgraded, as described in [“To Install the Pre-Installed Toolkit Image Inside a Closed Network” on page 235](#)
- The local repository server is configured, as described in [“To Configure a Local Repository Server Inside a Closed Network” on page 236](#)

1 Set the `http_proxy` environment variable for the local repository server, if necessary.

This step is required if a proxy is needed to access the local repository from within the closed network.

```
export http_proxy=proxy-host:port
```

proxy-host The fully qualified URL for the proxy host.

port The port on which the *proxy-host* listens.

2 Change to the GlassFish Server installation directory.

```
cd as-install
```

as-install The path to the directory that contains the GlassFish Server installation that is to be updated.

Note – The remainder of this procedure must be performed from within the GlassFish Server installation directory.

3 Use the `pkg` command in the Pre-Installed Image Toolkit installation directory to tell the GlassFish Server installation to use the local repository server.

```
toolkit-dir/pkg/bin/pkg -R as-install set-publisher -Pe -O http://repo-host:port publisher
```

<i>toolkit-dir</i>	The directory that contains the unzipped Pre-Installed Toolkit Image.
<i>as-install</i>	The path to the directory that contains the GlassFish Server installation that is to be updated.
<i>repo-host</i>	The name of the server on which the <code>pkg.depotd</code> repository server daemon is running.
<i>port</i>	The port used for the <code>pkg.depotd</code> daemon, as specified in “To Configure a Local Repository Server Inside a Closed Network” on page 236 .
<i>publisher</i>	The name of the preconfigured GlassFish Server publisher. For GlassFish Server, use <code>release.glassfish.oracle.com</code> as the publisher.

4 (Optional) Verify that the local GlassFish Server repository is configured correctly.

toolkit-dir/pkg/bin/pkg publisher

The name of the of the local server repository and publisher should be listed, as shown in the following example.

Example 10–2 Configuring the pkg Command to Use a Local Repository

This example configures a GlassFish Server installation to use a local repository server. The following parameters are used:

<code>/opt/glassfish</code>	The GlassFish Server installation directory.
<code>/opt/toolkit</code>	The Pre-Installed Toolkit Image directory.
<code>rephost</code>	The host name of the local repository server.
<code>30000</code>	The port number used by the repository server.

```
/opt/toolkit/pkg/bin/pkg -R /opt/glassfish set-publisher -P --enable \
-O http://rephost:30000 release.glassfish.oracle.com
# /opt/toolkit/pkg/bin/pkg publisher
PUBLISHER                                TYPE      STATUS    URI
release.glassfish.oracle.com (preferred) origin    online    http://rephost:30000/
```

▼ To Install Updates From a Local Repository

After configuring a GlassFish Server installation to use a local repository server, as described in the previous procedures in this section, GlassFish Server updates inside a closed network are performed normally. The only difference is that the GlassFish Server installation being updated inside the closed network will use a local repository server instead of the public repository servers.

Perform the following procedure on each GlassFish Server installation that will be updated.

Before You Begin Ensure that each GlassFish Server installation that will be updated is configured to use the local repository server, as described in [“To Configure a GlassFish Server Installation to Use a Local Repository Server Inside a Closed Network”](#) on page 239.

1 Stop GlassFish Server.

See [“To Stop a Domain”](#) on page 116.

2 Change to the GlassFish Server installation directory.

`cd as-install`

Note – The remainder of this procedure must be performed from within the GlassFish Server installation directory.

3 Use either the graphical Update Tool or the pkg command-line utility to perform the desired updates.

For detailed instructions on updating or installing GlassFish Server components, see [“Updating Installed Components”](#) on page 224.

4 Start GlassFish Server.

See [“To Restart a Domain”](#) on page 116.

PART II

Resources and Services Administration

Administering Database Connectivity

This chapter provides procedures for performing database connectivity tasks in the Oracle GlassFish Server 3.1 environment by using the `asadmin` command-line utility.

The following topics are addressed here:

- [“About Database Connectivity” on page 245](#)
- [“Setting Up the Database” on page 246](#)
- [“Configuring Access to the Database” on page 249](#)
- [“Configuration Specifics for JDBC Drivers” on page 263](#)

Instructions for accomplishing these tasks by using the Administration Console are contained in the Administration Console online help.

About Database Connectivity

A database management system (DBMS) provides facilities for storing, organizing, and retrieving data. The information in databases is often described as persistent data because it is saved on disk and exists after the application process ends. Most business applications store data in relational databases. Applications can access database information by using the Java Database Connectivity (JDBC) API.

The key elements of database connectivity are the following:

- **Database.** The repository where data is stored for an enterprise. Java EE applications access relational databases through the JDBC API. For administration procedures, see [“Setting Up the Database” on page 246](#).
- **JDBC Connection Pool.** A JDBC connection pool is a group of reusable connections for a particular database. For administration procedures, see [“Administering JDBC Connection Pools” on page 250](#).

- **JDBC Resource.** A JDBC resource (data source) provides applications with a means of connecting to a database. To create a JDBC resource, specify the connection pool with which it is associated. Multiple JDBC resources can specify a single connection pool. A JDBC resource is identified by its Java Naming and Directory Interface (JNDI) name. For administration procedures, see [“Administering JDBC Resources” on page 258](#).
- **JDBC Driver.** A database driver is a software component that enables a Java application to interact with a database connectivity API. Each database requires its own driver. For administration procedures, see [“Integrating the JDBC Driver” on page 262](#).

At runtime, the following sequence occurs when an application connects to a database:

1. The application gets the JDBC resource associated with the database by making a call through the JNDI API.

Using the JNDI name of the resource, the naming and directory service locates the JDBC resource. Each JDBC resource specifies a connection pool.

2. Using the JDBC resource, the application gets a database connection.

GlassFish Server retrieves a physical connection from the connection pool that corresponds to the database. The pool defines connection attributes such as the database name (URL), user name, and password.

3. After the database connection is established, the application can read, modify, and add data to the database.

The application accesses the database by making calls to the JDBC API. The JDBC driver translates the application's JDBC calls into the protocol of the database server.

4. When the application is finished accessing the database, the application closes the connection and returns the connection to the connection pool.

Setting Up the Database

Most applications use relational databases to store, organize, and retrieve data. Applications access relational databases through the Java Database Connectivity (JDBC) API.

The following topics are addressed here:

- [“To Install the Database and Database Driver” on page 247](#)
- [“To Start the Database” on page 247](#)
- [“To Stop the Database” on page 248](#)
- [“Java DB Utility Scripts” on page 248](#)

▼ To Install the Database and Database Driver

1 Install a supported database product.

To see the current list of database products supported by GlassFish Server, refer to the *GlassFish Server Open Source Edition 3.1-3.1.1 Release Notes*.

2 Install a supported JDBC driver for the database product.

For a list of drivers supported by GlassFish Server, see [“Configuration Specifics for JDBC Drivers” on page 263](#).

3 Make the JDBC driver JAR file accessible to the domain administration server (DAS).

See [“Integrating the JDBC Driver” on page 262](#).

4 Create the database.

The application provider usually delivers scripts for creating and populating the database.

Next Steps You are now ready to create a connection pool for the database, and a JDBC resource that points to the connection pool. See [“To Create a JDBC Connection Pool” on page 250](#) and [“To Create a JDBC Resource” on page 259](#). The final step is to integrate the JDBC driver into an administrative domain as described in [“Integrating the JDBC Driver” on page 262](#).

▼ To Start the Database

GlassFish Server includes an implementation of Java DB (formerly known as Derby), however, you can use any JDBC-compliant database. The database is not started automatically when you start GlassFish Server, so if you have applications that require a database, you need to start Java DB manually by using the local `start-database` subcommand.

● Start the database by using the `start-database(1)` subcommand.

When the database server starts, or a client connects to it successfully, the following files are created at the location that is specified by the `--dbhome` option:

- The `derby.log` file contains the database server process log along with its standard output and standard error information.
- The database files contain your schema (for example, database tables).

Example 11–1 Starting a Database

This example starts Derby on the host `host1` and port `5001`.

```
asadmin> start-database --dbhost host1 --dbport 5001 --terse=true
Starting database in the background.
Log redirected to /opt/SUNWappserver/databases/javadb.log.
Command start-database executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help start-database` at the command line.

▼ To Stop the Database

Use the local `stop-database` subcommand to stop Java DB on a specified port. A single host can have multiple database server processes running on different ports.

- 1 If necessary, notify users that the database is being stopped.
- 2 Stop the database by using the `stop-database(1)` subcommand.

Example 11–2 Stopping a Database

This example stops Java DB on port 5001 of `localhost`.

```
asadmin> stop-database --dbhost=localhost --dbport=5001
onnection obtained for host: localhost, port number 5001.
Apache Derby Network Server - 10.2.2.1 - (538595) shutdown
at 2008-10-17 23:34:2 7.218 GMT
Command stop-database executed successfully.
```

Troubleshooting For a laptop that roams between networks, you might have trouble shutting down the database. If you start Java DB and then change your IP address, you will not be able to stop Java DB unless you add a specific `--dbhost` argument. For example, if you run `asadmin start-database --dbhost = 0.0.0.0`, and then disconnect Ethernet and switch to wifi, you should run a command similar to the following to stop the database:

```
asadmin stop-database --dbhost localhost
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help stop-database` at the command line.

Java DB Utility Scripts

The Java DB configuration that is available for use with GlassFish Server includes scripts that can help you use Java DB. The following scripts are available in the `as-install/javadb/frameworks/NetworkServer/bin` directory:

`startNetworkServer, startNetworkServer.bat`

Script to start the network server

`stopNetworkServer, stopNetworkServer.bat`

Script to stop the network server

`ij, ij.bat`

Interactive JDBC scripting tool

`dblook, dblook.bat`

Script to view all or part of the DDL for a database

`sysinfo, sysinfo.bat`

Script to display versioning information about the Java DB environment

`NetworkServerControl, NetworkServerControl.bat`

Script to execute commands on the `NetworkServerControl` API

▼ To Configure Your Environment to Run Java DB Utility Scripts

- 1 Ensure that the `JAVA_HOME` environment variable specifies the directory where the JDK is installed.
- 2 Set the `JAVADB_HOME` environment variable to point to the *as-install/derby* directory.

See Also For more information about these utilities, see the following documentation:

- *Derby Tools and Utilities Guide* (<http://db.apache.org/derby/docs/10.6/tools/>)
- (*Derby Server and Administration Guide* (<http://db.apache.org/derby/docs/10.6/adminguide/>))

Configuring Access to the Database

After establishing the database, you are ready to set up access for GlassFish Server applications. The high-level steps include creating a JDBC connection pool, creating a JDBC resource for the connection pool, and integrating a JDBC driver into an administrative domain.

Instructions for performing these steps are contained in the following sections:

- “Administering JDBC Connection Pools” on page 250
- “Administering JDBC Resources” on page 258
- “Enabling the `jdbc/___default` Resource in a Clustered Environment” on page 261
- “Integrating the JDBC Driver” on page 262

Administering JDBC Connection Pools

A *JDBC connection pool* is a group of reusable connections for a particular database. Because creating each new physical connection is time consuming, GlassFish Server maintains a pool of available connections. When an application requests a connection, it obtains one from the pool. When an application closes a connection, the connection is returned to the pool. JDBC connection pools can be globally accessible or be scoped to an enterprise application, web module, EJB module, connector module or application client module, as described in “Application-Scoped Resources” in *GlassFish Server Open Source Edition 3.1 Application Deployment Guide*.

A JDBC resource is created by specifying the connection pool with which the resource is associated. Multiple JDBC resources can specify a single connection pool. The properties of connection pools can vary with different database vendors. Some common properties are the database name (URL), the user name, and the password.

The following tasks and information are used to administer JDBC connection pools:

- [“To Create a JDBC Connection Pool” on page 250](#)
- [“To List JDBC Connection Pools” on page 251](#)
- [“To Contact \(Ping\) a Connection Pool” on page 252](#)
- [“To Reset \(Flush\) a Connection Pool” on page 252](#)
- [“To Update a JDBC Connection Pool” on page 253](#)
- [“To Delete a JDBC Connection Pool” on page 254](#)
- [“Configuring Specific JDBC Connection Pool Features” on page 254](#)

▼ To Create a JDBC Connection Pool

Use the `create-jdbc-connection-pool` subcommand in remote mode to register a new JDBC connection pool with the specified JDBC connection pool name. A JDBC connection pool or a connector connection pool can be created with authentication. You can either use a subcommand option to specify user, password, or other connection information using the `asadmin` utility, or specify the connection information in the XML descriptor file.

One connection pool is needed for each database, possibly more depending on the application. When you are building the connection pool, certain data specific to the JDBC driver and the database vendor is required. You can find some of the following specifics in “[Configuration Specifics for JDBC Drivers](#)” on page 263:

- Database vendor name
- Resource type, such as `javax.sql.DataSource` (local transactions only)
`javax.sql.XADataSource` (global transactions)
- Data source class name
- Required properties, such as the database name (URL), user name, and password

Creating a JDBC connection pool is a dynamic event and does not require server restart. However, there are some parameters that do require server restart. See [“Configuration Changes That Require Restart” on page 40](#).

Before You Begin Before creating the connection pool, you must first install and integrate the database and its associated JDBC driver. For instructions, see [“Setting Up the Database” on page 246](#).

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Create the JDBC connection pool by using the `create-jdbc-connection-pool(1)` subcommand.

3 (Optional) If needed, restart the server.

Some parameters require server restart. See [“Configuration Changes That Require Restart” on page 40](#).

Example 11–3 Creating a JDBC Connection Pool

This example creates a JDBC connection pool named `sample_derby_pool` on `localhost`.

```
asadmin> create-jdbc-connection-pool
--datasourceclassname org.apache.derby.jdbc.ClientDataSource
--restype javax.sql.XADataSource
--property portNumber=1527:password=APP:user=APP:serverName=
localhost:databaseName=sun-appserv-samples:connectionAttributes=
;create=true sample_derby_pool
Command create-jdbc-connection-pool executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-jdbc-connection-pool` at the command line.

▼ **To List JDBC Connection Pools**

Use the `list-jdbc-connection-pools` subcommand in remote mode to list all existing JDBC connection pools.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List the JDBC connection pools by using the `list-jdbc-connection-pools(1)` subcommand.

Example 11–4 Listing JDBC Connection Pools

This example lists the JDBC connection pools that are on `localhost`.

```
asadmin> list-jdbc-connection-pools
sample_derby_pool2
poolA
__TimerPool
DerbyPool
sample_derby_pool
Command list-jdbc-connection-pools executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-jdbc-connection-pools` at the command line.

▼ To Contact (Ping) a Connection Pool

Use the `ping-connection-pool` subcommand in remote mode to test if a connection pool is usable. For example, if you create a new JDBC connection pool for an application that is expected to be deployed later, you can test the JDBC pool with this subcommand before the application is deployed. Running a ping will force the creation of the pool if it hasn't already been created.

Before You Begin Before you can contact a connection pool, the connection pool must be created with authentication, and the server or database must be running.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Ping a connection pool by using the `ping-connection-pool(1)` subcommand.**

Example 11-5 Contacting a Connection Pool

This example tests to see if the `DerbyPool` connection pool is usable.

```
asadmin> ping-connection-pool DerbyPool
Command ping-connection-pool executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help ping-connection-pool` at the command line.

You can also specify that a JDBC connection pool is automatically tested when created or reconfigured by setting its `--ping` option to `true` (the default is `false`). See [“To Create a JDBC Connection Pool” on page 250](#) or [“To Update a JDBC Connection Pool” on page 253](#).

▼ To Reset (Flush) a Connection Pool

Use the `flush-connection-pool` in remote mode to reinitialize all connections established in the specified connection pool without the need for reconfiguring the pool. Connection pool reconfiguration can result in application redeployment, which is a time-consuming operation.

The JDBC connection pool or connector connection pool is reset to its initial state. Any existing live connections are destroyed, which means that the transactions associated with these connections are lost and must be retried. The subcommand then recreates the initial connections for the pool, and restores the pool to its steady pool size.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Reset a connection pool by using the `flush-connection-pool(1)` subcommand.**

Example 11–6 Resetting (Flushing) a Connection Pool

This example resets the JDBC connection pool named `__TimerPool` to its steady pool size.

```
asadmin> flush-connection-pool __TimerPool
Command flush-connection-pool executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help flush-connection-pool` at the command line.

▼ To Update a JDBC Connection Pool

You can change all of the settings for an existing pool except its name. Use the `get` and `set` subcommands to view and change the values of the JDBC connection pool properties.

- 1 **List the JDBC connection pools by using the `list-jdbc-connection-pools(1)` subcommand.**
- 2 **View the attributes of the JDBC connection pool by using the `get` subcommand.**
For example:

```
asadmin get resources.jdbc-connection-pool.DerbyPool.property
```
- 3 **Set the attribute of the JDBC connection pool by using the `set` subcommand.**
For example:

```
asadmin set resources.jdbc-connection-pool.DerbyPool.steady-pool-size=9
```
- 4 **(Optional) If needed, restart the server.**
Some parameters require server restart. See [“Configuration Changes That Require Restart” on page 40](#).

See Also For information about how to tune a connection pool, see the *GlassFish Server Open Source Edition 3.1 Performance Tuning Guide*.

▼ To Delete a JDBC Connection Pool

Use the `delete-jdbc-connection-pool` subcommand in remote mode to delete an existing JDBC connection pool. Deleting a JDBC connection pool is a dynamic event and does not require server restart.

Before You Begin Before deleting a JDBC connection pool, all associations to the resource must be removed.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the JDBC connection pools by using the `list-jdbc-connection-pools(1)` subcommand.**
- 3 **If necessary, notify users that the JDBC connection pool is being deleted.**
- 4 **Delete the connection pool by using the `delete-jdbc-connection-pool(1)` subcommand.**

Example 11–7 Deleting a JDBC Connection Pool

This example deletes the JDBC connection pool named `DerbyPool`.

```
asadmin> delete-jdbc-connection-pool jdbc/DerbyPool  
Command delete-jdbc-connection-pool executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-jdbc-connection-pool` at the command line.

Configuring Specific JDBC Connection Pool Features

In GlassFish Server, JDBC Connection Pools support a variety of features to simplify administration, monitoring and performance tuning. The following topics address several of these features:

- [“Transparent Pool Reconfiguration” on page 254](#)
- [“Using an Initialization Statement” on page 255](#)
- [“Setting a Statement Timeout” on page 255](#)
- [“Statement Leak Detection and Leaked Statement Reclamation” on page 256](#)
- [“Statement Caching” on page 257](#)
- [“Statement Tracing” on page 257](#)

Transparent Pool Reconfiguration

When the properties or attributes of a JDBC connection pool are changed, the connection pool is destroyed and re-created. Normally, applications using the connection pool must be redeployed as a consequence. This restriction can be avoided by enabling transparent JDBC

connection pool reconfiguration. When this feature is enabled, applications do not need to be redeployed. Instead, requests for new connections are blocked until the reconfiguration operation completes. Connection requests from any in-flight transactions are served using the old pool configuration so as to complete the transaction. Then, connections are created using the pool's new configuration, and any blocked connection requests are served with connections from the re-created pool.

To enable transparent JDBC connection pool reconfiguration, set the `dynamic-reconfiguration-wait-timeout-in-seconds` property of the JDBC connection pool to a positive, nonzero value in one of the following ways:

- Add it as a property in the Edit JDBC Connection Pool Properties page in the Administration Console. For more information, click the Help button in the Administration Console.
- Specify it using the `--property` option in the `create-jdbc-connection-pool` subcommand. For more information, see `create-jdbc-connection-pool(1)`.
- Set it using the `set` subcommand. For example:

```
asadmin set resources.jdbc-connection-pool.pool-name.property.dynamic-reconfiguration-wait-timeout-in-seconds=15
```

This property specifies the time in seconds to wait for in-use connections to close and in-flight transactions to complete. Any connections in use or transaction in flight past this time must be retried.

Using an Initialization Statement

You can specify a statement that executes each time a physical connection to the database is created (not reused) from a JDBC connection pool. This is useful for setting request or session specific properties and is suited for homogeneous requests in a single application. Set the `Init SQL` attribute of the JDBC connection pool to the SQL string to be executed in one of the following ways:

- Enter an `Init SQL` value in the Edit Connection Pool Advanced Attributes page in the Administration Console. For more information, click the Help button in the Administration Console.
- Specify the `--initsql` option in the `asadmin create-jdbc-connection-pool` command. For more information, see `create-jdbc-connection-pool(1)`.
- Specify the `init-sql` option in the `asadmin set` command. For example:

```
asadmin set domain1.resources.jdbc-connection-pool.DerbyPool.init-sql="sql-string"
```

Setting a Statement Timeout

An abnormally long running JDBC query executed by an application may leave it in a hanging state unless a timeout is explicitly set on the statement. Setting a statement timeout guarantees that all queries automatically time out if not completed within the specified period. When

statements are created, the `queryTimeout` is set according to the statement timeout setting. This works only when the underlying JDBC driver supports `queryTimeout` for `Statement`, `PreparedStatement`, `CallableStatement`, and `ResultSet`.

You can specify a statement timeout in the following ways:

- Enter a `Statement Timeout` value in the `Edit Connection Pool Advanced Attributes` page in the Administration Console. For more information, click the `Help` button in the Administration Console.
- Specify the `--statementtimeout` option in the `asadmin create-jdbc-connection-pool` command. For more information, see `create-jdbc-connection-pool(1)`.

Statement Leak Detection and Leaked Statement Reclamation

If statements are not closed by an application after use, it is possible for the application to run out of cursors. Enabling statement leak detection causes statements to be considered as leaked if they are not closed within a specified period. Additionally, leaked statements can be reclaimed automatically.

To enable statement leak detection, set `Statement Leak Timeout In Seconds` for the JDBC connection pool to a positive, nonzero value in one of the following ways:

- Specify the `--statementleaktimeout` option in the `create-jdbc-connection-pool` subcommand. For more information, see `create-jdbc-connection-pool(1)`.
- Specify the `statement-leak-timeout-in-seconds` option in the `set` subcommand. For example:

```
asadmin set resources.jdbc-connection-pool.pool-name.statement-leak-timeout-in-seconds=300
```

When selecting a value for `Statement Leak Timeout In Seconds`, make sure that:

- It is less than the `Connection Leak Timeout`; otherwise, the connection could be closed before the statement leak is recognized.
- It is greater than the `Statement Timeout`; otherwise, a long running query could be mistaken as a statement leak.

After enabling statement leak detection, enable leaked statement reclamation by setting `Reclaim Leaked Statements` for the JDBC connection pool to a `true` value in one of the following ways:

- Specify the `--statementleakreclaim=true` option in the `create-jdbc-connection-pool` subcommand. For more information, see `create-jdbc-connection-pool(1)`.
- Specify the `statement-leak-reclaim` option in the `set` subcommand. For example:

```
asadmin set resources.jdbc-connection-pool.pool-name.statement-leak-reclaim=true
```


Statement Caching

Statement caching stores statements, prepared statements, and callable statements that are executed repeatedly by applications in a cache, thereby improving performance. Instead of the statement being prepared each time, the cache is searched for a match. The overhead of parsing and creating new statements each time is eliminated.

Statement caching is usually a feature of the JDBC driver. The GlassFish Server provides caching for drivers that do not support caching. To enable this feature, set the Statement Cache Size for the JDBC connection pool in one of the following ways:

- Enter a Statement Cache Size value in the Edit Connection Pool Advanced Attributes page in the Administration Console. For more information, click the Help button in the Administration Console.
- Specify the `--statementcachesize` option in the `asadmin create-jdbc-connection-pool` command. For more information, see `create-jdbc-connection-pool(1)`.
- Specify the `statement-cache-size` option in the `asadmin set` command. For example:

```
asadmin set domain1.resources.jdbc-connection-pool.DerbyPool.statement-cache-size=10
```

By default, this attribute is set to zero and the statement caching is turned off. To enable statement caching, you can set any positive nonzero value. The built-in cache eviction strategy is LRU-based (Least Recently Used). When a connection pool is flushed, the connections in the statement cache are recreated.

Statement Tracing

You can trace the SQL statements executed by applications that use a JDBC connection pool. Set the SQL Trace Listeners attribute to a comma-separated list of trace listener implementation classes in one of the following ways:

- Enter an SQL Trace Listeners value in the Edit Connection Pool Advanced Attributes page in the Administration Console. For more information, click the Help button in the Administration Console.
- Specify the `--sqltracelisteners` option in the `asadmin create-jdbc-connection-pool` command. For more information, see `create-jdbc-connection-pool(1)`.
- Specify the `sql-trace-listeners` option in the `asadmin set` command. For example:

```
asadmin set domain1.resources.jdbc-connection-pool.DerbyPool.sql-trace-listeners=listeners
```

The GlassFish Server provides a public interface, `org.glassfish.api.jdbc.SQLTraceListener`, that implements a means of recording `SQLTraceRecord` objects. To make custom implementations of this interface available to the GlassFish Server, place the implementation classes in `as-install/lib`.

The GlassFish Server provides an SQL tracing logger to log the SQL operations in the form of `SQLTraceRecord` objects in the server . log file. The module name under which the SQL

operation is logged is `javax.enterprise.resource.sqltrace`. SQL traces are logged as FINE messages along with the module name to enable easy filtering of the SQL logs. A sample SQL trace record looks like this:

```
[#|2009-11-27T15:46:52.202+0530|FINE|glassfishv3.0|javax.enterprise.resource.sqltrace.com.sun.gjc.util
|_ThreadID=29;_ThreadName=Thread-1;ClassName=com.sun.gjc.util.SQLTraceLogger;MethodName=sqlTrace;
|ThreadID=77|ThreadName=p: thread-pool-1; w: 6|TimeStamp=1259317012202
|ClassName=com.sun.gjc.spi.jdbc40.PreparedStatementWrapper40|MethodName=executeUpdate
|arg[0]=insert into table1(colName) values(100)|arg[1]=columnNames||#]
```

This trace shows that an `executeUpdate(String sql, String columnNames)` operation is being done.

When SQL statement tracing is enabled and JDBC connection pool monitoring is enabled, GlassFish Server maintains a tracing cache of recent queries and their frequency of use. The following JDBC connection pool properties can be configured to control this cache and the monitoring statistics available from it:

`time-to-keep-queries-in-minutes`

Specifies how long in minutes to keep a query in the tracing cache, tracking its frequency of use. The default value is 5 minutes.

`number-of-top-queries-to-report`

Specifies how many of the most used queries, in frequency order, are listed the monitoring report. The default value is 10 queries.

Set these parameters in one of the following ways:

- Add them as properties in the Edit JDBC Connection Pool Properties page in the Administration Console. For more information, click the Help button in the Administration Console.
- Specify them using the `-property` option in the `create-jdbc-connection-pool` subcommand. For more information, see `create-jdbc-connection-pool(1)`.
- Set them using the `set` subcommand. For example:

```
asadmin set resources.jdbc-connection-pool.pool-name.property.time-to-keep-queries-in-minutes=10
```

Administering JDBC Resources

A *JDBC resource*, also known as a data source, provides an application with a means of connecting to a database. Typically, you create a JDBC resource for each database that is accessed by the applications deployed in a domain. Multiple JDBC resources can be specified for a database. JDBC resources can be globally accessible or be scoped to an enterprise application, web module, EJB module, connector module or application client module, as described in “Application-Scoped Resources” in *GlassFish Server Open Source Edition 3.1 Application Deployment Guide*.

A JDBC resource is created by specifying the connection pool with which the resource will be associated. Use a unique Java Naming and Directory Interface (JNDI) name to identify the resource. For example, the JNDI name for the resource of a payroll database might be `java:comp/env/jdbc/payrolldb`.

The following tasks and information are used to administer JDBC resources:

- [“To Create a JDBC Resource” on page 259](#)
- [“To List JDBC Resources” on page 260](#)
- [“To Update a JDBC Resource” on page 260](#)
- [“To Delete a JDBC Resource” on page 260](#)

▼ To Create a JDBC Resource

Use the `create-jdbc-resource` subcommand in remote mode to create a JDBC resource. Creating a JDBC resource is a dynamic event and does not require server restart.

Because all JNDI names are in the `java:comp/env` subcontext, when specifying the JNDI name of a JDBC resource in the Administration Console, use only the `jdbc/name` format. For example, a payroll database might be specified as `jdbc/payrolldb`.

Before You Begin Before creating a JDBC resource, you must first create a JDBC connection pool. For instructions, see [“To Create a JDBC Connection Pool” on page 250](#).

- 1 Ensure that the server is running.**
Remote subcommands require a running server.
- 2 Create a JDBC resource by using the `create-jdbc-resource(1)` subcommand.**
Information about properties for the subcommand is included in this help page.
- 3 If necessary, notify users that the new resource has been created.**

Example 11–8 Creating a JDBC Resource

This example creates a JDBC resource named `DerbyPool`.

```
asadmin> create-jdbc-resource --connectionpoolid DerbyPool jdbc/DerbyPool
Command create-jdbc-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-jdbc-resource` at the command line.

▼ To List JDBC Resources

Use the `list-jdbc-resources` subcommand in remote mode to list the existing JDBC resources.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List JDBC resources by using the `list-jdbc-resources(1)` subcommand.**

Example 11–9 Listing JDBC Resources

This example lists JDBC resources for `localhost`.

```
asadmin> list-jdbc-resources
jdbc/__TimerPool
jdbc/DerbyPool
jdbc/__default
jdbc1
Command list-jdbc-resources executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-jdbc-resources` at the command line.

▼ To Update a JDBC Resource

You can enable or disable a JDBC resource by using the `set` subcommand. The JDBC resource is identified by its dotted name.

- 1 **List JDBC resources by using the `list-jdbc-resources(1)` subcommand.**
- 2 **Modify the values for the specified JDBC resource by using the `set(1)` subcommand.**
For example:

Example 11–10 Updating a JDBC Resource

This example changes the `res1.enabled` setting to `false`.

```
asadmin>set resources.jdbc-resource.res1.enabled=false
```

▼ To Delete a JDBC Resource

Use the `delete-jdbc-resource` subcommand in remote mode to delete an existing JDBC resource. Deleting a JDBC resource is a dynamic event and does not require server restart.

Before You Begin Before deleting a JDBC resource, all associations with this resource must be removed.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List JDBC resources by using the `list-jdbc-resources(1)` subcommand.**
- 3 **If necessary, notify users that the JDBC resource is being deleted.**
- 4 **Delete a JDBC resource by using the `delete-jdbc-resource(1)` subcommand.**

Example 11–11 Deleting a JDBC Resource

This example deletes a JDBC resource named `DerbyPool`.

```
asadmin> delete-jdbc-resource jdbc/DerbyPool
Command delete-jdbc-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-jdbc-resource` at the command line.

Enabling the `jdbc/__default` Resource in a Clustered Environment

GlassFish Server 3.1 includes a preconfigured JDBC resource with the JNDI name `jdbc/__default`. This `jdbc/__default` resource is not enabled by default, so you need to explicitly enable it if you want to use it in a cluster.

▼ To Enable the `jdbc/__default` Resource for a Clustered Environment

Instructions for creating JDBC resources in general are provided in [“To Create a JDBC Resource” on page 259](#). Use the following procedure to enable the preconfigured `jdbc/__default` resource for a clustered GlassFish Server environment.

- 1 **Create the `jdbc/__default` resource reference for the cluster.**
`asadmin create-resource-ref --target cluster-name jdbc/__default`
- 2 **(Optional) Enable the resource on the DAS that manages the cluster.**

```
asadmin set resources.jdbc-connection-pool.DerbyPool.property.serverName=DAS-machine-name
```

This step is only required if the cluster includes remote instances.

- 3 **Restart the DAS and the target cluster(s).**

```
asadmin stop-cluster cluster-name
asadmin stop-domain domain-name
asadmin start-domain domain-name
asadmin start-cluster cluster-name
```

Integrating the JDBC Driver

To use JDBC features, you must choose a JDBC driver to work with the GlassFish Server, then you must set up the driver. This section covers these topics:

- [“Supported Database Drivers” on page 262](#)
- [“Making the JDBC Driver JAR Files Accessible” on page 262](#)
- [“Automatic Detection of Installed Drivers” on page 262](#)

Supported Database Drivers

Supported JDBC drivers are those that have been fully tested by Oracle. For a list of the JDBC drivers currently supported by the GlassFish Server, see the *GlassFish Server Open Source Edition 3.1-3.1.1 Release Notes*. For configurations of supported and other drivers, see “Configuration Specifics for JDBC Drivers” on page 263.

Note – Because the drivers and databases supported by the GlassFish Server are constantly being updated, and because database vendors continue to upgrade their products, always check with Oracle technical support for the latest database support information.

Making the JDBC Driver JAR Files Accessible

To integrate the JDBC driver into a GlassFish Server domain, copy the JAR files into the *domain-dir/lib* directory, then restart the server. This makes classes accessible to all applications or modules deployed on servers that share the same configuration. For more information about GlassFish Server class loaders, see Chapter 2, “Class Loaders,” in *GlassFish Server Open Source Edition 3.1 Application Development Guide*.

If you are using an Oracle database with EclipseLink extensions, copy the JAR files into the *domain-dir/lib/ext* directory, then restart the server. For details, see “Oracle Database Enhancements” in *GlassFish Server Open Source Edition 3.1 Application Development Guide*.

Automatic Detection of Installed Drivers

The Administration Console detects installed JDBC Drivers automatically when you create a JDBC connection pool. To create a JDBC connection pool using the Administration Console, open the Resources component, open the JDBC component, select Connection Pools, and click on the New button. This displays the New JDBC Connection Pool page.

Based on the Resource Type and Database Vendor you select on the New JDBC Connection Pool page, data source or driver implementation class names are listed in the Datasource Classname or Driver Classname field when you click on the Next button. When you choose a specific implementation class name on the next page, additional properties relevant to the installed JDBC driver are displayed in the Additional Properties section.

Configuration Specifics for JDBC Drivers

GlassFish Server is designed to support connectivity to any database management system by using a corresponding JDBC driver. Configuration information is provided for these JDBC drivers:

- “IBM DB2 Database Type 2 Driver” on page 263
- “IBM DB2 Database Type 4 Driver” on page 264
- “Java DB/Derby Type 4 Driver” on page 264
- “MySQL Server Database Type 4 Driver” on page 265
- “Oracle 10 Database Driver” on page 265
- “Oracle 11 Database Driver” on page 266
- “PostgreSQL Type 4 Driver” on page 267
- “DataDirect Type 4 Driver for IBM DB2 Database” on page 267
- “DataDirect Type 4 Driver for IBM Informix” on page 268
- “DataDirect Type 4 Driver for Microsoft SQL Server Database” on page 268
- “DataDirect Type 4 Driver for MySQL Server Database” on page 269
- “DataDirect Type 4 Driver for Oracle 11 Database” on page 270
- “DataDirect Type 4 Driver for Sybase Database” on page 270
- “Inet Oraxo Driver for Oracle Database” on page 270
- “Inet Merlia Driver for Microsoft SQL Server Database” on page 271
- “Inet Sybelux Driver for Sybase Database” on page 271
- “JConnect Type 4 Driver for Sybase ASE 12.5 Database” on page 272

IBM DB2 Database Type 2 Driver

The JAR files for the DB2 driver are `db2jcc.jar`, `db2jcc_license_cu.jar`, and `db2java.zip`. Set your environment variables. For example:

```
LD_LIBRARY_PATH=/usr/db2user/sqlllib/lib:${Java EE.home}/lib
DB2DIR=/opt/IBM/db2/V8.2
DB2INSTANCE=db2user
INSTHOME=/usr/db2user
VWSPATH=/usr/db2user/sqlllib
THREADS_FLAG=native
```

Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** DB2
- **DataSource Classname:** `com.ibm.db2.jcc.DB2SimpleDataSource`
- **Properties:**
 - **databaseName** - Set as appropriate.

- **user** – Set as appropriate.
- **password** – Set as appropriate.
- **driverType** – Set to 2.
- **deferPrepares** – Set to false.

IBM DB2 Database Type 4 Driver

The JAR file for the DB2 driver is `db2jcc.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** DB2
- **DataSource Classname:** `com.ibm.db2.jcc.DB2SimpleDataSource`
- **Properties:**
 - **databaseName** - Set as appropriate.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.
 - **driverType** – Set to 4.

Java DB/Derby Type 4 Driver

The Java DB/Derby JDBC driver is included with GlassFish Server by default, so you do not need to integrate this JDBC driver with GlassFish Server.

The JAR file for the Java DB driver is `derbyclient.jar`. (Java DB is based upon Apache Derby.) Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** JavaDB
- **DataSource Classname:** Specify one of the following:
`org.apache.derby.jdbc.ClientDataSource40`
`org.apache.derby.jdbc.ClientXADataSource40`
- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.
 - **portNumber** – Specify the port number of the database server if it is different from the default.
 - **databaseName** – Specify the name of the database.
 - **user** - Specify the database user.

This is only necessary if Java DB is configured to use authentication. Java DB does *not* use authentication by default. When the user is provided, it is the name of the schema where the tables reside.

- **password** – Specify the database password.

This is only necessary if Java DB is configured to use authentication.

MySQL Server Database Type 4 Driver

The JAR file for the MySQL driver is `mysql-connector-java-5.1.14-bin.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** MySql
- **DataSource Classname:**

```
com.mysql.jdbc.jdbc2.optional.MysqlDataSource
com.mysql.jdbc.jdbc2.optional.MysqlXADataSource
```

- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **databaseName** – Set as appropriate.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.

Oracle 10 Database Driver

The JAR file for the Oracle 10 database driver is `ojdbc14.jar`. Make sure that the shared library is available through `LD_LIBRARY_PATH` and that the `ORACLE_HOME` property is set.

To make the Oracle driver behave in a Java EE-compliant manner, you must define the following JVM property:

```
-Doracle.jdbc.J2EE13Compliant=true
```

Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** Oracle
- **DataSource Classname:** Specify one of the following:

```
oracle.jdbc.pool.OracleDataSource  
oracle.jdbc.xa.client.OracleXADataSource
```

- **Properties:**
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.

Oracle 11 Database Driver

The JAR file for the Oracle 11 database driver is `ojdbc6.jar`.

To make the Oracle driver behave in a Java EE-compliant manner, you must define the following JVM property:

```
-Doracle.jdbc.J2EE13Compliant=true
```

Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** Oracle
- **DataSource Classname:** Specify one of the following:

```
oracle.jdbc.pool.OracleDataSource  
oracle.jdbc.xa.client.OracleXADataSource
```

- **Properties:**
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.

Note – For this driver, the `XAResource.recover` method repeatedly returns the same set of in-doubt Xids regardless of the input flag. According to the XA specifications, the Transaction Manager initially calls this method with `TMSTARTSCAN` and then with `TMNOFLAGS` repeatedly until no Xids are returned. The `XAResource.commit` method also has some issues.

To disable this GlassFish Server workaround, the `oracle-xa-recovery-workaround` property value must be set to `false`.

Additionally, in order for the transaction manager to recover transactions, the JDBC connection pool's database user must be given certain Oracle permissions:

- `SELECT` permission on `DBA_PENDING_TRANSACTIONS`, `PENDING_TRANS$`, `DBA_2PC_PENDING` and `DBA_2PC_NEIGHBORS`.
 - `EXECUTE` permissions on `DBMS_XA` and `DBMS_SYSTEM`.
-

PostgreSQL Type 4 Driver

The JAR file for the PostgreSQL driver is `postgresql-9.0-801.jdbc4.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** `Postgresql`
- **DataSource Classname:** `org.postgresql.ds.PGSimpleDataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **databaseName** – Set as appropriate.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.

DataDirect Type 4 Driver for IBM DB2 Database

The JAR file for DataDirect driver is `db2.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** `DataDirect-DB2`

- **DataSource Classname:** `com.ddtek.jdbcx.db2.DB2DataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **databaseName** – Set as appropriate.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.

DataDirect Type 4 Driver for IBM Informix

Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** DataDirect-Informix
- **DataSource Classname:** Specify one of the following:

```
com.informix.jdbcx.IfxDDataSource
com.informix.jdbcx.IfxxADDataSource
```

DataDirect DataSource Classname: `com.ddtek.jdbcx.informix.InformixDataSource`

- **Properties:**
 - **serverName** – Specify the Informix database server name.
 - **portNumber** – Specify the port number of the database server.
 - **databaseName** – Set as appropriate. This is optional.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.
 - **IfxIFXHost** – Specify the host name or IP address of the database server.

DataDirect Type 4 Driver for Microsoft SQL Server Database

The JAR file for the DataDirect driver is `sqlserver.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** DataDirect-Microsoft SQL Server
- **DataSource Classname:** `com.ddtek.jdbcx.sqlserver.SQLServerDataSource`
- **Properties:**

- **serverName** – Specify the host name or IP address and the port of the database server.
- **portNumber** – Specify the port number of the database server.
- **user** – Set as appropriate.
- **password** – Set as appropriate.
- **selectMethod** – Set to cursor.

DataDirect Type 4 Driver for MySQL Server Database

The JAR file for the DataDirect driver is `mysql.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** DataDirect-MySQL
- **DataSource:** `com.ddtek.jdbcx.mysql.MySQLDataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address and the port of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.
 - **selectMethod** – Set to cursor.

DataDirect Type 4 Driver for Oracle 11 Database

The JAR file for the DataDirect driver is `oracle.jar`.

To make the Oracle driver behave in a Java EE-compliant manner, you must define the following JVM property:

```
-Doracle.jdbc.J2EE13Compliant=true
```

Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** DataDirect-Oracle
- **DataSource Classname:** `com.ddtek.jdbcx.oracle.OracleDataSource`
- **Properties:**

- **serverName** – Specify the host name or IP address of the database server.
- **portNumber** – Specify the port number of the database server.
- **user** – Set as appropriate.
- **password** – Set as appropriate.

DataDirect Type 4 Driver for Sybase Database

The JAR file for the DataDirect driver is `sybase.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** DataDirect-Sybase
- **DataSource Classname:** `com.ddtek.jdbcx.sybase.SybaseDataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **databaseName** – Set as appropriate. This is optional.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.

Note – In some situations, using this driver can cause exceptions to be thrown because the driver creates a stored procedure for every parameterized PreparedStatement by default. If this situation arises, add the property **PrepareMethod**, setting its value to **direct**.

Inet Oraxo Driver for Oracle Database

The JAR file for the Inet Oracle driver is `Oranxo.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** Oracle
- **DataSource Classname:** `com.inet.ora.OraDataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **user** – Specify the database user.

- **password** – Specify the database password.
- **serviceName** – Specify the URL of the database. The syntax is as follows:

`jdbc:inetora:server:port:dbname`

For example:

`jdbc:inetora:localhost:1521:payrolldb`

In this example, `localhost` is the name of the host running the Oracle server, `1521` is the Oracle server's port number, and `payrolldb` is the SID of the database. For more information about the syntax of the database URL, see the Oracle documentation.

- **streamstolob** - If the size of BLOB or CLOB data types exceeds 4 KB and this driver is used for CMP, this property must be set to `true`.

Inet Merlia Driver for Microsoft SQL Server Database

The JAR file for the Inet Microsoft SQL Server driver is `Merlia.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** `MicrosoftSqlServer`
- **DataSource Classname:** `com.inet.tds.TdsDataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address and the port of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.

Inet Sybelux Driver for Sybase Database

The JAR file for the Inet Sybase driver is `Sybelux.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** `Sybase`
- **DataSource Classname:** `com.inet.syb.SybDataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.

- **portNumber** – Specify the port number of the database server.
- **databaseName** – Set as appropriate. Do not specify the complete URL, only the database name.
- **user** – Set as appropriate.
- **password** – Set as appropriate.

JConnect Type 4 Driver for Sybase ASE 12.5 Database

The JAR file for the Sybase driver is `jconn4.jar`. Configure the connection pool using the following settings:

- **Name:** Use this name when you configure the JDBC resource later.
- **Resource Type:** Specify the appropriate value.
- **Database Vendor:** Sybase
- **DataSource Classname:** Specify one of the following:
`com.sybase.jdbc4.jdbc.SybDataSource`
`com.sybase.jdbc4.jdbc.SybXADataSource`
- **Properties:**
 - **serverName** – Specify the host name or IP address of the database server.
 - **portNumber** – Specify the port number of the database server.
 - **databaseName** – Set as appropriate. Do not specify the complete URL, only the database name.
 - **user** – Set as appropriate.
 - **password** – Set as appropriate.
 - **BE_AS_JDBC_COMPLIANT_AS_POSSIBLE** – Set to `true`.
 - **FAKE_METADATA** – Set to `true`.

Administering EIS Connectivity

This chapter provides information and procedures for administering connections to enterprise information system (EconIS) data in the Oracle GlassFish Server 3.1 environment by using the `asadmin` command-line utility.

Note – If you installed the Web Profile, connector modules that use only outbound communication features and work-management that does not involve inbound communication features are supported. Other connector features are supported only in the Full Platform Profile.

The following topics are addressed here:

- [“About EIS Connectivity” on page 274](#)
- [“Administering Connector Connection Pools” on page 275](#)
- [“Administering Connector Resources” on page 278](#)
- [“Administering the Resource Adapter Configuration” on page 281](#)
- [“Administering Connector Security Maps” on page 283](#)
- [“Administering Connector Work Security Maps” on page 286](#)
- [“Administering Administered Objects” on page 289](#)

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

For information about database connectivity, see [Chapter 11, “Administering Database Connectivity.”](#)

About EIS Connectivity

Enterprise information system (EIS) refers to any system that holds the data of an organization. It can be a mainframe, a messaging system, a database system, or an application. Connection resources are used by applications and modules to access EIS software.)

The key elements of EIS connectivity are the following:

- **Connector Module.** A connector module, also called a *resource adapter*, is a Java EE component that enables applications to interact with EIS software. A connector module is used by GlassFish Server to implement Java Message Service (JMS). Like other Java EE modules, a connector module is installed when it is deployed. For instructions on creating a connector module, see Chapter 11, “Developing Connectors,” in *GlassFish Server Open Source Edition 3.1 Application Development Guide*
- **Connector Connection Pool.** A connector connection pool is a group of reusable connections for a particular EIS. A connector connection pool is created when you specify the connector module that is associated with the pool. For administration procedures, see [“Administering Connector Connection Pools” on page 275](#).
- **Connector Resource.** A connector resource is a program object that provides an application with a connection to an EIS. A connector resource is created when you specify its JNDI name and its associated connection pool. The JNDI name of a connector resource for an EIS is usually in the `java:comp/env/eis-specific` subcontext. For administration procedures, see [“Administering Connector Resources” on page 278](#).
- **Connector Module Configuration.** A connector module configuration is the information that resides in the domain configuration file (`domain.xml`) for the particular connector module (resource adapter). For administration procedures, see [“Administering the Resource Adapter Configuration” on page 281](#).
- **Connector Security Map.** A connector security map associates the caller identity of the application (principal or user group) to a suitable EIS principal or group. For administration procedures, see [“Administering Connector Security Maps” on page 283](#).
- **Connector Work Security Map.** A connector work security map associates the caller identity of the work submitted by the connector module (resource adapter) EIS principal or EIS user group to a suitable principal or user group in the GlassFish Server security domain. For administration procedures, see [“Administering Connector Work Security Maps” on page 286](#).
- **Administered Object.** An administered object provides specialized functionality for an application, such as providing access to a parser that is specific to the connector module and its associated EIS. For administration procedures, see [“Administering Administered Objects” on page 289](#).

At runtime, the following sequence occurs when an application connects to an EIS:

1. The application gets the connector resource (data source) associated with the EIS by making a call through the JNDI API.

Using the JNDI name of the connector resource, the naming and directory service locates the resource. Each EIS resource specifies a connector connection pool.

2. Using the connector resource, the application gets an EIS connection.

GlassFish Server retrieves a physical connection from the connection pool that corresponds to the EIS resource. The pool defines connection attributes such as the EIS name, user name, and password.

3. After the EIS connection is established, the application can read, modify, and add data to the EIS.

The application accesses the EIS information by making calls to the JMS API.

4. When the application is finished accessing the EIS, the application closes the connection and returns the connection to the connection pool.

Administering Connector Connection Pools

After a connector module has been deployed, you are ready to create a connector connection pool for it.

The following topics are addressed here:

- [“To Create a Connector Connection Pool” on page 275](#)
- [“To List Connector Connection Pools” on page 276](#)
- [“To Connect to \(Ping\) or Reset \(Flush\) a Connector Connection Pool” on page 277](#)
- [“To Update a Connector Connection Pool” on page 277](#)
- [“To Delete a Connector Connection Pool” on page 278](#)

▼ To Create a Connector Connection Pool

Use the `create-connector-connection-pool` subcommand in remote mode to create a connector connection pool for a deployed connector module. When you are building the connector connection pool, certain data specific to the EIS will be required. The value in the mandatory `--connectiondefinition` option provides the EIS info.

Multiple connector resources can specify a single connection pool.

Creating a connector connection pool is a dynamic event and does not require server restart. However, there are some parameters that do require server restart. See [“Configuration Changes That Require Restart” on page 40](#).

Before You Begin Before creating the connector connection pool, the connector must be installed.

- 1 **Ensure that the server is running.**

Remote subcommands require a running server.

- 2 **Create the connector connection pool by using the `create-connector-connection-pool(1)` subcommand.**
Information about properties for the subcommand is included in this help page.
- 3 **(Optional) If needed, restart the server.**
Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).
- 4 **(Optional) You can verify that a connection pool is usable by using the `ping-connection-pool` subcommand.**
For instructions, see [“To Contact \(Ping\) a Connection Pool” on page 252](#).

Example 12-1 Creating a Connector Connection Pool

This example creates the new `.jms/qConnPool` pool for the `javax.jms.QueueConnectionFactory` connector module.

```
asadmin> create-connector-connection-pool --steadypoolsize 20 --maxpoolsize 100
--poolresize 2 --maxwait 60000 --raname jmsra --connectiondefinition
javax.jms.QueueConnectionFactory jms/qConnPool
Command create-connector-connection-pool executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-connector-connection-pool` at the command line.

▼ To List Connector Connection Pools

Use the `list-connector-connection-pools` subcommand in remote mode to list the pools that have been created.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the connector connection pools by using the `list-connector-connection-pools(1)` subcommand.**

Example 12-2 Listing Connector Connection Pools

This example lists the existing connector connection pools.

```
asadmin> list-connector-connection-pools
jms/qConnPool
Command list-connector-connection-pools executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-connector-connection-pools` at the command line.

▼ To Connect to (Ping) or Reset (Flush) a Connector Connection Pool

Use the `ping-connection-pool` or `flush-connection-pool` subcommands in remote mode to perform these tasks on a connection pools. See [“To Contact \(Ping\) a Connection Pool” on page 252](#) or [“To Reset \(Flush\) a Connection Pool” on page 252](#) for instructions.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Connect to or reset a connector connection pool by using the `flush-connection-pool(1)` subcommand or the `ping-connection-pool(1)` subcommand.**

▼ To Update a Connector Connection Pool

Use the `get` and `set` subcommands to view and change the values of the connector connection pool properties.

- 1 **List the connector connection pools by using the `list-connector-connection-pools(1)` subcommand.**
- 2 **View the properties of the connector connection pool by using the `get(1)` subcommand.**

For example:

```
asadmin> get domain.resources.connector-connection-pool.connectionpoolname.*
```

- 3 **Set the property of the connector connection pool by using the `set(1)` subcommand.**

For example:

```
asadmin> set domain.resources.connector-connection-pool
.connectionpoolname.validate-atmost-once-period-in-seconds=3
```

- 4 **(Optional) If needed, restart the server.**

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

▼ To Delete a Connector Connection Pool

Use the `delete-connector-connection-pool` subcommand in remote mode to remove a connector connection pool.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the connector connection pools by using the `list-connector-connection-pools(1)` subcommand.**
- 3 **If necessary, notify users that the connector connection pool is being deleted.**
- 4 **Delete the connector connection pool by using the `delete-connector-connection-pool(1)` subcommand.**

Example 12-3 Deleting a Connector Connection Pool

This example deletes the connection pool named `jms/qConnPool`.

```
asadmin> delete-connector-connection-pool --cascade=false jms/qConnPool  
Command delete-connector-connection-pool executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-connector-connection-pool` at the command line.

Administering Connector Resources

A connector resource provides an application or module with the means of connecting to an EIS. Typically, you create a connector resource for each EIS that is accessed by the applications deployed in the domain.

The following topics are addressed here:

- [“To Create a Connector Resource” on page 278](#)
- [“To List Connector Resources” on page 279](#)
- [“To Update a Connector Resource” on page 280](#)
- [“To Delete a Connector Resource” on page 280](#)

▼ To Create a Connector Resource

Use the `create-connector-resource` subcommand in remote mode to register a new connector resource with its JNDI name.

Creating a connector resource is a dynamic event and does not require server restart. However, there are some parameters that do require server restart. See [“Configuration Changes That Require Restart” on page 40](#).

Before You Begin Before creating a connector resource, you must first create a connector connection pool. For instructions, see [“To Create a Connector Connection Pool” on page 275](#).

- 1 Ensure that the server is running.**

Remote subcommands require a running server.

- 2 Create the connector resource by using the `create-connector-resource(1)` subcommand.**

Information about properties for the subcommand is included in this help page.

- 3 (Optional) If needed, restart the server.**

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 12–4 Creating a Connector Resource

This example creates a new resource named `jms/qConnFactory` for the `jms/qConnPool` connection pool.

```
asadmin> create-connector-resource --poolname.jms/qConnPool
--description "creating sample connector resource" jms/qConnFactory
Command create-connector-resource executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-connector-resource` at the command line.

▼ **To List Connector Resources**

Use the `list-connector-resources` subcommand in remote mode to list the connector resources that have been created.

- 1 Ensure that the server is running.**

Remote subcommands require a running server.

- 2 List the connector connection pools by using the `list-connector-resources(1)` subcommand.**

Example 12–5 Listing Connector Resources

This example lists the existing connector resources.

```
asadmin> list-connector-resources
jms/qConnFactory
Command list-connector-resources executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-connector-resources` at the command line.

▼ To Update a Connector Resource

Use the `get` and `set` subcommands to view and change the values of the connector resource properties.

- 1 List the connector connection pools by using the `list-connector-resources(1)` subcommand.

- 2 View the properties of the connector resource by using the `get(1)` subcommand.

For example

```
asadmin> get domain.resources.connector-resource.jms/qConnFactory
```

- 3 Set the property of the connector resource by using the `set(1)` subcommand.

For example:

```
asadmin> set domain.resources.connector-resource.jms/qConnFactory.enabled=true
```

- 4 (Optional) If needed, restart the server.

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

▼ To Delete a Connector Resource

Use the `delete-connector-resource` subcommand in remote mode to remove a connector resource by specifying the JNDI name.

Before You Begin Before deleting a resource, all associations with the resource must be removed.

- 1 Ensure that the server is running.
Remote subcommands require a running server.
- 2 List the connector connection pools by using the `list-connector-resources(1)` subcommand.
- 3 If necessary, notify users that the connector resource is being deleted.
- 4 Delete the connector resource by using the `delete-connector-resource(1)` subcommand.

Example 12–6 Deleting a Connector Resource

This example deletes the `.jms/qConnFactory` connector resource.

```
asadmin> delete-connector-resource jms/qConnFactory
Command delete-connector-resources executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-connector-resource` at the command line.

Administering the Resource Adapter Configuration

The following topics are addressed here:

- [“To Create Configuration Information for a Resource Adapter” on page 281](#)
- [“To List Resource Adapter Configurations” on page 282](#)
- [“To Update a Resource Adapter Configuration” on page 282](#)
- [“To Delete a Resource Adapter Configuration” on page 283](#)

▼ To Create Configuration Information for a Resource Adapter

Use the `create-resource-adapter-config` subcommand in remote mode to create configuration information for a resource adapter, also known as a connector module. You can run the subcommand before deploying a resource adapter, so that the configuration information is available at the time of deployment. The resource adapter configuration can also be created after the resource adapter is deployed. In this situation, the resource adapter is restarted with the new configuration.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Create configuration information by using the `create-resource-adapter-config(1)` subcommand.

Information about properties for the subcommand is included in this help page.

Example 12–7 Creating a Resource Adapter Configuration

This example creates the configuration for resource adapter `ra1`.

```
asadmin> create-resource-adapter-config --property foo=bar
--threadpoolid mycustomerthreadpool ra1
Command create-resource-adapter-config executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-resource-adapter-config` at the command line.

▼ To List Resource Adapter Configurations

Use the `list-resource-adapter-configs` subcommand in remote mode to list the configuration information contained in the domain configuration file (`domain.xml`) for the specified resource adapter (connector module).

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the configurations for a resource adapter by using the `list-resource-adapter-configs(1)` subcommand.**

Example 12–8 Listing Configurations for a Resource Adapter

This example lists all the resource adapter configurations.

```
asadmin> list-resource-adapter-configs
ra1
ra2
Command list-resource-adapter-configs executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-resource-adapter-configs` at the command line.

▼ To Update a Resource Adapter Configuration

Use the `get` and `set` subcommands to view and change the values of the resource adapter configuration properties.

- 1 **List the configurations for a resource adapter by using the `list-resource-adapter-configs(1)` subcommand.**
- 2 **View the properties of the connector resource by using the `get(1)` subcommand.**

For example:

```
asadmin> get domain.resources.resource-adapter-config.ra1.*
```

- 3 **Set the property of the connector resource by using the `set(1)` subcommand.**

For example:

```
asadmin> set domain.resources.resource-adapter-config.ra1.raSpecificProperty=value
```

▼ To Delete a Resource Adapter Configuration

Use the `delete-resource-adapter-config` subcommand in remote mode to delete the configuration information contained in the domain configuration file (`domain.xml`) for a specified resource adapter (connector module).

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the configurations for a resource adapter by using the `list-resource-adapter-configs(1)` subcommand.**
- 3 **Delete the configuration for a resource adapter by using the `delete-resource-adapter-config(1)` subcommand.**

Example 12–9 Deleting a Resource Adapter Configuration

This example deletes the configuration for resource adapter `ra1`.

```
asadmin> delete-resource-adapter-config ra1
Command delete-resource-adapter-config executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-resource-adapter-config` at the command line.

Administering Connector Security Maps

The EIS is any system that holds the data of an organization. It can be a mainframe, a messaging system, a database system, or an application. The connector security map is used to map the application's credentials to the EIS credentials.

A security map applies to a particular connector connection pool. One or more named security maps can be associated with a connector connection pool.

The following topics are addressed here:

- [“To Create a Connector Security Map” on page 284](#)
- [“To List Connector Security Maps” on page 284](#)
- [“To Update a Connector Security Map” on page 285](#)
- [“To Delete a Connector Security Map” on page 286](#)

▼ To Create a Connector Security Map

Use the `create-connector-security-map` subcommand in remote mode to create a security map for the specified connector connection pool. If the security map is not present, a new one is created. You can specify back-end EIS principals or back-end EIS user groups. The connector security map configuration supports the use of the wild card asterisk (*) to indicate all users or all user groups.

You can also use this subcommand to map the caller identity of the application (principal or user group) to a suitable EIS principal in container-managed authentication scenarios.

Before You Begin For this subcommand to succeed, you must have first created a connector connection pool. For instructions, see [“To Create a Connector Connection Pool” on page 275](#).

- 1 Ensure that the server is running.**

Remote subcommands require a running server.

- 2 Create a connector security map by using the `create-connector-security-map(1)` subcommand.**

Information about the options for the subcommand is included in this help page.

- 3 (Optional) If needed, restart the server.**

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 12–10 Creating a Connector Security Map

This example creates a connector security map `securityMap1` for `connection-pool1`.

```
asadmin> create-connector-security-map --poolname connector-pool1
--principals principal1, principal2 --mappedusername backend-username securityMap1
Command create-connector-security-map executed successfully
```

▼ To List Connector Security Maps

Use the `list-connector-security-maps` subcommand in remote mode to list the existing security maps belonging to the specified connector connection pool. You can get a simple listing of the connector security maps for a connector connection pool, or you can get a more comprehensive listing that shows the principals of the map.

- 1 Ensure that the server is running.**

Remote subcommands require a running server.

- 2 List existing connector connection pools by using the `list-connector-connection-pools(1)` subcommand.
- 3 List the security maps for a specific connector connection pool by using the `list-connector-security-maps(1)` subcommand.

Example 12–11 Listing All Connector Security Maps for a Connector Connection Pool

This example lists the connector security maps associated with `connector-Pool1`.

```
asadmin> list-connector-security-maps connector-Pool1
securityMap1
Command list-connector-security-maps executed successfully.
```

Example 12–12 Listing Principals for a Specific Security Map for a Connector Connection Pool

This example lists the principals associated with `securityMap1`.

```
asadmin> list-connector-security-maps --securitymap securityMap1 connector-Pool1
principal1
principal1
Command list-connector-security-maps executed successfully.
```

Example 12–13 Listing Principals of All Connector Security Maps for a Connector Connection Pool

This example lists the connector security maps associated with `connector-Pool1`.

```
asadmin> list-connector-security-maps --verbose connector-Pool1
securityMap1
principal1
principal1
Command list-connector-security-maps executed successfully.
```

▼ To Update a Connector Security Map

Use the `update-connector-security-map` subcommand in remote mode to create or modify a security map for the specified connector connection pool.

- 1 Ensure that the server is running.
Remote subcommands require a running server.
- 2 List existing connector security maps by using the `list-connector-security-maps(1)` subcommand.
- 3 Modify a security map for a specific connector connection pool by using the `update-connector-security-map(1)` subcommand.

4 (Optional) If needed, restart the server.

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 12-14 Updating a Connector Security Map

This example adds principals to securityMap1.

```
asadmin> update-connector-security-map --poolname connector-pool1
--addprincipals principal1, principal2 securityMap1
Command update-connector-security-map executed successfully.
```

▼ To Delete a Connector Security Map

Use the `delete-connector-security-map` subcommand in remote mode to delete a security map for the specified connector connection pool.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List existing connector connection pools by using the `list-connector-connection-pools(1)` subcommand.**3 Delete a security map for a specific connector connection pool by using the `delete-connector-security-map(1)` subcommand.**

Information about options for this subcommand is included in this help page.

Example 12-15 Deleting a Connector Security Map

This example deletes securityMap1 from connector-pool1.

```
asadmin> delete-connector-security-map --poolname connector-pool1 securityMap1
Command delete-connector-security-map executed successfully
```

Administering Connector Work Security Maps

The EIS is any system that holds the data of an organization. It can be a mainframe, a messaging system, a database system, or an application. The connector work security map is used to map the EIS credentials to the credentials of GlassFish Server security domain.

A security map applies to a particular connector connection pool. One or more named security maps can be associated with a connector connection pool.

The following topics are addressed here:

- [“To Create a Connector Work Security Map” on page 287](#)
- [“To List Connector Work Security Maps” on page 288](#)
- [“To Update a Connector Work Security Map” on page 288](#)
- [“To Delete a Connector Work Security Map” on page 289](#)

▼ To Create a Connector Work Security Map

Use the `create-connector-work-security-map` subcommand in remote mode to map the caller identity of the work submitted by the connector module (resource adapter) EIS principal or EIS user group to a suitable principal or user group in the GlassFish Server security domain. One or more work security maps can be associated with a connector module.

The connector security map configuration supports the use of the wild card asterisk (*) to indicate all users or all user groups.

Before You Begin Before creating a connector work security map, you must first create a connector connection pool. For instructions, see [“To Create a Connector Connection Pool” on page 275](#).

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Create the connector work security map by using the `create-connector-work-security-map(1)` subcommand.

Information about properties for the subcommand is included in this help page.

3 (Optional) If needed, restart the server.

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 12–16 Creating Connector Work Security Maps

The following examples create `workSecurityMap1` and `workSecurityMap2` for `my-resource-adapter-name`.

```
asadmin> create-connector-work-security-map --rname my-resource-adapter-name
--principalsmap eis-principal-1=server-principal-1,eis-principal-2=server-principal-2,
eis-principal-3=server-principal-1 workSecurityMap1
```

```
asadmin> create-connector-work-security-map --rname my-resource-adapter-name
--groupsmap eis-group-1=server-group-1,eis-group-2=server-group-2,
eis-group-3=server-group-1 workSecurityMap2
Command create-connector-work-security-map executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-connector-work-security-map` at the command line.

▼ To List Connector Work Security Maps

Use the `list-connector-work-security-maps` subcommand in remote mode to list the work security maps that belong to a specific connector module.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the connector work security maps by using the `list-connector-work-security-maps(1)` subcommand.**

Example 12–17 Listing the Connector Work Security Maps

This example lists the generic work security maps.

```
asadmin> list-connector-work-security-maps generic-ra
generic-ra-groups-map: EIS group=eis-group, mapped group=glassfish-group
generic-ra-principals-map: EIS principal=eis-bar, mapped principal=bar
generic-ra-principals-map: EIS principal=eis-foo, mapped principal=foo
Command list-connector-work-security-maps executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-connector-work-security-maps` at the command line.

▼ To Update a Connector Work Security Map

Use the `update-connector-work-security-map` subcommand in remote to modify a work security map that belongs to a specific resource adapter (connector module).

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the connector work security maps by using the `list-connector-work-security-maps(1)` subcommand.**
- 3 **If necessary, notify users that the connector work security map is being modified.**
- 4 **Update a connector work security map by using the `update-connector-work-security-map(1)` subcommand.**

Example 12–18 Updating a Connector Work Security Map

This example removes a principal from a work security map.

```
asadmin> update-connector-work-security-map --raname generic-ra
--removeprincipals eis-foo generic-ra-principals-map
Command update-connector-work-security-map executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help update-connector-work-security-map` at the command line.

▼ To Delete a Connector Work Security Map

Use the `delete-connector-work-security-map` subcommand in remote mode to delete a work security map that belongs to a specific connector module (resource adapter).

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the connector work security maps by using the `list-connector-work-security-maps(1)` subcommand.**
- 3 **Delete a connector work security map by using the `delete-connector-work-security-map(1)` subcommand.**

Example 12–19 Deleting a Connector Work Security Map

This example deletes the `worksecuritymap1` map from the `my_ra` connector module.

```
asadmin> delete-connector-work-security-map --raname my_ra worksecuritymap1
Command delete-connector-work-security-map executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-connector-work-security-map` at the command line.

Administering Administered Objects

Packaged within a connector module, an administered object provides specialized functionality for an application. For example, an administered object might provide access to a parser that is specific to the connector module and its associated EIS.

The following topics are addressed here:

- [“To Create an Administered Object” on page 290](#)
- [“To List Administered Objects” on page 290](#)
- [“To Update an Administered Object” on page 291](#)
- [“To Delete an Administered Object” on page 291](#)

▼ To Create an Administered Object

Use the `create-admin-object` subcommand to create an administered object resource. When creating an administered object resource, name-value pairs are created, and the object is associated to a JNDI name.

Before You Begin The resource adapter must be deployed before running this subcommand (`jmsra.rar`).

1 Create an administered object by using the `create-admin-object(1)` subcommand.

Information about properties for the subcommand is included in this help page.

2 (Optional) If needed, restart the server.

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 12–20 Creating an Administered Object

For this example, the `javax.jms.Queue` resource type is obtained from the `ra.xml` file. The JNDI name of the new administered object is `.jms/samplequeue`.

```
asadmin> create-admin-object --restype javax.jms.Queue --raname jmsra
--description "sample administered object" --property Name=sample_jmsqueue jms/samplequeue
Command create-admin-object executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-admin-object` at the command line.

▼ To List Administered Objects

Use the `list-admin-object` subcommand in remote mode to list the existing administered objects.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List the administered objects by using the `list-admin-objects(1)` subcommand.

Example 12–21 Listing Administered Objects

This example lists the existing administered objects.

```
asadmin> list-admin-objects
jms/samplequeue
Command list-admin-objects executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-admin-object` at the command line.

▼ To Update an Administered Object

Use the `get` and `set` subcommands to view and change the values of the administered objects properties.

- 1 List the administered objects by using the `list-admin-objects(1)` subcommand.
- 2 View the properties of the administered object by using the `get(1)` subcommand.

For example:

```
asadmin> get domain.resources.admin-object-resource.jms/samplequeue.*
```

- 3 Set the property of the administered object by using the `set(1)` subcommand.

For example:

```
asadmin> set domain.resources.admin-object-resource.jms/samplequeue.enabled=false
```

- 4 (Optional) If needed, restart the server.

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

▼ To Delete an Administered Object

Use the `delete-admin-object` subcommand to delete an administered objects.

- 1 List the administered objects by using the `list-admin-objects(1)` subcommand.
- 2 If necessary, notify users that the administered object is being deleted.
- 3 Delete an administered object by using the `delete-admin-object(1)` subcommand.

Example 12–22 Deleting an Administered Object

This example deletes the administered object with the JNDI name `.jms/samplequeue`.

```
asadmin> delete-admin-object jms/samplequeue  
Command delete-admin-object executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-admin-object` at the command line.

Administering Internet Connectivity

This chapter provides procedures for performing internet connectivity tasks in the GlassFish Server Open Source Edition 3.1 environment by using the `asadmin` command-line utility.

The following topics are addressed here:

- [“About Internet Connectivity” on page 293](#)
- [“Administering HTTP Network Listeners” on page 295](#)
- [“Administering Virtual Servers” on page 305](#)

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

About Internet Connectivity

The HTTP service provides functionality for deploying web applications and for making deployed web applications accessible by Internet clients, either in a single application server instance or in a cluster of multiple server instances. HTTP services are provided by two kinds of related objects: listeners and virtual servers.

For more information about clusters, see the *GlassFish Server Open Source Edition 3.1 High Availability Administration Guide*.

The following topics are addressed here:

- [“About HTTP Network Listeners” on page 293](#)
- [“About Virtual Servers” on page 294](#)

About HTTP Network Listeners

An *HTTP listener*, also known as a *network listener*, is a listen socket that has an Internet Protocol (IP) address, a port number, a server name, and a default virtual server. Each virtual server provides connections between the server and clients through one or more listeners. Each

listener must have a unique combination of port number and IP address. For example, an HTTP listener can listen for a host on all configured IP addresses on a given port by specifying the IP address 0.0.0.0. Alternatively, the listener can specify a unique IP address for each listener while using the same port.

Because an HTTP listener is a combination of IP address and port number, you can have multiple HTTP listeners with the same IP address and different port numbers, or with different IP addresses and the same port number (if your host was configured to respond to these addresses). However, if an HTTP listener uses the 0.0.0.0 IP address, which listens on all IP addresses on a port, you cannot create HTTP listeners for additional IP addresses that listen on the same port for a specific IP address. For example, if an HTTP listener uses 0.0.0.0:8080 (all IP addresses on port 8080), another HTTP listener cannot use 1.2.3.4:8080. The host running the GlassFish Server typically has access to only one IP address. HTTP listeners typically use the 0.0.0.0 IP address and different port numbers, with each port number serving a different purpose. However, if the host does have access to more than one IP address, each address can serve a different purpose.

To access a web application deployed on GlassFish Server, use the URL `http://localhost:8080/` (or `https://localhost:8081/` for a secure application), along with the context root specified for the web application.

To access the Administration Console, use the URL `https://localhost:4848/` or `http://localhost:4848/asadmin/` (console default context root).

About Virtual Servers

A *virtual server*, sometimes called a virtual host, is an object that allows the same physical server to host multiple Internet domain names. All virtual servers hosted on the same physical server share the IP address of that physical server. A virtual server associates a domain name for a server (such as `www.aaa.com`) with the particular server on which GlassFish Server is running. Each virtual server must be registered with the DNS server for your network.

Note – Do not confuse an Internet domain with the administrative domain of GlassFish Server.

For example, assume that you want to host the following domains on your physical server: `www.aaa.com`, `www.bbb.com`, and `www.ccc.com`. Assume that these domains are respectively associated with web modules `web1`, `web2`, and `web3`. This means that the following URLs are handled by your physical server:

```
http://www.aaa.com:8080/web1
http://www.bbb.com:8080/web2
http://www.ccc.com:8080/web3
```

The first URL is mapped to virtual server `www.aaa.com`, the second URL is mapped to virtual server `www.bbb.com`, and the third is mapped to virtual server `www.ccc.com`. For this mapping to work, `www.aaa.com`, `www.bbb.com`, and `www.ccc.com` must all resolve to your physical server's IP address and each virtual server must be registered with the DNS server for your network. In addition, on a UNIX system, add these domains to your `/etc/hosts` file (if the setting for `hosts` in your `/etc/nsswitch.conf` file includes `files`).

Administering HTTP Network Listeners

By default, when GlassFish Server starts, the following HTTP listeners are started automatically:

- HTTP listeners associated with the virtual server named `server`:
 - The listener named `http-listener-1` does not have security enabled.
 - The listener named `http-listener-2` has security enabled
- An HTTP listener named `admin-listener`, associated with the virtual server named `__asadmin`. For this listener, security is not enabled.

The following table describes the GlassFish Server default ports for the listeners that use ports.

TABLE 13-1 Default Ports for Listeners

Listener	Default Port	Description
Administrative server	4848	A domain's administrative server is accessed by the Administration Console and the <code>asadmin</code> utility. For the Administration Console, specify the port number in the URL of the browser. When running an <code>asadmin</code> subcommand remotely, specify the port number by using the <code>-port</code> option.
HTTP	8080	The web server listens for HTTP requests on a port. To access deployed web applications and services, clients connect to this port.
HTTPS	8181	Web applications configured for secure communications listen on a separate port.

The following topics are addressed here:

- [“To Create an Internet Connection” on page 296](#)
- [“Administering HTTP Protocols” on page 296](#)
- [“Administering HTTP Configurations” on page 298](#)
- [“Administering HTTP Transports” on page 299](#)
- [“Administering HTTP Network Listeners” on page 301](#)

▼ To Create an Internet Connection

Use the subcommands in this procedure to create an internet connection with the full range of listener options. A network listener is created behind the scenes. For the shortcut version of this process, see [“To Create an HTTP Network Listener” on page 301](#).

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Create an HTTP or HTTPS protocol by using the `create-protocol(1)` subcommand with the `--securityenabled` option.

To use the built-in `http-listener-1` HTTP protocol, or `http-listener-2` HTTPS protocol, skip this step.

3 Create an HTTP configuration by using the `create-http(1)` subcommand.

To use a built-in protocol, skip this step.

4 Create a transport by using the `create-transport(1)` subcommand.

To use the built-in `tcp` transport, skip this step.

5 (Optional) Create a thread pool by using the `create-threadpool(1)` subcommand.

To avoid using a thread pool, or to use the built-in `http-thread-pool` thread pool, skip this step.

For additional thread pool information, see [Chapter 5, “Administering Thread Pools.”](#)

6 Create an HTTP listener by using the `create-network-listener(1)` subcommand.

Specify a protocol and transport, optionally a thread pool.

7 To apply your changes, restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

See Also You can also view the full syntax and options of the subcommand by typing a command such as `asadmin help create-http-listener` at the command line.

Administering HTTP Protocols

Each HTTP listener has an HTTP protocol, which is created either by using the `create-protocol` subcommand or by using the built-in protocols that are applied when you follow the instructions in [“To Create an HTTP Network Listener” on page 301](#).

The following topics are addressed here:

- [“To Create a Protocol” on page 297](#)
- [“To List Protocols” on page 297](#)
- [“To Delete a Protocol” on page 298](#)

▼ To Create a Protocol

Use the `create-protocol` subcommand in remote mode to create a protocol.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Create a protocol by using the `create-protocol(1)`

Information about options and properties for the subcommand are included in this help page.

Example 13–1 Creating an HTTP Protocol

This example creates a protocol named `http-1` with security enabled.

```
asadmin> create-protocol --securityenabled=true http-1
Command create-protocol executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-protocol` at the command line.

▼ To List Protocols

Use the `list-protocols` subcommand in remote mode to list the existing HTTP protocols.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List the existing protocols by using the `list-protocols(1)` subcommand.

Example 13–2 Listing the Protocols

This example lists the existing protocols.

```
asadmin> list-protocols
admin-listener
http-1
http-listener-1
http-listener-2
Command list-protocols executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-protocols` at the command line.

▼ **To Delete a Protocol**

Use the `delete-protocol` subcommand in remote mode to remove a protocol.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Delete a protocol by using the `delete-protocol(1)` subcommand**

Example 13–3 Deleting a Protocol

This example deletes the protocol named `http-1`.

```
asadmin> delete-protocol http-1
Command delete-protocol executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-protocol` at the command line.

Administering HTTP Configurations

Each HTTP listener has an HTTP configuration, which is created either by using the `create-http` subcommand or by using the built-in configurations that are applied when you follow the instructions in [“To Create an HTTP Network Listener” on page 301](#).

The following topics are addressed here:

- [“To Create an HTTP Configuration” on page 298](#)
- [“To Delete an HTTP Configuration” on page 299](#)

▼ **To Create an HTTP Configuration**

Use the `create-http` subcommand in remote mode to create a set of HTTP parameters for a protocol. This set of parameters configures one or more network listeners,

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Create an HTTP configuration by using the `create-http(1)` subcommand.**
Information about options and properties for the subcommand are included in this help page.

Example 13–4 Creating an HTTP Configuration

This example creates an HTTP parameter set for the protocol named `http-1`.

```
asadmin> create-http --timeout-seconds 60 --default-virtual-server server http-1
Command create-http executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-http` at the command line.

▼ **To Delete an HTTP Configuration**

Use the `delete-http` subcommand in remote mode to remove HTTP parameters from a protocol.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Delete the HTTP parameters from a protocol by using the `delete-http(1)` subcommand.**

Example 13–5 Deleting an HTTP Configuration

This example deletes the HTTP parameter set from a protocol named `http-1`.

```
asadmin> delete-http http-1
Command delete-http executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-http` at the command line.

Administering HTTP Transports

Each HTTP listener has an HTTP transport, which is created either by using the `create-transport` subcommand or by using the built-in transports that are applied when you follow the instructions in [“To Create an HTTP Network Listener” on page 301](#).

The following topics are addressed here:

- [“To Create a Transport” on page 300](#)
- [“To List Transports” on page 300](#)
- [“To Delete a Transport” on page 301](#)

▼ To Create a Transport

Use the `create-transport` subcommand in remote mode to create a transport for a network listener,

- 1 **Ensure that the server is running.**

Remote subcommands require a running server.

- 2 **Create a transport by using the `create-transport(1)` subcommand.**

Information about options and properties for the subcommand are included in this help page.

Example 13–6 Creating a Transport

This example creates a transport named `http1-trans` that uses a non-default number of acceptor threads.

```
asadmin> create-transport --acceptorthreads 100 http1-trans
Command create-transport executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-transport` at the command line.

▼ To List Transports

Use the `list-transports` subcommand in remote mode to list the existing HTTP transports.

- 1 **Ensure that the server is running.**

Remote subcommands require a running server.

- 2 **List the existing transports by using the `list-transports(1)` subcommand.**

Example 13–7 Listing HTTP Transports

This example lists the existing transports.

```
asadmin> list-transports
http1-trans
tcp
Command list-transports executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-transports` at the command line.

▼ To Delete a Transport

Use the `delete-transport` subcommand in remote mode to remove a transport.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Delete a transport by using the `delete-transport(1)` subcommand.**

Example 13–8 Deleting a Transport

This example deletes the transport named `http1-trans`.

```
asadmin> delete-transport http1-trans
Command delete-transport executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-transport` at the command line.

Administering HTTP Network Listeners

The following topics are addressed here:

- [“To Create an HTTP Network Listener” on page 301](#)
- [“To List HTTP Network Listeners” on page 302](#)
- [“To Update an HTTP Network Listener” on page 303](#)
- [“To Delete an HTTP Network Listener” on page 303](#)
- [“To Configure an HTTP Listener for SSL” on page 304](#)
- [“To Delete SSL From an HTTP Listener” on page 304](#)
- [“To Assign a Default Virtual Server to an HTTP Listener” on page 305](#)

▼ To Create an HTTP Network Listener

Use the `create-http-listener` subcommand or the `create-network-listener` subcommand in remote mode to create a listener. These subcommands provide backward compatibility and also provide a shortcut for creating network listeners that use the HTTP protocol. Behind the scenes, a network listener is created as well as its associated protocol, transport, and HTTP configuration. This method is a convenient shortcut, but it gives access to only a limited number of options. If you want to specify the full range of listener options, follow the instructions in [“To Create an Internet Connection” on page 296](#).

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.

- 2 **Create an HTTP network listener by using the `create-network-listener(1)` subcommand or the `create-http-listener(1)` subcommand.**

- 3 **If needed, restart the server.**

If you edit the special HTTP network listener named `admin-listener`, you must restart the server for changes to take effect. See [“To Restart a Domain” on page 116](#).

Example 13–9 Creating an HTTP Listener

This example creates an HTTP listener named `sampleListener` that uses a non-default number of acceptor threads. Security is not enabled at runtime.

```
asadmin> create-http-listener --listeneraddress 0.0.0.0
--listenerport 7272 --defaultvs server --servername host1.sun.com
--acceptorthreads 100 --securityenabled=false
--enabled=false sampleListener
Command create-http-listener executed successfully.
```

Example 13–10 Creating a Network Listener

This example a network listener named `sampleListener` that is not enabled at runtime:

```
asadmin> create-network-listener --listenerport 7272 protocol http-1
--enabled=false sampleListener
Command create-network-listener executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-http-listener` or `asadmin help create-network-listener` at the command line.

▼ To List HTTP Network Listeners

Use the `list-http-listeners` subcommand or the `list-network-listeners` subcommand in remote mode to list the existing HTTP listeners.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List HTTP listeners by using the `list-http-listeners(1)` or `list-network-listeners(1)` subcommand.**

Example 13–11 Listing HTTP Listeners

This example lists the HTTP listeners. The same output is given if you use the `list-network-listeners` subcommand.

```
asadmin> list-http-listeners
admin-listener
http-listener-2
http-listener-1
Command list-http-listeners executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-http-listeners` or `asadmin help list-network-listeners` at the command line.

▼ To Update an HTTP Network Listener

- 1 List HTTP listeners by using the `list-http-listeners(1)` or `list-network-listeners(1)` subcommand.
- 2 Modify the values for the specified listener by using the `set(1)` subcommand.
The listener is identified by its dotted name.

Example 13–12 Updating an HTTP Network Listener

This example changes `security-enabled` to `false` on `http-listener-2`.

```
asadmin> set server.network-config.protocols.protocol.http-listener-2.security-enabled=false
Command set executed successfully.
```

▼ To Delete an HTTP Network Listener

Use the `delete-http-listener` subcommand or the `delete-network-listener` subcommand in remote mode to delete an existing HTTP listener. This disables secure communications for the listener.

- 1 Ensure that the server is running.
Remote subcommands require a running server.
- 2 List HTTP listeners by using the `list-http-listeners(1)` subcommand.
- 3 Delete an HTTP listener by using the `delete-http-listener(1)` or `delete-network-listener(1)` subcommand.
- 4 To apply your changes, restart GlassFish Server.
See [“To Restart a Domain” on page 116](#).

Example 13–13 Deleting an HTTP Listener

This example deletes the HTTP listener named `sampleListener`:

```
asadmin> delete-http-listener sampleListener
Command delete-http-listener executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-http-listener` or `asadmin help delete-network-listener` at the command line.

▼ To Configure an HTTP Listener for SSL

Use the `create-ssl` subcommand in remote mode to create and configure an SSL element in the specified listener. This enables secure communication for the listener.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Configure an HTTP listener by using the `create-ssl(1)` subcommand.**
- 3 **To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 13–14 Configuring an HTTP Listener for SSL

This example enables the HTTP listener named `http-listener-1` for SSL:

```
asadmin> create-ssl --type http-listener --certname sampleCert http-listener-1
Command create-ssl executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-ssl` at the command line.

▼ To Delete SSL From an HTTP Listener

Use the `delete-ssl` subcommand in remote mode to delete the SSL element in the specified listener. This disables secure communications for the listener.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Delete SSL from an HTTP listener by using the `delete-ssl(1)` subcommand.**
- 3 **To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 13–15 Deleting SSL From an HTTP Listener

This example disables SSL for the HTTP listener named `http-listener-1`:


```
asadmin> delete-ssl --type http-listener http-listener-1
Command delete-http-listener executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-ssl` at the command line.

▼ To Assign a Default Virtual Server to an HTTP Listener

- 1 In the Administration Console, open the HTTP Service component under the relevant configuration.
- 2 Open the HTTP Listeners component under the HTTP Service component.
- 3 Select or create a new HTTP listener.
- 4 Select from the Default Virtual Server drop-down list.

For more information, see [“To Assign a Default Web Module to a Virtual Server”](#) on page 308.

See Also For details, click the Help button in the Administration Console from the HTTP Listeners page.

Administering Virtual Servers

A virtual server is a virtual web server that serves content targeted for a specific URL. Multiple virtual servers can serve content using the same or different host names, port numbers, or IP addresses. The HTTP service directs incoming web requests to different virtual servers based on the URL.

When you first install GlassFish Server, a default virtual server is created. You can assign a default virtual server to each new HTTP listener you create.

Web applications and Java EE applications containing web components (web modules) can be assigned to virtual servers during deployment. A web module can be assigned to more than one virtual server, and a virtual server can have more than one web module assigned to it. If you deploy a web application and don't specify any assigned virtual servers, the web application is assigned to all currently defined virtual servers. If you then create additional virtual servers and want to assign existing web applications to them, you must redeploy the web applications. For more information about deployment, see the *GlassFish Server Open Source Edition 3.1 Application Deployment Guide*.

You can define virtual server properties using the `asadmin set` command. For example:

```
asadmin> set server-config.http-service.virtual-server.MyVS.property.sso-enabled="true"
```

Some virtual server properties can be set for a specific web application. For details, see “glassfish-web-app” in *GlassFish Server Open Source Edition 3.1 Application Deployment Guide*.

The following topics are addressed here:

- [“To Create a Virtual Server” on page 306](#)
- [“To List Virtual Servers” on page 307](#)
- [“To Update a Virtual Server” on page 307](#)
- [“To Delete a Virtual Server” on page 307](#)
- [“To Assign a Default Web Module to a Virtual Server” on page 308](#)
- [“To Assign a Virtual Server to an Application or Module” on page 308](#)
- [“To Set JSESSIONIDSSO Cookie Attributes” on page 309](#)

▼ To Create a Virtual Server

By default, when GlassFish Server starts, the following virtual servers are started automatically:

- A virtual server named `server`, which hosts all user-defined web modules.
For development, testing, and deployment of web services in a non-production environment, `server` is often the only virtual server required.
- A virtual server named `__asadmin`, which hosts all administration-related web modules (specifically, the Administration Console). This server is restricted, which means that you cannot deploy web modules to this virtual server.

In a production environment, additional virtual servers provide hosting facilities for users and customers so that each appears to have its own web server, even though there is only one physical server.

Use the `create-virtual-server` subcommand in remote mode to create the named virtual server.

Before You Begin A virtual server must specify an existing HTTP listener. Because the virtual server cannot specify an HTTP listener that is already being used by another virtual server, create at least one HTTP listener before creating a new virtual server.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Create a virtual server by using the `create-virtual-server(1)` subcommand.**
Information about properties for this subcommand is included in this help page.
- 3 **To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 13–16 Creating a Virtual Server

This example creates a virtual server named `sampleServer` on `localhost`.

```
asadmin> create-virtual-server sampleServer  
Command create-virtual-server executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-virtual-server` at the command line.

▼ To List Virtual Servers

Use the `list-virtual-servers` subcommand in remote mode to list the existing virtual servers.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List virtual servers by using the `list-virtual-servers(1)` subcommand.**

Example 13–17 Listing Virtual Servers

This example lists the virtual servers for `localhost`.

```
asadmin> list-virtual-servers  
sampleListener  
admin-listener  
http-listener-2  
http-listener-1  
Command list-http-listeners executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-virtual-servers` at the command line.

▼ To Update a Virtual Server

- 1 **List virtual servers by using the `list-virtual-servers(1)` subcommand.**
- 2 **Modify the values for the specified virtual server by using the `set(1)` subcommand.**
The virtual server is identified by its dotted name.

▼ To Delete a Virtual Server

Use the `delete-virtual-server` subcommand in remote mode to delete an existing virtual server.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List virtual servers by using the `list-virtual-servers(1)` subcommand.**
- 3 **If necessary, notify users that the virtual server is being deleted.**
- 4 **Delete a virtual server by using the `delete-virtual-server(1)` subcommand.**
- 5 **To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 13–18 Deleting a Virtual Server

This example deletes the virtual server named `sampleServer` from `localhost`.

```
asadmin> delete-virtual-server sampleServer
Command delete-virtual-server executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-virtual-server` at the command line.

To Assign a Default Web Module to a Virtual Server

A default web module can be assigned to the default virtual server and to each new virtual server. To access the default web module for a virtual server, point the browser to the URL for the virtual server, but do not supply a context root. For example:

```
http://myvserver:3184/
```

A virtual server with no default web module assigned serves HTML or JavaServer Pages (JSP) content from its document root, which is usually *domain-dir/docroot*. To access this HTML or JSP content, point your browser to the URL for the virtual server, do not supply a context root, but specify the target file.

For example:

```
http://myvserver:3184/hellothere.jsp
```

▼ To Assign a Virtual Server to an Application or Module

You can assign a virtual server to a deployed application or web module.

Before You Begin The application or module must already be deployed. For more information, see *GlassFish Server Open Source Edition 3.1 Application Deployment Guide*.

- 1 In the Administration Console, open the HTTP Service component under the relevant configuration.
- 2 Open the Virtual Servers component under the HTTP Service component.
- 3 Select the virtual server to which you want to assign a default web module.
- 4 Select the application or web module from the Default Web Module drop-down list.

For more information, see [“To Assign a Default Web Module to a Virtual Server”](#) on page 308.

▼ To Set JSESSIONIDSSO Cookie Attributes

Use the `sso-cookie-http-only` and `sso-cookie-secure` virtual server attributes to set the `HttpOnly` and `Secure` attributes of any `JSESSIONIDSSO` cookies associated with web applications deployed to the virtual server.

- Use the `set(1)` subcommand to set the value of the `sso-cookie-http-only` and `sso-cookie-secure` virtual server attributes.

The values supported for these attributes are as follows:

`sso-cookie-http-only`

A boolean value that specifies whether the `HttpOnly` attribute is included in `JSESSIONIDSSO` cookies. When set to `true`, which is the default, the `HttpOnly` attribute is included. When set to `false`, the `HttpOnly` attribute is not included.

`sso-cookie-secure`

A string value that specifies whether the `Secure` attribute is included in `JSESSIONIDSSO` cookies. Allowed values are as follows:

- `true` — The `Secure` attribute is included.
- `false` — The `Secure` attribute is not included.
- `dynamic` — The `Secure` attribute setting is inherited from the first session participating in SSO. This is the default value.

Administering the Object Request Broker (ORB)

GlassFish Server supports a standard set of protocols and formats that ensure interoperability. Among these protocols are those defined by CORBA. The Object Request Broker (ORB) is the central component of CORBA. The ORB provides the required infrastructure to identify and locate objects, handle connection management, deliver data, and request communication. This chapter describes how to configure the ORB and the IIOP listeners.

The following topics are addressed here:

- [“About the ORB” on page 311](#)
- [“Configuring the ORB” on page 312](#)
- [“Administering IIOP Listeners” on page 312](#)

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

About the ORB

The Common Object Request Broker Architecture (CORBA) model is based on clients requesting services from distributed objects or servers through a well-defined interface by issuing requests to the objects in the form of remote method requests. A *remote method request* carries information about the operation that needs to be performed, including the object name (called an object reference) of the service provider and parameters, if any, for the invoked method. CORBA automatically handles network programming tasks such as object registration, object location, object activation, request de-multiplexing, error-handling, marshalling, and operation dispatching.

Configuring the ORB

A CORBA object never talks directly with another. Instead, the object makes requests through a remote stub to the Internet Inter-Orb Protocol (IIOP) running on the local host. The local ORB then passes the request to an ORB on the other host using IIOP. The remote ORB then locates the appropriate object, processes the request, and returns the results.

IIOP can be used as a Remote Method Invocation (RMI) protocol by applications or objects using RMI-IIOP. Remote clients of enterprise beans (EJB modules) communicate with GlassFish Server by using RMI-IIOP.

Administering IIOP Listeners

An *IIOP listener* is a listen socket that accepts incoming connections from the remote clients of enterprise beans and from other CORBA-based clients. Multiple IIOP listeners can be configured for GlassFish Server. For each listener, specify a port number (optional; default 1072), a network address, and security attributes (optional). If you create multiple listeners, you must assign a different port number for each listener.

The following topics are addressed here:

- [“To Create an IIOP Listener” on page 312](#)
- [“To List IIOP Listeners” on page 313](#)
- [“To Update an IIOP Listener” on page 313](#)
- [“To Delete an IIOP Listener” on page 314](#)

▼ To Create an IIOP Listener

Use the `create-iiop-listener` subcommand in remote mode to create an IIOP listener.

- 1 Ensure that the server is running.**
Remote subcommands require a running server.
- 2 Create an IIOP listener by using the `create-iiop-listener(1)` subcommand.**
Information about the properties for the subcommand is included in this help page.
- 3 To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 14–1 Creating an IIOP Listener

This example creates an IIOP listener named `sample_iiop_listener`.


```
asadmin> create-iiop-listener --listeneraddress 192.168.1.100
--iiopport 1400 sample_iiop_listener
Command create-iiop-listener executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-iiop-listener` at the command line.

▼ To List IIOP Listeners

Use the `list-iiop-listeners` subcommand in remote mode to list the existing IIOP listeners.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the IIOP listeners by using the `list-iiop-listeners(1)` subcommand.**

Example 14–2 Listing IIOP Listeners

This example lists all the IIOP listeners for the server instance.

```
asadmin> list-iiop-listeners
orb-listener-1
SSL
SSL_MUTUALAUTH
sample_iiop_listener
Command list-iiop-listeners executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-iiop-listeners` at the command line.

▼ To Update an IIOP Listener

- 1 **List the IIOP listeners by using the `list-iiop-listeners(1)` subcommand.**
- 2 **Modify the values for the specified IIOP listener by using the `set(1)` subcommand.**
The listener is identified by its dotted name.

Example 14–3 Updating an IIOP Listener

This example changes SSL from enabled to disabled.

```
asadmin> set "server.iiop-service.iiop-listener.SSL.enabled"
server.iiop-service.iiop-listener.SSL.enabled=false
Command set executed successfully.
```

▼ To Delete an IIOP Listener

Use the `delete-iiop-listener` subcommand in remote mode to delete an IIOP listener.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List the IIOP listeners by using the `list-iiop-listeners(1)` subcommand.

3 Delete an IIOP listener by using the `delete-iiop-listener(1)` subcommand.

4 To apply your changes, restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

Example 14–4 Deleting an IIOP Listener

This example deletes the IIOP listener named `sample_iiop_listener`.

```
asadmin> delete-iiop-listener sample_iiop_listener
Command delete-iiop-listener executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-iiop-listener` at the command line.

Administering the JavaMail Service

GlassFish Server includes the JavaMail API along with JavaMail service providers that allow an application component to send email notifications over the Internet and to read email from IMAP and POP3 mail servers.

The following topics are addressed here:

- “About JavaMail” on page 315
- “Administering JavaMail Resources” on page 316

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

About JavaMail

The JavaMail API is a set of abstract APIs that model a mail system. The JavaMail API provides a platform-independent and protocol-independent framework to build mail and messaging applications and provide facilities for reading and sending electronic messages. Service providers implement particular protocols. Using the API you can add email capabilities to your applications. JavaMail provides access from Java applications to Internet Message Access Protocol (IMAP) and Simple Mail Transfer Protocol (SMTP) capable mail servers on your network or the Internet. The API does not provide mail server functionality; you must have access to a mail server to use JavaMail.

The JavaMail API is implemented as an optional package in the Java platform and is also available as part of the Java EE platform.

To learn more about the JavaMail API, consult the [JavaMail web site \(http://www.oracle.com/technetwork/java/javamail/\)](http://www.oracle.com/technetwork/java/javamail/).

Administering JavaMail Resources

When you create a mail session, the server-side components and applications are enabled to access JavaMail services with JNDI, using the session properties you assign for them. When creating a mail session, you can designate the mail hosts, the transport and store protocols, and the default mail user so that components that use JavaMail do not have to set these properties. Applications that are heavy email users benefit because GlassFish Server creates a single session object and makes the session available to any component that needs it.

JavaMail settings such as the following can be specified:

- **JNDI Name.** The unique name for the mail session. Use the naming sub-context prefix `mail/` for JavaMail resources. For example: `mail/MySession`
- **Mail Host.** The host name of the default mail server. The connect methods of the store and transport objects use this value if a protocol-specific host property is not supplied. The name must be resolvable to an actual host name.
- **Default User.** The default user name to provide when connecting to a mail server. The connect methods of the store and transport objects use this value if a protocol-specific username property is not supplied.
- **Default Return Address.** The email address of the default user, in the form: `username@host.domain`.
- **Description.** A descriptive statement for the component.
- **Session.** Indicates whether or not mail session is enabled or disabled at this time

The following topics are addressed here:

- [“To Create a JavaMail Resource” on page 316](#)
- [“To List JavaMail Resources” on page 317](#)
- [“To Update a JavaMail Resource” on page 317](#)
- [“To Delete a JavaMail Resource” on page 318](#)

▼ To Create a JavaMail Resource

Use the `create-javamail-resource` subcommand in remote mode to create a JavaMail session resource. The JNDI name for a JavaMail session resource customarily includes the `mail/` naming subcontext. For example: `mail/MyMailSession`.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Create a JavaMail resource by using the `create-javamail-resource(1)` subcommand.**
Information about the properties for the subcommand is included in this help page.

3 To apply your changes, restart GlassFish Server.

See [“To Restart a Domain” on page 116](#).

Example 15–1 Creating a JavaMail Resource

This example creates a JavaMail resource named `mail/MyMailSession`. The escape character (`\`) is used in the `--fromaddress` option to distinguish the dot (`.`) and at sign (`@`).

```
asadmin> create-javamail-resource --mailhost localhost
--mailuser sample --fromaddress sample\@sun\.com mail/MyMailSession
Command create-javamail-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-javamail-resource` at the command line.

▼ To List JavaMail Resources

Use the `list-javamail-resources` subcommand in remote mode to list the existing JavaMail session resources.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 List the JavaMail resources by using the `list-javamail-resources(1)` subcommand.

Example 15–2 Listing JavaMail Resources

This example lists the JavaMail resources on `localhost`.

```
asadmin> list-javamail-resources
mail/MyMailSession
Command list-javamail-resources executed successfully.
```

See Also You can also view the full syntax and options of the subcommands by typing `asadmin help list-javamail-resources` at the command line.

▼ To Update a JavaMail Resource

1 List the JavaMail resources by using the `list-javamail-resources(1)` subcommand.

2 Modify the values for the specified JavaMail source by using the `set(1)` subcommand.

The resource is identified by its dotted name.

Example 15-3 Updating a JavaMail Resource

This example changes joeserver to joe.

```
asadmin> set server.resources.mail-resource.mail/  
MyMailSession.user=joeserver.resources.mail-resource.mail/  
MyMailSession.user=joe  
Command set executed successfully.
```

▼ To Delete a JavaMail Resource

Use the `delete-javamail-resource` subcommands in remote mode to delete a JavaMail session resource.

Before You Begin References to the specified resource must be removed before running the `delete-javamail-resource` subcommands.

- 1 Ensure that the server is running.**
Remote subcommands require a running server.
- 2 List the JavaMail resources by using the `list-javamail-resources(1)` subcommands.**
- 3 Delete a JavaMail resource by using the `delete-javamail-resource(1)` subcommands.**
- 4 To apply your changes, restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 15-4 Deleting a JavaMail Resource

This example deletes the JavaMail session resource named `mail/MyMailSession`.

```
asadmin> delete-javamail-resource mail/MyMailSession  
Command delete-javamail-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-javamail-resource` at the command line.

Administering the Java Message Service (JMS)

The Java Message Service (JMS) API is a messaging standard that allows Java EE applications and components, including message-driven beans (MDBs), to create, send, receive, and read messages. It enables distributed communication that is loosely coupled, reliable, and asynchronous.

GlassFish Server supports JMS messaging by communicating with a *JMS provider* through a Java EE Connector resource adapter. By default, GlassFish Server provides JMS messaging through its built-in *jmsra* resource adapter communicating with Open Message Queue, which is included with GlassFish Server. This combination, known as the *JMS Service*, is tightly integrated with GlassFish Server, providing a rich set of `asadmin` subcommands and Administration Console pages to simplify JMS messaging administration tasks.

GlassFish Server also supports the Generic Resource Adapter for JMS (GenericJMSRA), available as an Add-On in the Administration Console's Update Tool, for use as a resource adapter to connect to other JMS providers. The last section in this chapter, [“Using the Generic Resource Adapter for JMS to Integrate Supported External JMS Providers” on page 336](#), describes the GenericJMSRA and provides instructions for using it to make other supported JMS providers available to GlassFish Server.

The following topics are addressed here:

- [“About the JMS Service” on page 320](#)
- [“Updating the JMS Service Configuration” on page 321](#)
- [“Administering JMS Hosts” on page 323](#)
- [“Administering JMS Connection Factories and Destinations” on page 328](#)
- [“Administering JMS Physical Destinations” on page 332](#)
- [“Special Situations When Using the JMS Service” on page 335](#)
- [“Troubleshooting the JMS Service” on page 336](#)
- [“Using the Generic Resource Adapter for JMS to Integrate Supported External JMS Providers” on page 336](#)

Instructions for accomplishing the task in this chapter by using the Administration Console are contained in the Administration Console online help.

About the JMS Service

To support JMS messaging, the JMS Service provides the following administrative objects:

JMS Service Configuration

The JMS service configuration is part of the overall configuration for a GlassFish standalone instance or cluster. It specifies how the JMS Service is to create and maintain connections with JMS Hosts.

JMS Hosts

JMS hosts are the message servers that host destinations, store messages, and interact with applications to send and receive messages across connections. In Message Queue, JMS hosts are called *brokers*.

The JMS service supports these types of JMS hosts:

- **Embedded** type, in which the JMS host runs in the same JVM as the GlassFish instance; its configuration and lifecycle are managed by the JMS service
- **Local** type, in which the JMS host runs separately on the same host as the GlassFish instance; its configuration and lifecycle are managed by the JMS service
- **Remote** type, in which the JMS host represents a Message Queue broker or broker cluster that is external to the JMS service; its operation is managed using Message Queue administrative tools

For more information about JMS host types, see [“About JMS Host Types” on page 323](#).

JMS Connection Factory Resources

JMS connection factory resources house the information that applications use to connect to a JMS provider. For each JMS connection factory, the JMS service automatically maintains a GlassFish connector resource and a GlassFish connector connection pool in order to support connection pooling and failover.

JMS Destination Resources

JMS destination resources house the information that applications use to specify the target destination of messages they produce and the source destination of messages they consume. For each JMS destination resource, the JMS service automatically maintains a GlassFish administered object.

JMS Physical Destinations

JMS physical destinations provide a means to create and manage JMS destinations administratively instead of having them created dynamically when needed by an application. While dynamic creation of destinations is often sufficient during application development, administratively created physical destinations are more suitable for production environments.

JMS Service High Availability

Just as GlassFish Server supports clusters of instances to provide high availability, Message Queue supports clusters of brokers to provide service availability or service and data availability, depending on the type of broker cluster, as described in Chapter 4, “Broker Clusters,” in *Open Message Queue 4.5 Technical Overview*.

The JMS service takes advantage of this Message Queue capability and automatically creates and manages a Message Queue broker cluster when a GlassFish cluster's configuration specifies Embedded or Local type JMS hosts. Additionally, both GlassFish clusters and standalone instances can use Message Queue broker clusters as Remote type JMS hosts.

For information about how the JMS service supports GlassFish clusters and Message Queue broker clusters, see Chapter 10, “Configuring Java Message Service High Availability,” in *GlassFish Server Open Source Edition 3.1 High Availability Administration Guide*.

Updating the JMS Service Configuration

Because the JMS service configuration is part of the overall configuration for a standalone instance or cluster, it is created when the standalone instance or cluster is created. You can then update the JMS service configuration by using the Java Message Service page for the configuration in the Administration Console, or by using a `set` subcommand of the following form:

```
set configs.config.config-name.jms-service.attribute-name=attribute-value
```

The attributes you can set are:

`type`

The JMS host type the service is to use. Available choices are EMBEDDED, LOCAL and REMOTE. See “[About JMS Host Types](#)” on page 323 for more information.

`init-timeout-in-seconds`

The number of seconds GlassFish Server waits for the JMS service to start before aborting the startup.

`start-args`

A list of arguments the JMS service passes to Embedded and Local type JMS hosts on startup. Permissible arguments are the options supported by the Message Queue `imqbrokerd` command, as described in “Broker Utility” in *Open Message Queue 4.5 Administration Guide*.

`default-jms-host`

The name of the default JMS host.

`reconnect-enabled`

When set to `true`, the JMS service attempts to reconnect to a JMS host (or one of the JMS hosts in the `AddressList`) when a connection is lost.

`reconnect-attempts`

The number of attempts to connect (or reconnect) for each JMS host in the `AddressList` before the JMS service tries the next address in the list. A value of `-1` indicates that the number of reconnect attempts is unlimited (the JMS service attempts to connect to the first address until it succeeds).

`reconnect-interval-in-seconds`

The number of seconds between reconnect attempts. This interval applies for attempts on each JMS host in the `AddressList` and for successive addresses in the list. If it is too short, this time interval does not give a JMS host time to recover. If it is too long, the reconnect might represent an unacceptable delay.

`addresslist-behavior`

The order of connection attempts. Available choices are:

`random`

Select a JMS host from the `AddressList` randomly. If there are many clients attempting a connection using the same connection factory, specify `random` to prevent them from all being connected to the same JMS host.

`priority`

Always try to connect to the first JMS host in the `AddressList` and use another one only if the first one is not available.

`addresslist-iterations`

The number of times the JMS service iterates through the `AddressList` in an effort to establish (or reestablish) a connection. A value of `-1` indicates that the number of attempts is unlimited.

`mq-scheme`

`mq-service`

The Message Queue address scheme name and connection service name to use for the `AddressList` if a non-default scheme or service is to be used. See “Connection Handling” in *Open Message Queue 4.5 Administration Guide* for syntax information.

Note – After making changes to the JMS service configuration, GlassFish Server instances that use the configuration must be restarted in order for the changes to be propagated.

Setting Message Queue Broker Properties in the JMS Service Configuration

You can specify any Message Queue broker property in the JMS service configuration by adding it by name to the Additional Properties table on the Java Message Service page for the configuration in the Administration Console, or by using a set subcommand of the following form:

```
set configs.config.config-name.jms-service.property.broker-property-name=value
```

If the broker property name includes dots, preface the dots with two backslashes (\); for example, to set the `imq.system.max_count` property, specify `imq\\.system\\.max_count` in the set subcommand.

Note – You can also set broker properties in the JMS host. If you set the same broker property in both the JMS service configuration and the JMS host, the value specified in the JMS host is used.

Administering JMS Hosts

A *JMS host* represents a Message Queue broker. JMS contains a *JMS hosts list* (the `AddressList` property) that contains all the JMS hosts that are used by GlassFish Server. The JMS hosts list is populated with the hosts and ports of the specified Message Queue brokers and is updated whenever a JMS host configuration changes. When you create JMS resources or deploy message driven beans, the resources or beans inherit the JMS hosts list.

The following topics are addressed here:

- [“About JMS Host Types” on page 323](#)
- [“Configuring Embedded and Local JMS Hosts” on page 324](#)
- [“To Create a JMS Host” on page 325](#)
- [“To List JMS Hosts” on page 326](#)
- [“To Update a JMS Host” on page 327](#)
- [“To Delete a JMS Host” on page 328](#)

For information about administering JMS hosts that are servicing GlassFish clusters, see “Configuring GlassFish Clusters to Use Message Queue Broker Clusters” in *GlassFish Server Open Source Edition 3.1 High Availability Administration Guide*.

About JMS Host Types

The JMS service uses Message Queue (MQ) brokers as JMS hosts, integrating them in three ways:

Embedded Type

When the JMS service configuration's `type` attribute is `EMBEDDED`, the MQ broker is co-located in the same JVM as the GlassFish server instance it services. The JMS service starts it in-process and manages its configuration and lifecycle.

For this type, the JMS service uses lazy initialization to start the broker when the first JMS operation is requested instead of immediately when the GlassFish instance is started. If necessary, you can force startup of the broker by using the `jsm-ping(1)` command.

Additionally, if the GlassFish instance is a standalone instance (not a clustered instance), JMS operations use a Message Queue feature called *direct mode* to bypass the networking stack, leading to performance optimization.

Local Type

When the JMS service configuration's `type` attribute is `LOCAL`, the JMS service starts the MQ broker specified in the configuration as the default JMS host in a separate process on the same host as the GlassFish server instance. The JMS service manages its configuration and lifecycle.

For this type, the JMS service starts the broker immediately when the GlassFish instance is started.

The JMS service provides the Message Queue broker an additional port to start the RMI registry. This port number is equal to the broker's JMS port plus 100. For example, if the JMS port number is 37676, then the additional port's number will be 37776. Additionally, the `start-args` property of the JMS service configuration can be used to specify Message Queue broker startup options.

Remote Type

When the JMS service configuration's `type` attribute is `REMOTE`, the JMS service uses the information defined by the default JMS host to communicate with an MQ broker or broker cluster that has been configured and started using Message Queue tools, as described in the *Open Message Queue 4.5 Administration Guide*. Ongoing administration and tuning of the broker or broker cluster are also performed using Message Queue tools.

Configuring Embedded and Local JMS Hosts

Because the JMS service, not Message Queue, manages Embedded and Local JMS hosts automatically, you should avoid using Message Queue utilities to configure them. Instead, specify broker properties in the JMS service configuration or in the JMS host.

Should the need to use Message Queue utilities arise, you must use the `-varhome` option when running certain Message Queue utilities to specify the `IMQ_VARHOME` location of the Embedded or Local JMS host. This location depends on which GlassFish instance the JMS host is servicing:

- For server, the Domain Administration Server (DAS), the `IMQ_VARHOME` location is:

domain-root-dir/domain-name/imq

- For any other GlassFish instance, the `IMQ_VARHOME` location is:

as-install/nodes/node-name/instance-name/imq

For example, the broker log file for an Embedded or Local JMS host servicing the DAS is available at *domain-root-dir/domain-name/imq/instances/imqbroker/log/log.txt*, and the broker log file for an Embedded or Local JMS host servicing any other GlassFish instance is available at *as-install/nodes/node-name/instance-name/imq/instances/mq-instance-name/log/log.txt*.

Note – When using Message Queue utilities on the Windows platform, you must explicitly use the Windows executable (.exe) versions of the utilities, even when running command shells such as Cygwin. For example, instead of running `imqcmd`, you must run `imqcmd.exe`.

▼ To Create a JMS Host

The default JMS service configuration includes a JMS host, `default_JMS_host`. For most situations, this host is sufficient, so replacing it or creating additional JMS hosts is not often necessary and is a task for advanced users. Use the `create-jms-host` subcommand in remote `asadmin` mode to create an additional JMS host.

1 Ensure that the server is running.

Remote `asadmin` subcommands require a running server.

2 Create the JMS host by using the `create-jms-host(1)` subcommand:

```
asadmin> create-jms-host --mqhost hostName --mqport portNumber
--mquser adminUser --mqpassword adminPassword --target glassfishTarget
--property mqBrokerPropList jms-host-name
```

--mqhost

The host name of the Message Queue broker.

--mqport

The port number of the Message Queue broker.

--mquser

The user name of the administrative user of the Message Queue broker.

--mqpassword

The password of the administrative user of the Message Queue broker.

--target

The GlassFish Server object for which the JMS host is being created. For details, see `create-jms-host(1)`.

--property

A list of one or more Message Queue broker properties to configure the broker. The list is colon-separated (:) and has the form:

prop1Name=prop1Value:prop2Name=prop2Value:...

If a broker property name includes dots, preface the dots with two backslashes (\\); for example, to include the `imq.system.max_count` property, specify `imq\\.system\\.max_count` in the `--property` option.

Note – You can also set broker properties in the JMS service configuration. If you set the same broker property in both the JMS host and the JMS service configuration, the value specified in the JMS host is used.

jms-host-name

The unique name of the JMS host.

Example 16–1 Creating a JMS Host

This example creates a JMS host named `MyNewHost`.

```
asadmin> create-jms-host --mqhost pigeon --mqport 7677
--mquser admin --mqpassword admin MyNewHost
Jms Host MyNewHost created.
Command create-jms-host executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-jms-host` at the command line.

▼ To List JMS Hosts

Use the `list-jms-hosts` subcommand in remote `asadmin` mode to list the existing JMS hosts.

- 1 **Ensure that the server is running.**
Remote `asadmin` subcommands require a running server.
- 2 **List the JMS hosts by using the `list-jms-hosts(1)` subcommand.**

Example 16–2 Listing JMS Hosts

The following subcommand lists the existing JMS hosts.

```
asadmin> list-jms-hosts
default_JMS_host
MyNewHost
Command list-jmsdest executed successfully
```

▼ To Update a JMS Host

Use the set subcommand in remote asadmin mode to update an existing JMS host.

1 Ensure that the server is running.

Remote asadmin subcommands require a running server.

2 Use the get(1) subcommand to list the current attribute values of the desired JMS host:

```
asadmin> get configs.config.config-name.jms-service.jms-host.jms-host-name.*
```

For information about JMS host attributes, see `create-jms-host(1)`.

3 Use the set(1) subcommand to modify a JMS host attribute:

```
asadmin> set configs.config.config-name.jms-service.jmshost.
jms-host-name.attribute-name=attribute-value
```

The attributes you can set are:

`host`

The host name of the Message Queue broker.

`port`

The port number of the Message Queue broker.

`admin-user-name`

The user name of the administrative user of the Message Queue broker.

`admin-password`

The password of the administrative user of the Message Queue broker.

`property.broker-property-name`

A Message Queue broker property. The property, and the value assigned to it, are used to configure the Message Queue broker.

If the broker property name includes dots, preface the dots with two backslashes (`\\`); for example, to include the `imq.system.max_count` property, specify `imq\\.system\\.max_count` in the set subcommand.

Note – You can also set broker properties in the JMS service configuration. If you set the same broker property in both the JMS host and the JMS service configuration, the value specified in the JMS host is used.

Example 16-3 Updating a JMS Host

This example changes the value of the `host` attribute of the JMS host `default_JMS_Host`. By default this value is `localhost`.

```
asadmin> set configs.config.server-config.jms-service.jms-host.default_JMS_host.host=
"server1.middleware.example.com"
```

▼ To Delete a JMS Host

Use the `delete-jms-host` subcommand in remote `asadmin` mode to delete a JMS host from the JMS service. If you delete the only JMS host, the JMS service will not be able to start until you create a new JMS host.

- 1 **Ensure that the server is running.**
Remote `asadmin` subcommands require a running server.
- 2 **List the JMS hosts by using the `list-jms-hosts(1)` subcommand.**
- 3 **Delete a JMS host by using the `delete-jms-host(1)` subcommand.**

Example 16-4 Deleting a JMS Host

This example deletes a JMS host named `MyNewHost`.

```
asadmin> delete-jms-host MyNewHost
Command delete-jms-host executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-jms-host` at the command line.

Administering JMS Connection Factories and Destinations

The JMS API uses two kinds of administered objects. *Connection factory objects* allow an application to create other JMS objects programmatically. *Destination objects* serve as repositories for messages. How these objects are created is specific to each implementation of JMS. In GlassFish Server, JMS is implemented by performing the following tasks:

- Creating a connection factory
- Creating a destination, which requires creating a physical destination and a destination resource that refers to the physical destination

JMS applications use the Java Naming and Directory Interface (JNDI) API to access the connection factory and destination resources. A JMS application normally uses at least one connection factory and at least one destination. By studying the application or consulting with the application developer, you can determine what resources must be created. The order in which the resources are created does not matter.

GlassFish Server provides the following types of connection factory objects:

- `QueueConnectionFactory` objects, used for point-to-point communication
- `TopicConnectionFactory` objects, used for publish-subscribe communication
- `ConnectionFactory` objects, which can be used for both point-to-point and publish-subscribe communications (recommended for new applications)

GlassFish Server provides the following types of destination objects:

- Queue objects, used for point-to-point communication
- Topic objects, used for publish-subscribe communication

The following topics are addressed here:

- [“To Create a Connection Factory or Destination Resource” on page 329](#)
- [“To List JMS Resources” on page 331](#)
- [“To Delete a Connection Factory or Destination Resource” on page 331](#)

The subcommands in this section can be used to administer both the connection factory resources and the destination resources. For information on JMS service support of connection pooling and failover, see “Connection Failover” in *GlassFish Server Open Source Edition 3.1 High Availability Administration Guide*. For instructions on administering physical destinations, see [“Administering JMS Physical Destinations” on page 332](#).

▼ To Create a Connection Factory or Destination Resource

For each JMS connection factory that you create, GlassFish Server creates a connector connection pool and connector resource. For each JMS destination that you create, GlassFish Server creates a connector admin object resource. If you delete a JMS resource, GlassFish Server automatically deletes the connector resources.

Use the `create-jms-resource` command in remote `asadmin` mode to create a JMS connection factory resource or a destination resource.

Tip – To specify the `addresslist` property (in the format `host:mqport,host2:mqport,host3:mqport`) for the `asadmin create-jms-resource` command, escape the `:` by using `\\`. For example, `host1\\:mqport,host2\\:mqport,host3\\:mqport`. For more information about using escape characters, see the `asadmin(1M)` concepts page.

To update a JMS connection factory, use the `set` subcommand for the underlying connector connection pool. See [“To Update a Connector Connection Pool” on page 277](#).

To update a destination, use the `set` subcommand for the admin object resource. See [“To Update an Administered Object” on page 291](#).

1 Ensure that the server is running.

Remote `asadmin` subcommands require a running server.

2 Create a JMS resource by using the `create-jms-resource(1)` command.

Information about the properties for the subcommand is included in this help page.

3 (Optional) If needed, restart the server.

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 16–5 Creating a JMS Connection Factory

This example creates a connection factory resource of type `javax.jms.ConnectionFactory` whose JNDI name is `.jms/DurableConnectionFactory`. The `ClientId` property sets a client ID on the connection factory so that it can be used for durable subscriptions. The JNDI name for a JMS resource customarily includes the `./` naming subcontext.

```
asadmin> create-jms-resource --restype javax.jms.ConnectionFactory
--description "connection factory for durable subscriptions"
--property ClientId=MyID ./DurableConnectionFactory
Command create-jms-resource executed successfully.
```

Example 16–6 Creating a JMS Destination

This example creates a destination resource whose JNDI name is `./MyQueue`.

```
asadmin> create-jms-resource --restype javax.jms.Queue
--property Name=PhysicalQueue ./MyQueue
Command create-jms-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-jms-resource` at the command line.

▼ To List JMS Resources

Use the `list-jms-resources` subcommand in remote `asadmin` mode to list the existing connection factory and destination resources.

- 1 **Ensure that the server is running.**
Remote `asadmin` subcommands require a running server.
- 2 **List the existing JMS resources by using the `list-jms-resources(1)` subcommand.**

Example 16–7 Listing All JMS Resources

This example lists all the existing JMS connection factory and destination resources.

```
asadmin> list-jms-resources
jms/Queue
jms/ConnectionFactory
jms/DurableConnectionFactory
jms/Topic
Command list-jms-resources executed successfully
```

Example 16–8 Listing a JMS Resources of a Specific Type

This example lists the resources for the resource type `javax.jms.TopicConnectionFactory`.

```
asadmin> list-jms-resources --restype javax.jms.TopicConnectionFactory
jms/DurableTopicConnectionFactory
jms/TopicConnectionFactory
Command list-jms-resources executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-jms-resources` at the command line.

▼ To Delete a Connection Factory or Destination Resource

Use the `delete-jms-resource` subcommand in remote `asadmin` mode to remove the specified connection factory or destination resource.

Before You Begin Ensure that you remove all references to the specified JMS resource before running this subcommand.

- 1 **Ensure that the server is running.**
Remote `asadmin` subcommands require a running server.

- 2 List the existing JMS resources by using the `list-jms-resources(1)` subcommand.
- 3 Delete the JMS resource by using the `delete-jms-resource(1)` subcommand.

Example 16–9 Deleting a JMS Resource

This example deletes the `.jms/Queue` resource.

```
asadmin> delete-jms-resource .jms/Queue
Command delete-jms-resource executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-jms-resource` at the command line.

Administering JMS Physical Destinations

Messages are delivered for routing and delivery to consumers by using *physical destinations* in the JMS provider. A physical destination is identified and encapsulated by an administered object (such as a `Topic` or `Queue` destination resource) that an application component uses to specify the destination of messages it is producing and the source of messages it is consuming. For instructions on configuring a destination resource, see [“To Create a Connection Factory or Destination Resource” on page 329](#).

If a message-driven bean is deployed and the physical destination it listens to does not exist, GlassFish Server automatically creates the physical destination and sets the value of the `maxNumActiveConsumers` property to `-1`. However, it is good practice to create the physical destination beforehand. The first time that an application accesses a destination resource, Message Queue automatically creates the physical destination specified by the `Name` property of the destination resource. This automatically created physical destination is temporary and expires after a period specified by a Message Queue configuration property, provided that there are no messages in it and no message producers or consumers connected to it.

The following topics are addressed here:

- [“To Create a JMS Physical Destination” on page 332](#)
- [“To List JMS Physical Destinations” on page 333](#)
- [“To Purge Messages From a Physical Destination” on page 334](#)
- [“To Delete a JMS Physical Destination” on page 334](#)

▼ To Create a JMS Physical Destination

For production purposes, always create physical destinations. During the development and testing phase, however, this step is not required. Use the `create-jmsdest` subcommand in remote `asadmin` mode to create a physical destination.

Because a physical destination is actually a Message Queue object rather than a server object, you use Message Queue broker commands to update properties. For information on Message Queue properties, see *Open Message Queue 4.5 Administration Guide*.

- 1 **Ensure that the server is running.**

Remote `asadmin` subcommands require a running server.

- 2 **Create a JMS physical destination by using the `create-jmsdest(1)` subcommand.**

Information about the properties for the subcommand is included in this help page.

- 3 **(Optional) If needed, restart the server.**

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 16–10 Creating a JMS Physical Destination

This example creates a queue named `PhysicalQueue`.

```
asadmin> create-jmsdest --desttype queue --property
User=public:Password=public PhysicalQueue
Command create-jmsdest executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-jmsdest` at the command line.

▼ To List JMS Physical Destinations

Use the `list-jmsdest` subcommand in remote `asadmin` mode to list the existing JMS physical destinations.

- 1 **Ensure that the server is running.**

Remote `asadmin` subcommands require a running server.

- 2 **List the existing JMS physical destinations by using the `list-jmsdest(1)` subcommand.**

Example 16–11 Listing JMS Physical Destinations

This example lists the physical destinations for the default server instance.

```
asadmin> list-jmsdest
PhysicalQueue queue {}
PhysicalTopic topic {}
Command list-jmsdest executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-jmsdest` at the command line.

▼ To Purge Messages From a Physical Destination

Use the `flush-jmsdest` subcommand in remote `asadmin` mode to purge the messages from a physical destination in the specified target's JMS service configuration.

- 1 Ensure that the server is running.**

Remote `asadmin` subcommands require a running server.

- 2 Purge messages from the a JMS physical destination by using the `flush-jmsdest(1)` subcommand.**

- 3 (Optional) If needed, restart the server.**

Some properties require server restart. See [“Configuration Changes That Require Restart” on page 40](#). If your server needs to be restarted, see [“To Restart a Domain” on page 116](#).

Example 16–12 Flushing Messages From a JMS Physical Destination

This example purges messages from the queue named `PhysicalQueue`.

```
asadmin> flush-jmsdest --desttype queue PhysicalQueue
Command flush-jmsdest executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help flush-jmsdest` at the command line.

▼ To Delete a JMS Physical Destination

Use the `delete-jmsdest` subcommand in remote `asadmin` mode to remove the specified JMS physical destination.

- 1 Ensure that the server is running.**

Remote `asadmin` subcommands require a running server.

- 2 List the existing JMS physical destinations by using the `list-jmsdest(1)` subcommand.**

3 Delete the physical resource by using the `delete-jmsdest(1)` subcommand.

Example 16–13 Deleting a Physical Destination

This example deletes the queue named `PhysicalQueue`.

```
asadmin> delete-jmsdest --desttype queue PhysicalQueue
Command delete-jmsdest executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-jmsdest` at the command line.

Special Situations When Using the JMS Service

As mentioned earlier, Message Queue, through the built-in `jmsra` resource adapter, is tightly integrated with GlassFish Server to provide JMS messaging managed through a rich set of `asadmin` subcommands and Administration Console pages to simplify JMS messaging administration tasks. In most instances, this tight integration is transparent and automatic, requiring no special effort on the part of an administrator. In certain special situations, though, an administrator must perform a task such as setting a Message Queue broker property or a GlassFish object attribute to enable or disable a capability of the integration. The topics in this section describe these situations.

Restarting an Embedded or Local Broker That Has Failed

Because the JMS service, not Message Queue, manages the lifecycle of brokers acting as Embedded and Local JMS hosts, do not use the `imqbrokerd` Message Queue utility to start such a broker that has failed. Instead, restart the GlassFish instance that the broker is servicing.

Changing the Admin User Password for an Embedded or Local Broker

Follow these steps to change the admin user password for an Embedded or Local broker:

1. Make sure the broker is running.
2. Use the `imqusermgr` Message Queue utility to change the password of the admin user.
3. Edit the configuration of the JMS host, changing the password of the admin user to the new password.
4. Restart the GlassFish instance that the broker is servicing.

When changing the password for the brokers in a broker cluster, first perform steps 1 and 2 on each broker. Then, perform step 3. Finally, perform step 4 on each broker.

Using SSL to Connect to an Oracle Internet Directory (OID) or Oracle Virtual Directory (OVD) User Repository

When using SSL to connect to an OID or OVD user repository, you must set the `imq.user_repository.ldap.ssl.socketfactory` Message Queue broker property to

```
com.sun.enterprise.security.auth.realm.ldap.CustomSocketFactory.
```

Troubleshooting the JMS Service

If you encounter problems, consider the following:

- Use the `jms-ping(1)` subcommand to confirm that the Message Queue broker is running.
- View the GlassFish Server log file. For server, the Domain Administrations Server (DAS), the log is available at *domain-dir/logs/server.log*; for other GlassFish instances, the log is available at *as-install/nodes/node-name/instance-name/logs/server.log*.
If the log file indicates that a Message Queue broker acting as a Remote JMS host did not respond to a message, stop the broker and then restart it.
- View the broker log. For a broker associated with the Domain Administration Server (DAS), the log is available at *domain-dir/imq/instances/imqbroker/log/log.txt*; for brokers associated with other GlassFish instances, the log is available at *as-install/nodes/node-name/instance-name/imq/instances/mq-instance-name/log/log.txt*.
- For Remote type JMS hosts, be sure to start Message Queue brokers first, then GlassFish Server instances.
- If all Message Queue brokers are down, it can take up to 30 minutes for GlassFish Server to go down or up when you are using the default values in JMS. You can change the default values for this timeout. For example:

```
asadmin set domain1.jms-service.reconnect-interval-in-seconds=5
```

Using the Generic Resource Adapter for JMS to Integrate Supported External JMS Providers

GlassFish Server supports the integration and use of Oracle WebLogic JMS and IBM WebSphere MQ JMS providers through the use of the Generic Resource Adapter for JMS (GenericJMSRA), which is available as an Add-On in the Administration Console's Update Tool. This Java EE connector 1.5 resource adapter can wrap the JMS client library of Oracle WebLogic JMS and IBM WebSphere MQ and make it available for use by GlassFish. The adapter is a .rar archive that can be deployed and configured using GlassFish Server administration tools.

The following topics are addressed here:

- [“Configuring GenericJMSRA for Supported External JMS Providers” on page 337](#)
- [“Using GenericJMSRA with WebLogic JMS” on page 344](#)
- [“Using GenericJMSRA with IBM WebSphere MQ” on page 357](#)

Configuring GenericJMSRA for Supported External JMS Providers

GenericJMSRA has three main properties that need to be configured: `SupportXA`, `DeliveryType`, and `ProviderIntegrationMode`. The values that need to be set for them depends on the capabilities of the JMS provider being used, as follows:

- `SupportXA` — indicates whether the JMS provider supports XA or not.
- `DeliveryType` — indicates whether an MDB should use a `ConnectionConsumer` or `Consumer.receive()` when consuming messages.
- `ProviderIntegrationMode` — indicates what mode of integration is required. The available integration modes are *jndi* and *javabean*. Some JMS providers support only one integration mode while others may offer the choice of both
 - If *jndi* is specified, then the resource adapter will obtain JMS connection factories and destinations from the JMS provider's JNDI repository.
 - If *javabean* is specified then the resource adapter will obtain JMS connection factories and destinations by instantiating the appropriate classes directly.

Which option is specified determines which other properties need to be set.

▼ To Deploy and Configure GenericJMSRA

Before deploying GenericJMSRA, JMS client libraries must be made available to GlassFish Server. For some JMS providers, client libraries might also include native libraries. In such cases, these native libraries must be made available to any GlassFish Server JVMs.

- 1 **Download the `genericra.rar` archive as an Add-On in the Administration Console's Update Tool.**
- 2 **Deploy GenericJMSRA the same way you would deploy a connector module.**
See “Deploying a Connector Module” in *GlassFish Server Open Source Edition 3.1 Application Deployment Guide*
- 3 **Configure the resource adapter's properties.**
See “GenericJMSRA Configuration Properties” on page 338.
- 4 **Create a connector connection pool.**
See “To Create a Connector Connection Pool” on page 275.
- 5 **Create a connector resource.**
See “To Create a Connector Resource” on page 278.

6 Create an administered object resource.

See [“To Create an Administered Object”](#) on page 290.

GenericJMSRA Configuration Properties

The following table describes the properties that can be set to when configuring the resource adapter.

<i>Property Name</i>	<i>Valid Values</i>	<i>Default Value</i>	<i>Description</i>
SupportsXA	true/false	false	Specifies whether the JMS client supports XA transactions.
DeliveryType	Synchronous/Asynchronous	Asynchronous	Specifies whether an MDB should use a <code>ConnectionConsumer</code> (Asynchronous) or <code>consumer.receive()</code> (Synchronous) when consuming messages.
QueueConnectionFactoryClassName	A valid class name	None	Class name of <code>javax.jms.QueueConnectionFactory</code> implementation of the JMS client. This class must be made available on the application server classpath. Used if <code>ProviderIntegrationMode</code> is <code>javabeen</code> .
TopicConnectionFactoryClassName	A valid class name	None	Class name of <code>javax.jms.TopicConnectionFactory</code> implementation of the JMS client. This class must be made available on the application server classpath. Used if <code>ProviderIntegrationMode</code> is specified as <code>javabeen</code> .
XAConnectionFactoryClassName	A valid class name	None	Class name of <code>javax.jms.ConnectionFactory</code> implementation of the JMS client. This class must be made available on the application server classpath. Used if <code>ProviderIntegrationMode</code> is specified as <code>javabeen</code> .

<i>Property Name</i>	<i>Valid Values</i>	<i>Default Value</i>	<i>Description</i>
<code>XAQueueConnectionFactoryClassName</code>	A valid class name	None	Class name of <code>javax.jms.XAQueueConnectionFactory</code> implementation of the JMS client. This class must be made available on the application server classpath. Used if <code>ProviderIntegrationMode</code> is specified as <code>javabeen</code> .
<code>XATopicConnectionFactoryClassName</code>	A valid class name	None	Class name of <code>javax.jms.XATopicConnectionFactory</code> implementation of the JMS client. This class must be made available on the application server classpath. Used if <code>ProviderIntegrationMode</code> is <code>javabeen</code> .
<code>TopicClassName</code>	A valid class name	None	Class Name of <code>javax.jms.Topic</code> implementation of the JMS client. This class must be made available on the application server classpath. Used if <code>ProviderIntegrationMode</code> is <code>javabeen</code> .
<code>QueueClassName</code>	A valid class name	None	Class Name of <code>javax.jms.Queue</code> implementation of the JMS client. This class must be made available on the application server classpath. Used if <code>ProviderIntegrationMode</code> is specified as a <code>javabeen</code> .
<code>ConnectionFactoryProperties</code>	Name value pairs separated by comma	None	Specifies the <code>javabeen</code> property names and values of the <code>ConnectionFactory</code> of the JMS client. Required only if <code>ProviderIntegrationMode</code> is <code>javabeen</code> .
<code>JndiProperties</code>	Name value pairs separated by comma	None	Specifies the JNDI provider properties to be used for connecting to the JMS provider's JNDI. Used only if <code>ProviderIntegrationMode</code> is <code>jndi</code> .

<i>Property Name</i>	<i>Valid Values</i>	<i>Default Value</i>	<i>Description</i>
CommonSetter MethodName	Method name	None	Specifies the common setter method name that some JMS vendors use to set the properties on their administered objects. Used only if <code>ProviderIntegrationMode</code> is <code>javabeen</code> . For example, in the case of Message Queue, this would be <code>setProperty</code> .
UserName	Name of the JMS user	None	User name to connect to the JMS Provider.
Password	Password for the JMS user	None	Password to connect to the JMS provider.
RMPolicy	ProviderManaged or OnePerPhysicalConnection	Provider Managed	<p>The <code>isSameRM</code> method on an <code>XAResource</code> is used by the Transaction Manager to determine if the Resource Manager instance represented by two <code>XAResources</code> are the same. When <code>RMPolicy</code> is set to <code>ProviderManaged</code> (the default value), the JMS provider is responsible for determining the <code>RMPolicy</code> and the <code>XAResource</code> wrappers in <code>GenericJMSRA</code> merely delegate the <code>isSameRM</code> call to the JMS provider's <code>XA</code> resource implementations. This should ideally work for most JMS providers.</p> <p>Some <code>XAResource</code> implementations such as WebSphere MQ rely on a resource manager per physical connection and this causes issues when there is inbound and outbound communication to the same queue manager in a single transaction (for example, when an MDB sends a response to a destination). When <code>RMPolicy</code> is set to <code>OnePerPhysicalConnection</code>, the <code>XAResource</code> wrapper implementation's <code>isSameRM</code> in <code>GenericJMSRA</code> would check if both the <code>XAResources</code> use the same physical connection, before delegating to the wrapped objects.</p>

Connection Factory Properties

ManagedConnectionFactory properties are specified when a connector - connection - pool is created. All the properties specified while creating the resource adapter can be overridden in a ManagedConnectionFactory. Additional properties available only in ManagedConnectionFactory are given below.

Property Name	Valid Value	Default Value	Description
ClientId	A valid client ID	None	ClientId as specified by JMS 1.1 specification.
ConnectionFactoryJndiName	JNDI Name	None	JNDI name of the connection factory bound in the JNDI tree of the JMS provider. The administrator should provide all connection factory properties (except clientId) in the JMS provider itself. This property name will be used only if ProviderIntegratinMode is jndi.
ConnectionValidationEnabled	true/false	false	If set to true, the resource adapter will use an exception listener to catch any connection exception and will send a CONNECTION_ERROR_OCCURED event to application server.

Destination Properties

Properties in this section are specified when a destination (queue or topic) is created. All the resource adapter properties can be overridden in a destination. Additional properties available only in the destination are given below.

Property Name	Valid Value	Default Value	Description
DestinationJndiName	JNDI Name	None	JNDI name of the destination bound in the JNDI tree of the JMS provider. The Administrator should provide all properties in the JMS provider itself. This property name will be used only if ProviderIntegrationMode is jndi.
DestinationProperties	Name value pairs separated by a comma	None	Specifies the javabeen property names and values of the destination of the JMS client. Required only if ProviderIntegrationMode is javabeen.

Activation Spec Properties

Properties in this section are specified in the GlassFish Server `glassfish-ejb-jar.xml` deployment descriptor of an MDB as `activation-config-properties`. All the resource adapter properties can be overridden in an Activation Spec. Additional properties available only in `ActivationSpec` are given below.

<i>Property Name</i>	<i>Valid Value</i>	<i>Default Value</i>	<i>Description</i>
MaxPoolSize	An integer	8	Maximum size of server session pool internally created by the resource adapter for achieving concurrent message delivery. This should be equal to the maximum pool size of MDB objects.
MaxWaitTime	An integer	3	The resource adapter will wait for the time in seconds specified by this property to obtain a server session from its internal pool. If this limit is exceeded, message delivery will fail.
SubscriptionDurability	Durable or Non-Durable	Non-Durable	SubscriptionDurability as specified by JMS 1.1 specification.
SubscriptionName		None	SubscriptionName as specified by JMS 1.1 specification.
MessageSelector	A valid message selector	None	MessageSelector as specified by JMS 1.1 specification.
ClientID	A valid client ID	None	ClientID as specified by JMS 1.1 specification.
ConnectionFactoryJndiName	A valid JNDI Name	None	JNDI name of connection factory created in JMS provider. This connection factory will be used by resource adapter to create a connection to receive messages. Used only if <code>ProviderIntegrationMode</code> is configured as <code>jndi</code> .
DestinationJndiName	A valid JNDI Name	None	JNDI name of destination created in JMS provider. This destination will be used by resource adapter to create a connection to receive messages from. Used only if <code>ProviderIntegrationMode</code> is configured as <code>jndi</code> .

<i>Property Name</i>	<i>Valid Value</i>	<i>Default Value</i>	<i>Description</i>
DestinationType	javax.jms.Queue or javax.jms.Topic	Null	Type of the destination the MDB will listen to.
Destination Properties	Name-value pairs separated by comma	None	Specifies the javabeen property names and values of the destination of the JMS client. Required only if ProviderIntegrationMode is javabeen.
RedeliveryAttempts	integer		Number of times a message will be delivered if a message causes a runtime exception in the MDB.
RedeliveryInterval	time in seconds		Interval between repeated deliveries, if a message causes a runtime exception in the MDB.
SendBadMessages ToDMD	true/false	False	Indicates whether the resource adapter should send the messages to a dead message destination, if the number of delivery attempts is exceeded.
DeadMessage Destination JndiName	a valid JNDI name.	None	JNDI name of the destination created in the JMS provider. This is the target destination for dead messages. This is used only if ProviderIntegrationMode is jndi.
DeadMessage Destination ClassName	class name of destination object.	None	Used if ProviderIntegrationMode is javabeen.
DeadMessage Destination Properties	Name Value Pairs separated by comma	None	Specifies the javabeen property names and values of the destination of the JMS client. This is required only if ProviderIntegrationMode is javabeen.
DeadMessage Connection FactoryJndiName	a valid JNDI name	None	JNDI name of the connection factory created in the JMS provider. This is the target connection factory for dead messages. This is used only if ProviderIntegrationMode is jndi.
DeadMessage DestinationType	queue or topic destination	None	The destination type for dead messages.

Property Name	Valid Value	Default Value	Description
ReconnectAttempts	integer	0	Number of times a reconnect will be attempted in case exception listener catches an error on connection.
ReconnectInterval	time in seconds	0	Interval between reconnects.

Using GenericJMSRA with WebLogic JMS

You can configure GenericJMSRA to enable applications running in GlassFish Server to send messages to, and receive messages from, Oracle WebLogic JMS.

GenericJMSRA should be used in conjunction with the WebLogic Server Thin T3 Client. Due to the nature of this client, messages exchanged between GlassFish Server and WebLogic Server cannot be sent or received in XA transactions. There is also only limited support for asynchronous receipt of messages in an MDB, as described in detail in [“Limitations When Using GenericJMSRA with WebLogic JMS” on page 351](#).

The following topics are addressed here:

- [“Deploy the WebLogic Thin T3 Client JAR in GlassFish Server” on page 344](#)
- [“Configure WebLogic JMS Resources for Integration” on page 345](#)
- [“Create a Resource Adapter Configuration for GenericJMSRA to Work With WebLogic JMS” on page 345](#)
- [“Deploy the GenericJMSRA Resource Archive” on page 346](#)
- [“Configuring an MDB to Receive Messages from WebLogic JMS” on page 347](#)
- [“Accessing Connections and Destinations Directly” on page 348](#)
- [“Limitations When Using GenericJMSRA with WebLogic JMS” on page 351](#)
- [“Configuration Reference of GenericJMSRA Properties for WebLogic JMS” on page 353](#)

Deploy the WebLogic Thin T3 Client JAR in GlassFish Server

WebLogic Server provides several different clients for use by standalone applications that run outside of WebLogic Server. These client are summarized in [Overview of Stand-alone Clients](#) in *Programming Stand-alone Clients for Oracle WebLogic Server*. When connecting from GlassFish Server to WebLogic JMS resources you must use the WebLogic Thin T3 client, `wlthint3client.jar`.

There are a couple of methods to deploy the WebLogic Thin T3 client in GlassFish Server and make it available to GenericJMSRA:

- To make the Thin T3 client available to all applications, copy the `wlthint3client.jar` to the `as-install/lib` directory under your GlassFish Server installation. The Thin T3 client can be found in a WebLogic Server installation in a directory similar to `MW_HOME/server/lib`.

- It is also possible to deploy the Thin T3 client in a less global manner, so that it is specific to an individual application. For information on how to do this, see “Application-Specific Class Loading” in *GlassFish Server Open Source Edition 3.1 Application Development Guide*.

Configure WebLogic JMS Resources for Integration

If you need to configure the necessary WebLogic JMS resources on the WebLogic Server from which you want to access messages using GlassFish Server, then follow the instructions in the WebLogic Server documentation for configuring the necessary resources, such as destinations, and connection factories.

- JMS System Module Configuration
- Queue and Topic Destination Configuration
- Connection Factory Configuration

The example code snippets in this section refer to a WebLogic JMS connection factory named `WLoutboundQueueFactory` and queue destination named `WLoutboundQueue`. For conceptual overviews on configuring WebLogic JMS resources, refer to [Understanding JMS Resource Configuration](#) in *Configuring and Managing JMS for Oracle WebLogic Server*. For detailed instructions on configuring WebLogic JMS resources, refer to [Configure JMS system modules and add JMS resources](#) in the WebLogic Administration Console Online Help.

Create a Resource Adapter Configuration for GenericJMSRA to Work With WebLogic JMS

When you deploy GenericJMSRA, you also need to create a resource adapter configuration in GlassFish Server. You can do this using either the Administration Console or the `asadmin` command. If you use the Administration Console then you need deploy the GenericJMSRA resource archive first. Here's an example using `asadmin`:

```
asadmin create-resource-adapter-config --host localhost --port 4848
--property SupportsXA=false:DeliveryType=Synchronous:ProviderIntegrationMode
=jndi:JndiProperties=java.naming.factory.initial\
=weblogic.jndi.WLInitialContextFactory,java.naming.provider.url\
=t3\://localhost:7001,java.naming.factory.url.pkgs\
=weblogic.corba.client.naming genericra
```

This creates a resource adapter configuration with the name `genericra`, and Oracle recommends not changing the default name. The resource adapter configuration is configured with the properties specified using the `--properties` argument; multiple properties are configured as a colon-separated list of name-value pairs that are entered as a single line. You will also need to change the host and port that WebLogic Server is running on to suit your installation.

In this example, the following properties are configured:

Property	Value
SupportsXA	false
DeliveryType	Synchronous
ProviderIntegration Mode	jndi
JndiProperties	<code>java.naming.factory.initial =weblogic.jndi.WLInitialContextFactory,java.naming.provider.url =t3://localhost:7001,java.naming.factory.url.pkgs =weblogic.corba.client.naming</code> (replace " localhost:7001 " with the host:port of WebLogic Server)

You must use the same values for `SupportsXA`, `DeliveryType` and `ProviderIntegrationMode` as the required values that are used in this table. The `JndiProperties` value must be set to a list of JNDI properties needed for connecting to WebLogic JNDI.

Note – When using `asadmin` you need to escape each `=` and any `:` characters by prepending a backward slash `\`. The escape sequence is not necessary if the configuration is performed through the Administration Console.

For a description of all the resource adapter properties that are relevant for WebLogic JMS, see the [“Configuration Reference of GenericJMSRA Properties for WebLogic JMS” on page 353](#).

▼ Deploy the GenericJMSRA Resource Archive

The supported version of the GenericJMSRA resource archive is available as an Add-On in the Administration Console's Update Tool.

- 1 **Download the GenericJMSRA resource archive (genericra.rar) using the Administration Console's Update Tool.**
- 2 **Deploy the resource adapter. You can do this using either the Administration Console or the `asadmin` deploy command. Here's an example using the `asadmin` deploy command:**

```
$ asadmin deploy --user admin --password adminadmin  
  <location of the generic resource adapter rar file>
```

If you deploy the resource adapter using the Administration Console, then after deployment you need to create a resource adapter configuration as described in [“Create a Resource Adapter Configuration for GenericJMSRA to Work With WebLogic JMS” on page 345](#).

▼ Configuring an MDB to Receive Messages from WebLogic JMS

In this example, all configuration information is defined in two deployment descriptor files: `ejb-jar.xml` and the GlassFish Server `glassfish-ejb-jar.xml` file. To configure a MDB to receive messages from WebLogic JMS, you would configure these deployment descriptor files as follows:

1 Configure the `ejb-jar.xml` deployment descriptor:

```
<ejb-jar>
  <enterprise-beans>
    <message-driven>
      <ejb-name>SimpleMessageEJB</ejb-name>
      <ejb-class>test.simple.queue.ejb.SimpleMessageBean</ejb-class>
      <transaction-type>Container</transaction-type>
    </message-driven>
  </enterprise-beans>
  <assembly-descriptor>
    <container-transaction>
      <method>
        <ejb-name>SimpleMessageEJB</ejb-name>
        <method-name>onMessage</method-name>
        <method-params>
          <method-param>javax.jms.Message</method-param>
        </method-params>
      </method>
      <trans-attribute>NotSupported</trans-attribute>
    </container-transaction>
  </assembly-descriptor>
</ejb-jar>
```

Note – If container-managed transactions are configured, then the transactional attribute must be set to `NotSupported`. For more information, see [“Limitations When Using GenericJMSRA with WebLogic JMS” on page 351](#).

2 Configure the `glassfish-ejb-jar.xml` deployment descriptor:

```
<sun-ejb-jar>
  <enterprise-beans>
    <ejb>
      <ejb-name>SimpleMessageEJB</ejb-name>
      <mdb-resource-adapter>
        <resource-adapter-mid>genericcra</resource-adapter-mid>
        <activation-config>
          <activation-config-property>
            <activation-config-property-name>
              ConnectionFactoryJndiName
            </activation-config-property-name>
            <activation-config-property-value>
              jms/WLInboundQueueFactory
            </activation-config-property-value>
          </activation-config-property>
          <activation-config-property>
            <activation-config-property-name>
              DestinationJndiName
            </activation-config-property-name>
            <activation-config-property-value>
              jms/WLInboundQueueFactory
            </activation-config-property-value>
          </activation-config-property>
        </activation-config>
      </mdb-resource-adapter>
    </ejb>
  </enterprise-beans>
</sun-ejb-jar>
```

```
        </activation-config-property-name>
        <activation-config-property-value>
            jms/WLInboundQueue
        </activation-config-property-value>
    </activation-config-property>
</activation-config>
</mdb-resource-adapter>
</ejb>
</enterprise-beans>
</sun-ejb-jar>
```

where:

The `<resource-adapter-mid>genericra</resource-adapter-mid>` element is used to specify the resource adapter and resource adapter configurations that was deployed in the [“Create a Resource Adapter Configuration for GenericJMSRA to Work With WebLogic JMS” on page 345](#) instructions. It is recommended you stick to `genericra` as is used here.

The `activation-config` element in `glassfish-ejb-jar.xml` is the one which defines how and where the MDB receives messages, as follows:

- The `ConnectionFactoryJndiName` property must be set to the JNDI name of the connection factory in the WebLogic JNDI store that will be used to receive messages. Therefore, replace `.jms/WLInboundQueueFactory` in the example above with the JNDI name used in your environment.
- The `DestinationJndiName` property must be set to the JNDI name of the destination (the queue or topic from which messages will be consumed) in the WebLogic JNDI store. Therefore, replace `.jms/WLInboundQueue` in the example above with the JNDI name used in your environment.

For a description of all the `ActivationSpec` properties that are relevant for WebLogic JMS, see the [“Configuration Reference of GenericJMSRA Properties for WebLogic JMS” on page 353](#).

Make sure to use the appropriate WebLogic administration tools, such as the WebLogic Administration Console or the WebLogic Scripting Tool (WLST). For more information, see [Configure Messaging](#) in the *WebLogic Server Administration Console Online Help* and the [WebLogic Server WLST Online and Offline Command Reference](#).

▼ Accessing Connections and Destinations Directly

When configuring a MDB to consume messages from WebLogic JMS your code does not need to access the WebLogic JMS connection factory and destination directly. You simply define them in the activation configuration, as shown in [“Configuring an MDB to Receive Messages from WebLogic JMS” on page 347](#). However when configuring an MDB to send messages, or when configuring a EJB, Servlet, or application client to either send or receive messages, your code needs to obtain these objects using a JNDI lookup.

Note – If you want configure connections and destination resources using the Administration Console, this is explained in the Administration Console online help. When using Administration Console, follow the instructions for creating a new **Connector Connection Pool** and **Admin Object Resources**, and not the instructions for creating a JMS Connection Pool and Destination Resources. For more information about using `asadmin` to create these resources, see [“To Create a Connector Connection Pool” on page 275](#) and [“To Create a Connector Resource” on page 278](#).

1 Looking up the connection factory and destination

The following code looks up a connection factory with the JNDI name `jms/QCFactory` and a queue with the name `jms/outboundQueue` from the GlassFish Server JNDI store:

```
Context initialContext = new InitialContext();
QueueConnectionFactory queueConnectionFactory = (QueueConnectionFactory)
    jndiContext.lookup("java:comp/env/jms/MyQCFactory");
Queue queue = (Queue) jndiContext.lookup("java:comp/env/jms/outboundQueue");
```

Note that the resources used are GlassFish Server resources, not WebLogic JMS resources. For every connection factory or destination that you want to use in the WebLogic JMS JNDI store, you need to create a corresponding connection factory or destination in the GlassFish Server JNDI store and configure the GlassFish Server object to point to the corresponding WebLogic JMS object.

2 Declaring the connection factory and destination

In accordance with standard Java EE requirements, these resources need to be declared in the deployment descriptor for the MDB, EJB or other component. For example, for a session bean, configure the `ejb-jar.xml` with `<resource-env-ref>` elements, as follows:

```
<ejb-jar>
  <enterprise-beans>
    <session>
      .
      .
      .
      <resource-env-ref>
        <resource-env-ref-name>jms/QCFactory</resource-env-ref-name>
        <resource-env-ref-type>javax.jms.QueueConnectionFactory</resource-env-ref-type>
      </resource-env-ref>
      <resource-env-ref>
        <resource-env-ref-name>jms/outboundQueue</resource-env-ref-name>
        <resource-env-ref-type>javax.jms.Queue</resource-env-ref-type>
      </resource-env-ref>
```

3 Create a Connector Connection Pool and Connector Resource by entering the following `asadmin` commands, both all in one line:

In order to configure a JMS Connection Factory using GenericJMSRA, a Connector connection pool and resource need to be created in GlassFish Server using names that map to the corresponding connection factory in the WebLogic JNDI store.

```
asadmin create-connector-connection-pool --host localhost --port 4848
--raname genericra --connectiondefinition javax.jms.QueueConnectionFactory
--target server --transactionsupport LocalTransaction
```

```
--property ConnectionFactoryJndiName=jms/WLOutboundQueueFactory
qcpool

asadmin create-connector-resource --host localhost --port 4848
--poolname qcpool --target server jms/QCFactory
```

These `asadmin` commands together creates a connection factory in GlassFish Server and its corresponding connection pool.

- The connection pool has the JNDI name `jms/WLOutboundQueueFactory` and obtains connections from a connection pool named `qcpool`.
- The connection pool `qcpool` uses the resource adapter `genericra` and contains objects of type `javax.jms.QueueConnectionFactory`.
- The `transactionsupport` argument is set to `LocalTransaction`, which specifies that the connection will be used in local transactions only. You can also specify `NoTransaction`. However, the default setting of `XATransaction` cannot be used. For more information, see [“Limitations When Using GenericJMSRA with WebLogic JMS” on page 351](#).
- The connection pool is configured with the properties specified using the `properties` argument; multiple properties are configured as a colon-separated list of name-value pairs. Only one property is configured in this example, as follows:

```
ConnectionFactoryJndiName=jms/WLOutboundQueueFactory
```

The `ConnectionFactoryJndiName` property *must* be set to the JNDI name of the corresponding connection factory in the WebLogic JMS JNDI store. Therefore, replace `jms/WLOutboundQueueFactory` in the example above with the JNDI name used in your environment.

- For a description of the `ManagedConnectionFactory` properties that are relevant for WebLogic JMS, see the [“Configuration Reference of GenericJMSRA Properties for WebLogic JMS” on page 353](#).

4 Create a destination object that refers to a corresponding WebLogic JMS destination by entering the following `asadmin` command, all in one line:

```
asadmin create-admin-object --host localhost --port 4848 --target server
--restype javax.jms.Queue --property DestinationJndiName=jms/WLOutboundQueue
--raname genericra jms/outboundQueue
```

This `asadmin` command creates a destination in GlassFish Server.

- The destination has the JNDI name `jms/outboundQueue`, uses the resource adapter `genericra`, and is of type `javax.jms.Queue`.
- The destination is configured with the properties specified using the `properties` argument; multiple properties are configured as a colon-separated list of name-value pairs. Only one property is configured in this example, as follows:

```
DestinationJndiName=jms/WLOutboundQueue
```

The `DestinationJndiName` property *must* be set to the JNDI name of the corresponding destination in the WebLogic JMS JNDI store. Therefore, replace `jms/WLOutboundQueue` in the example above with the JNDI name used in your environment.

- For a description of the destination properties that are relevant for WebLogic JMS, see the [“Configuration Reference of GenericJMSRA Properties for WebLogic JMS”](#) on page 353.

Limitations When Using GenericJMSRA with WebLogic JMS

Due to the nature of the WebLogic T3 Thin Client there are a number of limitations in the way in which it can be used with GenericJMSRA.

No Support for XA Transactions

WebLogic JMS does not support the optional JMS "Chapter 8" interfaces for XA transactions in a form suitable for use outside of WebLogic Server. Therefore, the GenericJMSRA configuration must have the `SupportsXA` property set to `false`. This has a number of implications for the way in which applications may be used, as described in this section.

Using a MDB to Receive Messages: Container-managed Transactions (CMT)

- If container-managed transactions are used, the transactional attribute of a MDB should be set to `NotSupported`. No transaction will be started. Messages will be received in a non-transacted session with an *acknowledgeMode* of `AUTO_ACKNOWLEDGE`.
- A transactional `Required` attribute should not be used; otherwise, MDB activation will fail with an exception: `javax.resource.ResourceException: MDB is configured to use container managed transaction. But SupportsXA is configured to false in the resource adapter.`

The remaining transactional attributes are normally considered inappropriate for use with a MDB. If used, the following behavior will occur:

- If the transactional attribute is `RequiresNew`, then MDB activation will fail with an exception: `javax.resource.ResourceException: MDB is configured to use container managed transaction But SupportsXA is configured to false in the resource adapter.`
- If the transactional attribute is `Mandatory`, the MDB can be activated but a `TransactionRequiredException` (or similar) will always be thrown by the server.
- If the transactional attribute is `Supports`, then no transaction will be started and the MDB will work as if `NotSupported` had been used.
- If the transactional attribute is `Never`, then no transaction will be started and the MDB will work as if `NotSupported` had been used.

Using a MDB to Receive Messages: Bean-managed Transactions (BMT)

- If bean-managed transactions are configured in accordance with the EJB specification any `UserTransaction` started by the bean will have no effect on the consumption of messages.

- Messages will be received in a non-transacted session with an *acknowledgeMode* of `AUTO_ACKNOWLEDGE`.

Accessing Connections and Destinations Directly - Container-managed Transactions (CMT)

When accessing connections directly (such as when sending messages from a MDB or an EJB) and container-managed transactions are being used, the connection pool's `transaction-support` property should be set to either `LocalTransaction` or `NoTransaction`. If the default value of `XATransaction` is used, an exception will be thrown at runtime when `createConnection()` is called. This is the case irrespective of the transactional attribute of the MDB or EJB. Note that MDBs must have their transactional attribute set to `NotSupported` as specified above; whereas, an EJB can use any transactional attribute.

If there is no transaction in progress within the bean method (for example, `notSupported` is being used) then it does not make any difference whether the connection pool's `transaction-support` property is set to `LocalTransaction` or `NoTransaction`; the transactional behavior will be determined by the arguments to `createSession()`. If you want the outbound message to be sent without a transaction, call `createSession(false, ...)`. If you want the outbound message to be sent in a local transaction call `createSession(true, Session.SESSION_TRANSACTED)`, remembering to call `session.commit()` or `session.rollback()` after the message is sent.

If there is a transaction in progress within the bean method (which will only be possible for EJBs), then setting the connection pool's `transaction-support` property to `LocalTransaction` or `NoTransaction` gives different results:

- If it is set to `NoTransaction` then a non-transacted session will be used.
- If it is set to `LocalTransaction` then a (local, non-XA) transacted session will be used, which will be committed or rolled back when the `UserTransaction` is committed or rolled back. In this case, calling `session.commit()` or `session.rollback()` will cause an exception.

No Support for Redelivery Limits and Dead Message Queue

Due to the lack of XA support when using WebLogic JMS, there is no support for GenericJMSRA's dead message queue feature, in which a message that has been redelivered to a MDB a defined number of times is sent to a dead message queue.

Limited Support for Asynchronous Receipt of Messages In a MDB

WebLogic JMS does not support the optional JMS "Chapter 8" interfaces for "Concurrent Processing of a Subscription's Messages" (that is, `ServerSession`, `ServerSessionPool` and `ConnectionConsumer`) in a form suitable for use outside of WebLogic Server. Therefore, the generic JMSRA configuration must set the property `DeliveryType` to `Synchronous`.

This affects the way in which MDBs consume messages from a queue or topic as follows:

- When messages are being received from a queue, each MDB instance will have its own session and consumer, and it will consume messages by repeatedly calling `receive(timeout)`. This allows the use of a pool of MDBs to process messages from the queue.
- When messages are being received from a topic, only one MDB instance will be used irrespective of the configured pool size. This means that a pool of multiple MDBs cannot be used to share the load of processing messages, which may reduce the rate at which messages can be received and processed.

This restriction is a consequence of the semantics of synchronously consuming messages from topics in JMS: In the case of non-durable topic subscriptions, each consumer receives a copy of all the messages on the topic, so using multiple consumers would result in multiple copies of each message being received rather than allowing the load to be shared among the multiple MDBs. In the case of durable topic subscriptions, only one active consumer is allowed to exist at a time.

Configuration Reference of GenericJMSRA Properties for WebLogic JMS

The tables in this section list the properties that need to be set to configure the resource adapter and any activation specs, managed connections, and other administered objects that are relevant only when using GenericJMSRA to communicate with WebLogic JMS. For a complete list of properties, see the comprehensive table in [“GenericJMSRA Configuration Properties” on page 338](#)

Resource Adapter Properties

These properties are used to configure the resource adapter itself when it is deployed, and can be specified using the `create-resource-adapter-config` command.

<i>Property Name</i>	<i>Required Value</i>	<i>Description</i>
SupportsXA	false	Specifies whether the JMS client supports XA transactions. Set to false for WebLogic JMS.
DeliveryType	Synchronous	Specifies whether an MDB should use a <code>ConnectionConsumer</code> (Asynchronous) or <code>consumer.receive()</code> (Synchronous) when consuming messages. Set to Synchronous for WebLogic JMS.

<i>Property Name</i>	<i>Required Value</i>	<i>Description</i>
ProviderIntegration Mode	jndi	Specifies that connection factories and destinations in GlassFish's JNDI store are configured to refer to connection factories and destinations in WebLogic's JNDI store. Set to jndi for WebLogic JMS.
JndiProperties	java.naming.factory.initial= =weblogic.jndi.WLInitialContextFactory, java.naming.provider.url= =t3://localhost:7001,java.naming.factory.url =weblogic.corba.client.naming (replace localhost:7001 with the host:port of WebLogic Server)	JNDI properties for connect to WebLogic JNDI, specified as comma-separated list of name=value pairs without spaces.
UserName	Name of the WebLogic JMS user	User name to connect to WebLogic JMS. The user name can be overridden in ActivationSpec and ManagedConnection. If no user name is specified anonymous connections will be used, if permitted.
Password	Password for the WebLogic JMS user	Password to connect to WebLogic JMS. The password can be overridden in ActivationSpec and ManagedConnection.
LogLevel	Desired log level of JDK logger	Used to specify the level of logging.

Connection Factory Properties

ManagedConnectionFactory objects are created in the GlassFish Server JNDI store using the Administration Console or the `asadmin connector-connection-pool` command. All the properties that can be set on a resource adapter configuration can be overridden by setting them on a destination object. The properties specific to ManagedConnectionFactory objects are listed in the following table.

<i>Property Name</i>	<i>Valid Value</i>	<i>Default Value</i>	<i>Description</i>
ClientId	A valid client ID	None	ClientId as specified by JMS 1.1 specification.
ConnectionFactoryJndiName	A valid JNDI Name	None	JNDI name of connection factory in the GlassFish Server JNDI store. This connection factory should be configured to refer to the physical connection factory in the WebLogic JNDI store.
ConnectionValidationEnabled	true or false	FALSE	If set to true, the resource adapter will use an exception listener to catch any connection exception and will send a CONNECTION_ERROR_OCCURED event to GlassFish Server.

Destination Properties

Destination (queue or topic) objects are created in the GlassFish Server JNDI store using the Administration Console or the `asadmin connector-admin-object` command. All the properties that can be set on a resource adapter configuration can be overridden by setting them on a destination object. The properties specific to destination objects are listed in the following table.

<i>Property Name</i>	<i>Valid Value</i>	<i>Default Value</i>	<i>Description</i>
DestinationJndiName	A valid JNDI name	None	JNDI name of the destination object in the GlassFish Server JNDI store. This destination object should be configured to refer to the corresponding physical destination in the WebLogic JNDI store.

ActivationSpec Properties

An `ActivationSpec` is a set of properties that configures a MDB. It is defined either in the MDB's GlassFish Server deployment descriptor `glassfish-ejb-jar.xml` using `activation-config-property` elements or in the MDB itself using annotation. All the resource adapter properties listed in the table above can be overridden in an `ActivationSpec`. Additional properties available only to a `ActivationSpec` are given below.

<i>Property Name</i>	<i>Valid Value</i>	<i>Default Value</i>	<i>Description</i>
MaxPoolSize	An integer	8	Maximum size of server session pool internally created by the resource adapter for achieving concurrent message delivery. This should be equal to the maximum pool size of MDB objects. Only used for queues; ignored for topics, when a value of 1 is always used.
SubscriptionDurability	Durable or Non-Durable	Non-Durable	Only used for topics. Specifies whether the subscription is durable or non-durable.
SubscriptionName		None	Only used for topics when SubscriptionDurability is Durable. Specifies the name of the durable subscription.
MessageSelector	A valid message selector	None	JMS message selector.
ClientID	A valid client ID	None	JMS ClientID.
ConnectionFactoryJndiName	A valid JNDI Name	None	JNDI name of connection factory in the GlassFish Server JNDI store. This connection factory should be configured to refer to the physical connection factory in the WebLogic JNDI store.
DestinationJndiName	A valid JNDI Name	None	JNDI name of destination in the GlassFish Server JNDI store. This destination should be configured to refer to the physical destination in the WebLogic JNDI store.
DestinationType	javax.jms.Queue or javax.jms.Topic	Null	Specifies whether the configured DestinationJndiName refers to a queue or topic.
ReconnectAttempts	integer	0	Number of times a reconnect will be attempted in case exception listener catches an error on connection.
ReconnectInterval	time in seconds	0	Interval between reconnection attempts.

Using GenericJMSRA with IBM WebSphere MQ

You can configure GenericJMSRA to enable applications running in GlassFish Server to send messages to, and receive messages from, IBM WebSphere MQ. GlassFish Server only supports using GenericJMSRA with WebSphere MQ version 6.0 and WebSphere MQ version 7.0

These instructions assume that the WebSphere MQ broker and GlassFish Server are deployed and running on the same physical host/machine. If you have the WebSphere MQ broker running on a different machine and need to access it remotely, refer to the WebSphere MQ documentation for configuration details. The resource adapter configuration and other application server related configuration remains unchanged.

The following topics are addressed here:

- [“Preliminary Setup Procedures for WebSphere MQ Integration” on page 357](#)
- [“Configure the WebSphere MQ Administered Objects” on page 358](#)
- [“Create a Resource Adapter Configuration for GenericJMSRA to Work With WebSphere MQ” on page 361](#)
- [“Deploy the GenericJMSRA Archive” on page 363](#)
- [“Create the Connection Factories and Administered Objects in GlassFish Server” on page 363](#)
- [“Configuring an MDB to Receive Messages from WebSphere MQ” on page 365](#)

Preliminary Setup Procedures for WebSphere MQ Integration

Before you can configure WebSphere MQ to exchange messages with GlassFish Server, you must complete the following tasks:

- The following permissions must be added to the `server.policy` and the `client.policy` file to deploy GenericJMSRA and to run the client application.
 - Use a text editor to modify the `server.policy` file in the `${appserver-install-dir}/domains/domain1/config/directory` by adding the following line to the default grant block:

```
permission java.util.logging.LoggingPermission "control";
permission java.util.PropertyPermission "*", "read,write";
```

- If you use an application client in your application, edit the client's `client.policy` file in the `${appserver-install-dir}/lib/appclient/` directory by adding the following permission:

```
permission javax.security.auth.PrivateCredentialPermission
"javax.resource.spi.security.PasswordCredential * \**\*", "read";
```

- To integrate GlassFish Server with WebSphere MQ 6.0 or 7.0, copy the necessary JAR files to the `as-install/lib` directory:
 - For WebSphere MQ 6.0, copy these JAR files to the `as-install/lib` directory:

```
/opt/mqm/java/lib/com.ibm.mq.jar
/opt/mqm/java/lib/com.ibm.mq.jms.Nojndi.jar
/opt/mqm/java/lib/com.ibm.mq.soap.jar
```

```
/opt/mqm/java/lib/com.ibm.mqjms.jar  
/opt/mqm/java/lib/com.ibm.mqetclient.jar  
/opt/mqm/java/lib/commonservices.jar  
/opt/mqm/java/lib/dhbc core.jar  
/opt/mqm/java/lib/rmm.jar  
/opt/mqm/java/lib/providerutil.jar  
/opt/mqm/java/lib/CL3Export.jar  
/opt/mqm/java/lib/CL3Nonexport.jar
```

where `/opt/mqm` is the location of the WebSphere MQ 6.0 installation.

- For WebSphere MQ 7.0, copy these JAR files to the `as-install/lib` directory:

```
/opt/mqm/java/lib/com.ibm.mq.jar,  
/opt/mqm/java/lib/com.ibm.mq.jms.Nojndi.jar,  
/opt/mqm/java/lib/com.ibm.mq.soap.jar,  
/opt/mqm/java/lib/com.ibm.mqjms.jar,  
/opt/mqm/java/lib/com.ibm.mq.jmqi.jar,  
/opt/mqm/java/lib/com.ibm.mq.commonservices.jar,  
/opt/mqm/java/lib/dhbc core.jar,  
/opt/mqm/java/lib/rmm.jar,  
/opt/mqm/java/lib/providerutil.jar,  
/opt/mqm/java/lib/CL3Export.jar,  
/opt/mqm/java/lib/CL3Nonexport.jar
```

where `/opt/mqm` is the location of the WebSphere MQ 7.0 installation.


- Set the `LD_LIBRARY_PATH` environment variable to the `java/lib` directory, and then restart GlassFish Server. For example, in a UNIX—based system, with WebSphere MQ installed under `/opt/mqm`, you would enter:

```
$ export LD_LIBRARY_PATH=/opt/mqm/java/lib
```

▼ Configure the WebSphere MQ Administered Objects

This section provides an example of how you could configure the necessary administered objects, such as destinations and connection factories, on the WebSphere MQ instance from which you want to access messages using GlassFish Server. Therefore, you will need to change the administered object names to suit your installation.

Before You Begin If WebSphere MQ created a user and a group named `mqm` during the installation, then you must specify a password for the `mqm` user using the `$ passwd mqm` command.



1 Switch to the mqm user:

```
$ su mqm
```

2 For Linux, set the following kernel version:

```
$ export LD_ASSUME_KERNEL=2.2.5
```

3 Create a new MQ queue manager named "QM1":

```
$ crtmqm QM1
```

4 Start the new MQ queue manager.

In the image above, QM1 is associated with the IBM WebSphere MQ broker.

```
$ strmqm QM1
```

5 Start the MQ listener:

```
$ runmqclsr -t tcp -m QM1 -p 1414 &
```

6 Modify the default JMSAdmin console configuration as follows:

a. Edit the JMSAdmin script in the `/opt/mqm/java/bin` directory to change the JVM to a location of a valid JVM your system.

b. Set the relevant environment variable required for JMSAdmin by sourcing the `setjmsenv` script located in the `/opt/mqm/java/bin` directory.

```
$ cd /opt/mqm/java/bin
$ source setjmsenv
```

where /opt/mqm is the location of the WebSphere MQ installation.

- c. Change the JMSAdmin.config file to indicate the Initial Context Factory you will be using by setting the following name-value pairs and commenting out the rest:**

```
INITIAL_CONTEXT_FACTORY=com.sun.jndi.fscontext.RefFSContextFactory
PROVIDER_URL=file:/opt/tmp
```

- 7 Create WebSphere MQ queues using the runmqsc console and MQJMS_PSQ.mqsc script.**

```
$ runmqsc QM1 < MQJMS_PSQ.mqsc
```

- 8 Create user defined physical queue for your application using runmqsc console and an appropriate physical queue name. An example of how this could be done is shown below.**

In the image above, ORANGE.LOCAL.QUEUE is associated with QM1.

```
$ runmqsc QM1
> DEFINE QLOCAL(ORANGE.LOCAL.QUEUE)
> end
```

- 9 Start the WebSphere MQ Broker:**

```
$ strmqbrk -m QM1
```

- 10 In the WebSphere MQ JMSAdmin console, use the following commands to create the connection factories, XA connection factories, and destinations for your application, as shown in the following sample, which lists each of the various JMS administered objects.**

In the image above, QCF (for QM1) and TQueue (associated with ORANGE.LOCAL.QUEUE) are defined in the FileSystem Naming Context.

```
$ ./JMSAdmin
```

```
InitCtx>def qcf<JNDI name to be given to the Queue Connection Factory>
hostname<IBM MQ server hostname> port(1414) channel(SYSTEM.DEF.SVRCONN)
transport(CLIENT) qmanager<name of queue manager defined>
```

For example:

```
def qcf(QCF) hostname(localhost) port(1414) channel(SYSTEM.DEF.SVRCONN)
transport(CLIENT) qmanager(QM1)
```

```
InitCtx%def xaqcf<JNDI name to be given to the XA Queue Connection Factory>
hostname<IBM MQ server hostname> port(1414) channel(SYSTEM.DEF.SVRCONN)
transport(CLIENT) qmanager<name of queue manager defined>
```

For example:

```
def xaqcf(XAQCF) hostname(localhost) port(1414) channel(SYSTEM.DEF.SVRCONN)
transport(CLIENT) qmanager(QM1)
```

```
InitCtx%def q<JNDI Name to be given to the Queue> queue<physical queue name>
qmanager(name of queue manager defined )
```

For example: def q(TQueue) queue(ORANGE.LOCAL.QUEUE) qmanager(QM1)

```
InitCtx%def tcf<JNDI Name to be given to the Topic Connection Factory>
qmanager(name of queue manager defined )
```



```
For example: def tcf(TCF) qmanager(QM1)

InitCtx%def xatcf<JNDI Name to be given to the  XA Topic Connection Factory>
qmanager(name of queue manager defined )

For example: def xatcf(XATCF) qmanager(QM1)

InitCtx%def t<JNDI Name to be given to the Topic> topic<sample topic name>

For example: def t(TTopic) topic(topic)
```

Create a Resource Adapter Configuration for GenericJMSRA to Work With WebSphere MQ

Before deploying GenericJMSRA, you need to create a resource adapter configuration in GlassFish Server. You can do this using either the Administration Console or the `asadmin` command. Use the following `asadmin` command to create a resource adapter configuration for `genericra` to configure it to work with WebSphere MQ.

```
asadmin> create-resource-adapter-config
--user <adminname> --password <admin password>
--property SupportsXA=true:ProviderIntegrationMode
=jndi:UserName=mqm:Password=###:RMPolicy
=OnePerPhysicalConnection:JndiProperties
=java.naming.factory.url.pkgs\\
=com.ibm.mq.jms.naming,java.naming.factory.initial\\
=com.sun.jndi.fscontext.RefFSContextFactory,java.naming.provider.url\\
=file\\:\\\\\\opt\\tmp:LogLevel=finest genericra
```

Note – When using `asadmin` you need to escape each `=` and any `:` characters by prepending a backward slash `\`. The escape sequence is not necessary if the configuration is performed through the Administration Console. Also, ensure that the provider URL is configured correctly depending on the platform. For example, on Windows systems it should be `file:/C:/opt/tmp` and on UNIX—based systems it is `file://opt/tmp`.

This creates a resource adapter configuration with the name `genericra`, and Oracle recommends not changing the default name. The resource adapter configuration is configured with the properties specified using the `--properties` argument; multiple properties are configured as a colon-separated list of name-value pairs that are entered as a single line.

In this example, the following properties are configured:

Note – The tables in this section describe the GenericJMSRA properties that are relevant only when integrating with WebSphere MQ. For a complete list of properties, see the comprehensive table in [“GenericJMSRA Configuration Properties” on page 338](#).

<i>Property Name</i>	<i>Required Value</i>	<i>Description</i>
SupportsXA	true	Set the supports distributed transactions attribute to true. The level of transactional support the adapter provides -- none, local, or XA -- depends on the capabilities of the Enterprise Information System (EIS) being adapted. If an adapter supports XA transactions and this attribute is XA, the application can use distributed transactions to coordinate the EIS resource with JDBC and JMS resources.
ProviderIntegration Mode	jndi	Specifies that connection factories and destinations in GlassFish's JNDI store are configured to refer to connection factories and destinations in WebSphere MQ's JNDI store.
JndiProperties	JndiProperties= java.naming.factory.url.pkgs\ =com.ibm.mq.jms.naming, java.naming. factory.initial\ =com.sun.jndi.fscontext. RefFSContextFactory, java.naming. provider.url\ =file\\:\\\\\\opt\\tmp: LogLevel=finest genericra	JNDI properties for connecting to WebSphere MQ's JNDI, specified as comma-separated list of name=value pairs without spaces.
UserName	Name of the WebSphere MQ user	User name to connect to WebSphere MQ. The user name can be overridden in ActivationSpec and ManagedConnection. If no user name is specified anonymous connections will be used, if permitted.
Password	Password for the WebSphere MQ user	Password to connect to WebSphere MQ. The password can be overridden in ActivationSpec and ManagedConnection.

Property Name	Required Value	Description
RMIPolicy	OnePerPhysicalConnection	<p>Some XAResource implementations, such as WebSphere MQ, rely on a Resource Manager per Physical Connection, and this causes issues when there is inbound and outbound communication to the same queue manager in a single transaction (for example, when an MDB sends a response to a destination).</p> <p>When <i>RMPolicy</i> is set to <i>OnePerPhysicalConnection</i>, the XAResource wrapper implementation's <i>isSameRM</i> in <i>GenericJMSRA</i> would check if both the XAResources use the same physical connection, before delegating to the wrapped objects. Therefore, ensure that this attribute is set to <i>OnePerPhysicalConnection</i> if the application uses XA.</p>
LogLevel	Desired log level of JDK logger	Used to specify the level of logging.

Note – You must use the values for *SupportsXA*, *RMPolicy* and *ProviderIntegrationMode* as the required values that are used in this table.

Deploy the GenericJMSRA Archive

The GenericJMSRA archive is available as an Add-On in the Administration Console's Update Tool.

For instructions on downloading and deploying GenericJMSRA, see [“Deploy the GenericJMSRA Resource Archive” on page 346](#).

Create the Connection Factories and Administered Objects in GlassFish Server

In order to configure a JMS Connection Factory using GenericJMSRA, a Connector Connection Pool and resource needs to be created in GlassFish Server, as described in this section.

Using the example WebSphere MQ configuration in [“Configure the WebSphere MQ Administered Objects” on page 358](#), you will see `mypool` (pointing to `GenericJMSRA` and `QCF`) and `jms/MyQCF` (for `mypool`) created in GlassFish Server.

Note – If you want configure connections and destination resources using the Administration Console, this is explained in the Administration Console online help. When using Administration Console, following the, instructions for creating a new **Connector Connection Pool** and **Admin Object Resources**, and not the instructions for creating a JMS Connection Pool and Destination Resources. For more information about using `asadmin` to create these resources, see [“To Create a Connector Connection Pool” on page 275](#) and [“To Create a Connector Resource” on page 278](#).

▼ Creating Connections and Destinations

In order to configure a JMS Connection Factory, using `GenericJMSRA`, a Connector Connection Pool and Destination resources need to be created in GlassFish Server using names that map to the corresponding connection and destination resources in WebSphere MQ. The connections and destination name in these steps map to the example WebSphere MQ configuration in [“Configure the WebSphere MQ Administered Objects” on page 358](#).

1 Create connection pools that point to the connection pools in WebSphere MQ.

The following `asadmin` command creates a Connection Pool called `mypool` and points to the `XAQCF` created in WebSphere MQ:

```
asadmin create-connector-connection-pool -- raname genericra connectiondefinition
      javax.jms.QueueConnectionFactory --transactionsupport XATransaction
      --property ConnectionFactoryJndiName=QCF mypool
```

The following `asadmin` command creates a Connection Pool called `mypool2` and points to the `XATCF` created in WebSphere MQ:

```
asadmin create-connector-connection-pool
      -- raname genericra connectiondefinition javax.jms.TopicConnectionFactory
      --transactionsupport XATransaction
      --property ConnectionFactoryJndiName=XATCF mypool2
```

2 Create the connector resources.

The following `asadmin` command creates a connector resource named `jms/MyQCF` and binds this resource to JNDI for applications to use:

```
asadmin create-connector-resource --poolname mypool jms/MyQCF
```

The following `asadmin` command creates a connector resource named `jms/MyTCF` and binds this resource to JNDI for applications to use:

```
asadmin create-connector-resource --poolname mypool2 jms/MyTCF
```

3 Create the JMS destination resources as administered objects.

In the image above, `jms/MyQueue` (pointing to `GenericJMSRA` and `TQueue`) is created in GlassFish Server.

The following `asadmin` command creates a `javax.jms.Queue` administered object and binds it to the GlassFish Server JNDI tree at `jms/MyQueue` and points to the `jms/TQueue` created in WebSphere MQ.

```
asadmin create-admin-object --raname genericra --restype javax.jms.Queue
--property DestinationJndiName=TQueue jms/MyQueue
```

The following `asadmin` command creates a `javax.jms.Topic` administered object and binds it to the GlassFish Server JNDI tree at `jms/MyTopic` and points to the `jms/TTopic` created in WebSphere MQ.

```
asadmin create-admin-object --raname genericra --restype javax.jms.Topic
--property DestinationJndiName=TTopic jms/MyTopic
```

Configuring an MDB to Receive Messages from WebSphere MQ

The administered object names in the sample deployment descriptor below map to the example WebSphere MQ configuration in [“Configure the WebSphere MQ Administered Objects” on page 358](#). The deployment descriptors need to take into account the resource adapter and the connection resources that have been created. A sample `sun-ejb-jar.xml` for a Message Driven Bean that listens to a destination called `TQueue` in WebSphere MQ, and publishes back reply messages to a destination resource named `jms/replyQueue` in GlassFish Server, as shown below.

```
<sun-ejb-jar>
<enterprise-beans>
<unique-id.1/></unique-id>
<ejb>
  <ejb-name>SimpleMessageEJB</ejb-name>
  <jndi-name>jms/SampleQueue</jndi-name>
  <!-- QCF used to publish reply messages -->
  <resource-ref>
    <res-ref-name>jms/MyQueueConnectionFactory</res-ref-name>
    <jndi-name>jms/MyQCF</jndi-name>
    <default-resource-principal>
      <name>mqm</name>
      <password>mqm</password>
    </default-resource-principal>
  </resource-ref>
  <!-- reply destination resource> Creating of this replyQueue destination resource is not
    shown above, but the steps are similar to creating the "jms/MyQueue" resource -->
  <resource-env-ref>
    <resource-env-ref-name>jms/replyQueue</resource-env-ref-name>
    <jndi-name>jms/replyQueue</jndi-name>
  </resource-env-ref>

  <!-- Activation related RA specific configuration for this MDB -->
  <mdb-resource-adapter>
  <!-- resource-adapter-mid points to the Generic Resource Adapter for JMS -->
```

```

<resource-adapter-mid>genericra</resource-adapter-mid>
<activation-config>
  <activation-config-property>
    <activation-config-property-name>DestinationType</activation-config-property-name>
    <activation-config-property-value>javax>jms>Queue</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>ConnectionFactoryJndiName</activation-config-property-name>
    <activation-config-property-value>QCF</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>DestinationJndiName</activation-config-property-name>
    <activation-config-property-value>TQueue</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>MaxPoolSize</activation-config-property-name>
    <activation-config-property-value>32</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>RedeliveryAttempts</activation-config-property-name>
    <activation-config-property-value>0</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>ReconnectAttempts</activation-config-property-name>
    <activation-config-property-value>4</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>ReconnectInterval</activation-config-property-name>
    <activation-config-property-value>10</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>RedeliveryInterval</activation-config-property-name>
    <activation-config-property-value>1</activation-config-property-value>
  </activation-config-property>
  <activation-config-property>
    <activation-config-property-name>SendBadMessagesToDMD</activation-config-property-name>
    <activation-config-property-value>>false</activation-config-property-value>
  </activation-config-property>
</activation-config>
</mdb-resource-adapter>
</ejb>
</enterprise-beans>
</sun-ejb-jar>

```

The business logic encoded in Message Driven Bean could then lookup the configured QueueConnectionFactory/Destination resource to create a connection as shown below.

```

Context context = null;
ConnectionFactory connectionFactory = null;
logger>info("In PublisherBean>ejbCreate()");
try {
  context = new InitialContext();
  queue = (javax>jms>Queue) context>lookup("java:comp/env/jms/replyQueue");
  connectionFactory = (ConnectionFactory) context>lookup("java:comp/env/jms/MyQueueConnectionFactory");
  connection = connectionFactory>createConnection();
} catch (Throwable t) {
  logger>severe("PublisherBean>ejbCreate:" + "Exception: " +
    t.toString());
}

```

Administering the Java Naming and Directory Interface (JNDI) Service

The Java Naming and Directory Interface (JNDI) API is used for accessing different kinds of naming and directory services. Java EE components locate objects by invoking the JNDI lookup method.

The following topics are addressed here:

- [“About JNDI” on page 367](#)
- [“Administering JNDI Resources” on page 369](#)

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

About JNDI

By making calls to the JNDI API, applications locate resources and other program objects. A *resource* is a program object that provides connections to systems, such as database servers and messaging systems. A JDBC resource is sometimes referred to as a data source. Each resource object is identified by a unique, people-friendly name, called the *JNDI name*. A resource object and its JNDI name are bound together by the naming and directory service, which is included with the GlassFish Server.

When a new name-object binding is entered into the JNDI, a new resource is created.

The following topics are addressed here:

- [“Java EE Naming Environment” on page 368](#)
- [“How the Naming Environment and the Container Work Together” on page 368](#)
- [“Naming References and Binding Information” on page 369](#)

Java EE Naming Environment

JNDI names are bound to their objects by the naming and directory service that is provided by a Java EE server. Because Java EE components access this service through the JNDI API, the object usually uses its JNDI name. For example, the JNDI name of the PointBase database is `jdbc/Pointbase`. At startup, the GlassFish Server reads information from the configuration file and automatically adds JNDI database names to the name space, one of which is `jdbc/Pointbase`.

Java EE application clients, enterprise beans, and web components must have access to a JNDI naming environment.

The application component's naming environment is the mechanism that allows customization of the application component's business logic during deployment or assembly. This environment allows you to customize the application component without needing to access or change the source code of the component. A Java EE container implements the provides the environment to the application component instance as a *JNDI naming context*.

How the Naming Environment and the Container Work Together

The application component's environment is used as follows:

- The application component's business methods access the environment using the JNDI interfaces. In the deployment descriptor, the application component provider declares all the environment entries that the application component expects to be provided in its environment at runtime.
- The container provides an implementation of the JNDI naming context that stores the application component environment. The container also provides the tools that allow the deployer to create and manage the environment of each application component.
- A deployer uses the tools provided by the container to initialize the environment entries that are declared in the application component's deployment descriptor. The deployer sets and modifies the values of the environment entries.
- The container makes the JNDI context available to the application component instances at runtime. These instances use the JNDI interfaces to obtain the values of the environment entries.

Each application component defines its own set of environment entries. All instances of an application component within the same container share the same environment entries. Application component instances are not allowed to modify the environment at runtime.

Naming References and Binding Information

A *resource reference* is an element in a deployment descriptor that identifies the component's coded name for the resource. For example, `jdbc/SavingsAccountDB`. More specifically, the coded name references a connection factory for the resource.

The JNDI name of a resource and the resource reference name are not the same. This approach to naming requires that you map the two names before deployment, but it also decouples components from resources. Because of this decoupling, if at a later time the component needs to access a different resource, the name does not need to change. This flexibility makes it easier for you to assemble Java EE applications from preexisting components.

The following table lists JNDI lookups and their associated resource references for the Java EE resources used by the GlassFish Server.

TABLE 17-1 JNDI Lookup Names and Their Associated References

JNDI Lookup Name	Associated Resource Reference
<code>java:comp/env</code>	Application environment entries
<code>java:comp/env/jdbc</code>	JDBC DataSource resource manager connection factories
<code>java:comp/env/ejb</code>	EJB References
<code>java:comp/UserTransaction</code>	UserTransaction references
<code>java:comp/env/mail</code>	JavaMail Session Connection Factories
<code>java:comp/env/url</code>	URL Connection Factories
<code>java:comp/env/jms</code>	JMS Connection Factories and Destinations
<code>java:comp/ORB</code>	ORB instance shared across application components

Administering JNDI Resources

Within GlassFish Server, you can configure your environment for custom and external JNDI resources. A custom resource accesses a local JNDI repository; an external resource accesses an external JNDI repository. Both types of resources need user-specified factory class elements, JNDI name attributes, and so on.

- [“Administering Custom JNDI Resources” on page 370](#)
- [“Administering External JNDI Resources” on page 372](#)

Administering Custom JNDI Resources

A custom resource specifies a custom server-wide resource object factory that implements the `javax.naming.spi.ObjectFactory` interface.

The following topics are addressed here:

- [“To Create a Custom JNDI Resource” on page 370](#)
- [“To List Custom JNDI Resources” on page 370](#)
- [“To Update a Custom JNDI Resource” on page 371](#)
- [“To Delete a Custom JNDI Resource” on page 371](#)

▼ To Create a Custom JNDI Resource

Use the `create-custom-resource` subcommand in remote mode to create a custom resource.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Create a custom resource by using the `create-custom-resource(1)` subcommand.**
Information on properties for the subcommand is contained in this help page.
- 3 **Restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 17–1 Creating a Custom Resource

This example creates a custom resource named `sample-custom-resource`.

```
asadmin> create-custom-resource --restype topic --factoryclass com.imq.topic
sample_custom_resource
Command create-custom-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-custom-resource` at the command line.

▼ To List Custom JNDI Resources

Use the `list-custom-resources` subcommand in remote mode to list the existing custom resources.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the custom resources by using the `list-custom-resources(1)` subcommand.**

Example 17-2 Listing Custom Resources

This example lists the existing custom resources.

```
asadmin> list-custom-resources
sample_custom_resource01
sample_custom_resource02
Command list-custom-resources executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-custom-resources` at the command line.

▼ To Update a Custom JNDI Resource

- 1 List the custom resources by using the `list-custom-resources(1)` subcommand.
- 2 Use the `set(1)` subcommand to modify a custom JNDI resource.

Example 17-3 Updating a Custom JNDI Resource

This example modifies a custom resource.

```
asadmin> set server.resources.custom-resource.custom
/my-custom-resource.property.value=2010server.resources.custom-resource.custom
/my-custom-resource.property.value=2010
```

▼ To Delete a Custom JNDI Resource

Use the `delete-custom-resource` subcommand in remote mode to delete a custom resource.

- 1 Ensure that the server is running.
Remote subcommands require a running server.
- 2 List the custom resources by using the `list-custom-resources(1)` subcommand.
- 3 Delete a custom resource by using the `delete-custom-resource(1)` subcommand.

Example 17-4 Deleting a Custom Resource

This example deletes a custom resource named `sample-custom-resource`.

```
asadmin> delete-custom-resource sample_custom_resource
Command delete-custom-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-custom-resource` at the command line.

Administering External JNDI Resources

Applications running on GlassFish Server often require access to resources stored in an external JNDI repository. For example, generic Java objects might be stored in an LDAP server according to the Java schema. External JNDI resource elements let you configure such external resource repositories.

The following topics are addressed here:

- [“To Register an External JNDI Resource” on page 372](#)
- [“To List External JNDI Resources” on page 373](#)
- [“To List External JNDI Entries” on page 373](#)
- [“To Update an External JNDI Resource” on page 374](#)
- [“To Delete an External JNDI Resource” on page 374](#)
- [“Example of Using an External JNDI Resource” on page 374](#)
- [“To Disable GlassFish Server v2 Vendor-Specific JNDI Names” on page 375](#)

▼ To Register an External JNDI Resource

Use the `create-jndi-resource` subcommand in remote mode to register an external JNDI resource.

Before You Begin The external JNDI factory must implement the `javax.naming.spi.InitialContextFactory` interface.

- 1 Ensure that the server is running.**
Remote subcommands require a running server.
- 2 Register an external JNDI resource by using the `create-jndi-resource(1)` subcommand.**
Information on properties for the subcommand is contained in this help page.
- 3 Restart GlassFish Server.**
See [“To Restart a Domain” on page 116](#).

Example 17–5 Registering an External JNDI Resource

In This example `sample_jndi_resource` is registered.

```
asadmin> create-jndi-resource --jndilookupname sample_jndi
--restype queue --factoryclass sampleClass --description "this is a sample jndi
resource" sample_jndi_resource
Command create-jndi-resource executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help create-jndi-resource` at the command line.

▼ To List External JNDI Resources

Use the `list-jndi-resources` subcommand in remote mode to list all existing JNDI resources.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the existing JNDI resources by using the `list-jndi-resources(1)` subcommand.**

Example 17–6 Listing JNDI Resources

This example lists the JNDI resources.

```
asadmin> list-jndi-resources
jndi_resource1
jndi_resource2
jndi_resource3
Command list-jndi-resources executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-jndi-resources` at the command line.

▼ To List External JNDI Entries

Use the `list-jndi-entries` subcommand in remote mode to browse and list the entries in the JNDI tree. You can either list all entries, or you can specify the JNDI context or subcontext to list specific entries.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **List the JNDI entries for a configuration by using the `list-jndi-entries(1)` subcommand.**

Example 17–7 Listing JNDI Entries

This example lists all the JNDI entries for the naming service.

```
asadmin> list-jndi-entries
jndi_entry03
jndi_entry72
jndi_entry76
Command list-jndi-resources executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help list-jndi-entries` at the command line.

▼ To Update an External JNDI Resource

- 1 List the existing JNDI resources by using the `list-jndi-resources(1)` subcommand.
- 2 Use the `set(1)` subcommand to modify an external JNDI resource.

Example 17–8 Updating an External JNDI Resource

This example modifies an external resource.

```
asadmin> set server.resources.external-jndi-resource.my-jndi-resource.  
jndi-lookup-name=bar server.resources.external-jndi-resource.my-jndi-resource.jndi-lookup-name=bar
```

▼ To Delete an External JNDI Resource

Use the `delete-jndi-resource` subcommand in remote mode to remove a JNDI resource.

- 1 Ensure that the server is running.
Remote subcommands require a running server.
- 2 Remove an external JNDI entry by using the `delete-jndi-resource(1)` subcommand.

Example 17–9 Deleting an External JNDI Resource

This example deletes an external JNDI resource:

```
asadmin> delete-jndi-resource jndi_resource2  
Command delete-jndi-resource executed successfully.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help delete-jndi-resource` at the command line.

Example of Using an External JNDI Resource

```
<resources>  
<!-- external-jndi-resource element specifies how to access Java EE resources  
-- stored in an external JNDI repository. This example  
-- illustrates how to access a java object stored in LDAP.  
-- factory-class element specifies the JNDI InitialContext factory that  
-- needs to be used to access the resource factory. property element  
-- corresponds to the environment applicable to the external JNDI context  
-- and jndi-lookup-name refers to the JNDI name to lookup to fetch the  
-- designated (in this case the java) object.  
-->  
  <external-jndi-resource jndi-name="test/myBean"  
    jndi-lookup-name="cn=myBean"  
    res-type="test.myBean"
```

```

        factory-class="com.sun.jndi.ldap.LdapCtxFactory">
        <property name="PROVIDER-URL" value="ldap://ldapserver:389/o=myObjects" />
        <property name="SECURITY_AUTHENTICATION" value="simple" />
        <property name="SECURITY_PRINCIPAL", value="cn=joeSmith, o=Engineering" />
        <property name="SECURITY_CREDENTIALS" value="changeit" />
    </external-jndi-resource>
</resources>

```

▼ To Disable GlassFish Server v2 Vendor-Specific JNDI Names

The EJB 3.1 specification supported by GlassFish Server 3.1 defines portable EJB JNDI names. Because of this, there is less need to continue to use older vendor-specific JNDI names.

By default, GlassFish Server v2-specific JNDI names are applied automatically by GlassFish Server 3.1 for backward compatibility. However, this can lead to some ease-of-use issues. For example, deploying two different applications containing a Remote EJB component that exposes the same remote interface causes a conflict between the default JNDI names.

The default handling of v2-specific JNDI names in GlassFish Server 3.1 can be managed with the `asadmin` command or with the `disable-nonportable-jndi-names` boolean property for the `ejb-container` element in `glassfish-ejb-jar.xml`.

● Use the `asadmin` command or directly modify the `glassfish-ejb-jar.xml` file to set the `disable-nonportable-jndi-names` property.

■ Using the `asadmin` command:

```
asadmin> set server.ejb-container.property.disable-nonportable-jndi-names="true"
```

■ Directly modifying the `glassfish-ejb-jar.xml` file.

a. Add the `disable-nonportable-jndi-names` property to the `ejb-container` element in `glassfish-ejb-jar.xml`.

b. Set the value of the `disable-nonportable-jndi-names` boolean, as desired.

- `false` — Enables the automatic use of GlassFish Server v2-specific JNDI names. This is the default setting.
- `true` — Disables the automatic use of v2-specific JNDI names. In all cases, 3.1-compatible JNDI names will be used.

c. Save the `glassfish-ejb-jar.xml` file and restart the GlassFish Server domain.

This setting applies to all EJBs deployed to the server.

Administering Transactions

This chapter discusses how to manage the transaction service for the GlassFish Server Open Source Edition environment by using the `asadmin` command-line utility. Instructions for manually recovering transactions are also included.

The following topics are addressed here:

- “About Transactions” on page 377
- “Configuring the Transaction Service” on page 380
- “Managing the Transaction Service for Rollbacks” on page 381
- “Recovering Transactions” on page 384
- “Transaction Logging” on page 388

Instructions for accomplishing the tasks in this chapter by using the Administration Console are contained in the Administration Console online help.

For more information about the Java Transaction API (JTA) and Java Transaction Service (JTS), see the following sites: <http://www.oracle.com/technetwork/java/javaee/tech/jta-138684.html> and <http://www.oracle.com/technetwork/java/javaee/tech/jts-140022.html>.

You might also want to read Chapter 43, “Transactions,” in *The Java EE 6 Tutorial*.

About Transactions

A *transaction* is a series of discreet actions in an application that must all complete successfully. By enclosing one or more actions in an indivisible unit of work, a transaction ensures data integrity and consistency. If all actions do not complete, the changes are rolled back.

For example, to transfer funds from a checking account to a savings account, the following steps typically occur:

1. Check to see if the checking account has enough money to cover the transfer.

2. Debit the amount from the checking account.
3. Credit the amount to the savings account.
4. Record the transfer to the checking account log.
5. Record the transfer to the savings account log.

These steps together are considered a single transaction.

If all the steps complete successfully, the transaction is *committed*. If any step fails, all changes from the preceding steps are rolled back, and the checking account and savings account are returned to the states they were in before the transaction started. This type of event is called a *rollback*. A normal transaction ends in either a committed state or a rolled back state.

The following elements contribute to reliable transaction processing by implementing various APIs and functionalities:

- **Transaction Manager.** Provides the services and management functions required to support transaction demarcation, transactional resource management, synchronization, and transaction context propagation.
- **GlassFish Server.** Provides the infrastructure required to support the application runtime environment that includes transaction state management.
- **Resource Manager.** Through a resource adapter, the resource manager provides the application access to resources. The resource manager participates in distributed transactions by implementing a transaction resource interface used by the transaction manager to communicate transaction association, transaction completion, and recovery work. An example of such a resource manager is a relational database server.
- **Resource Adapter.** A system-level software library is used by GlassFish Server or a client to connect to a resource manager. A resource adapter is typically specific to a resource manager. The resource adapter is available as a library and is used within the address space of the client using it. An example of such a resource adapter is a Java Database Connectivity (JDBC) driver. For information on supported JDBC drivers, see [“Configuration Specifics for JDBC Drivers” on page 263](#).
- **Transactional User Application.** In the GlassFish Server environment, the transactional user application uses Java Naming and Directory Interface (JNDI) to look up transactional data sources and, optionally, the user transaction). The application might use declarative transaction attribute settings for enterprise beans, or explicit programmatic transaction demarcation. For more information, see “The Transaction Manager, the Transaction Synchronization Registry, and UserTransaction” in *GlassFish Server Open Source Edition 3.1 Application Development Guide*.

The following topics are addressed here:

- [“Transaction Resource Managers” on page 379](#)
- [“Transaction Scope” on page 379](#)

Transaction Resource Managers

There are three types of transaction resource managers:

- Databases - Use of transactions prevents databases from being left in inconsistent states due to incomplete updates. For information about JDBC transaction isolation levels, see “Using JDBC Transaction Isolation Levels” in *GlassFish Server Open Source Edition 3.1 Application Development Guide*.

The GlassFish Server supports a variety of JDBC XA drivers. For a list of the JDBC drivers currently supported by the GlassFish Server, see the *GlassFish Server Open Source Edition 3.1-3.1.1 Release Notes*. For configurations of supported and other drivers, see “Configuration Specifics for JDBC Drivers” on page 263.

- Java Message Service (JMS) Providers - Use of transactions ensures that messages are reliably delivered. The GlassFish Server is integrated with Open Message Queue, a fully capable JMS provider. For more information about transactions and the JMS API, see Chapter 16, “Administering the Java Message Service (JMS).”
- J2EE Connector Architecture (CA) components - Use of transactions prevents legacy EIS systems from being left in inconsistent states due to incomplete updates. For more information about connectors, see Chapter 12, “Administering EIS Connectivity.”

Transaction Scope

A *local* transaction involves only one non-XA resource and requires that all participating application components execute within one process. Local transaction optimization is specific to the resource manager and is transparent to the Java EE application.

In the GlassFish Server, a JDBC resource is non-XA if it meets either of the following criteria:

- In the JDBC connection pool configuration, the DataSource class does not implement the `javax.sql.XADataSource` interface.
- The Resource Type setting is not set to `javax.sql.XADataSource`.

A transaction remains local if the following conditions remain true:

- One and only one non-XA resource is used. If any additional non-XA resource is used, the transaction is aborted, because the transaction manager must use XA protocol to commit two or more resources.
- No transaction importing or exporting occurs.

Transactions that involve multiple resources or multiple participant processes are *distributed* or *global* transactions. A global transaction can involve one non-XA resource if last agent optimization is enabled. Otherwise, all resources must be XA. The `use-last-agent-optimization` property is set to `true` by default. For details about how to set this property, see “Configuring the Transaction Service” on page 380.

If only one XA resource is used in a transaction, one-phase commit occurs, otherwise the transaction is coordinated with a two-phase commit protocol.

A two-phase commit protocol between the transaction manager and all the resources enlisted for a transaction ensures that either all the resource managers commit the transaction or they all abort. When the application requests the commitment of a transaction, the transaction manager issues a `PREPARE_TO_COMMIT` request to all the resource managers involved. Each of these resources can in turn send a reply indicating whether it is ready for commit (`PREPARED`) or not (`NO`). Only when all the resource managers are ready for a commit does the transaction manager issue a commit request (`COMMIT`) to all the resource managers. Otherwise, the transaction manager issues a rollback request (`ABORT`) and the transaction is rolled back.

Configuring the Transaction Service

You can configure the transaction service in the GlassFish Server in the following ways:

- To configure the transaction service using the Administration Console, open the Transaction Service component under the relevant configuration. For details, click the Help button in the Administration Console.
- To configure the transaction service, use the `set(1)` subcommand to set the following attributes.

The following examples show the `server-config` configuration, but values for any configuration can be set. For example, if you create a cluster named `cluster1` and a configuration named `cluster1-config` is automatically created for it, you can use `cluster1-config` in the `set` subcommand to get the transaction service settings for that cluster.

```
server-config.transaction-service.automatic-recovery = false
server-config.transaction-service.heuristic-decision = rollback
server-config.transaction-service.keypoint-interval = 2048
server-config.transaction-service.retry-timeout-in-seconds = 600
server-config.transaction-service.timeout-in-seconds = 0
server-config.transaction-service.tx-log-dir = domain-dir/logs
```

You can also set these properties:

```
server-config.transaction-service.property.oracle-xa-recovery-workaround = true
server-config.transaction-service.property.sybase-xa-recovery-workaround = false
server-config.transaction-service.property.disable-distributed-transaction-logging = false
server-config.transaction-service.property.xaresource-txn-timeout = 0
server-config.transaction-service.property.pending-txn-cleanup-interval = -1
server-config.transaction-service.property.use-last-agent-optimization = true
server-config.transaction-service.property.delegated-recovery = false
server-config.transaction-service.property.wait-time-before-recovery-insec = 60
server-config.transaction-service.property.purge-cancelled-transactions-after = 0
server-config.transaction-service.property.commit-one-phase-during-recovery = false
server-config.transaction-service.property.add-wait-point-during-recovery = 0
server-config.transaction-service.property.db-logging-resource = jdbc/TxnDS
server-config.transaction-service.property.xa-servername = myserver
```

Default property values are shown where they exist. For `db-logging-resource` and `xa-servername`, typical values are shown. Values that are not self-explanatory are as follows:

- The `xaresource-txn-timeout` default of `0` means there is no timeout. The units are seconds.
- The `pending-txn-cleanup-interval` default of `-1` means the periodic recovery thread doesn't run. The units are seconds.
- The `purge-cancelled-transactions-after` default of `0` means cancelled transactions are not purged. The units are the number of cancellations in between purging attempts.
- The `add-wait-point-during-recovery` property does not have a default value. If this property is unset, recovery does not wait. The units are seconds.
- The `db-logging-resource` property does not have a default value. It is unset by default. However, if you set `db-logging-resource` to an empty value, the value used is `jdbc/TxnDS`.
- The `xa-servername` property does not have a default value. Use this property to override server names that can cause errors.

You can use the `get(1)` subcommand to list all the transaction service attributes and the properties that have been set. For details, see the *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual*.

Changing `keypoint-interval`, `retry-timeout-in-seconds`, or `timeout-in-seconds` does not require a server restart. Changing other attributes or properties requires a server restart.

- You can also set the following system properties:

```
ALLOW_MULTIPLE_ENLISTS_DELISTS=false
JTA_RESOURCE_TABLE_MAX_ENTRIES=8192
JTA_RESOURCE_TABLE_DEFAULT_LOAD_FACTOR=0.75f
```

The `JTA_RESOURCE_TABLE_DEFAULT_LOAD_FACTOR` default is the default Map resizing value.

Managing the Transaction Service for Rollbacks

You can roll back a single transaction by using the `asadmin` subcommands described in this section. To do so, the transaction service must be stopped (and later restarted), allowing you to see the active transactions and correctly identify the one that needs to be rolled back.

The following topics are addressed here:

- [“To Stop the Transaction Service” on page 382](#)
- [“To Roll Back a Transaction” on page 382](#)
- [“To Restart the Transaction Service” on page 383](#)
- [“Determining Local Transaction Completion at Shutdown” on page 384](#)

▼ To Stop the Transaction Service

Use the `freeze-transaction-service` subcommand in remote mode to stop the transaction service. When the transaction service is stopped, all in-flight transactions are immediately suspended. You must stop the transaction service before rolling back any in-flight transactions.

Running this subcommand on a stopped transaction subsystem has no effect. The transaction service remains suspended until you restart it by using the `unfreeze-transaction-service` subcommand.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Stop the transaction service by using the `freeze-transaction-service(1)` subcommand.**

Example 18–1 Stopping the Transaction Service

This example stops the transaction service.

```
asadmin> freeze-transaction-service --target instance1  
Command freeze-transaction-service executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help freeze-transaction-service` at the command line.

▼ To Roll Back a Transaction

In some situations, you might want to roll back a particular transaction. Before you can roll back a transaction, you must first stop the transaction service so that transaction operations are suspended. Use the `rollback-transaction` subcommand in remote mode to roll back a specific transaction.

- 1 **Ensure that the server is running.**
Remote subcommands require a running server.
- 2 **Enable monitoring using the `set` subcommand. For example:**

```
asadmin> set cluster1-config.monitoring-service.module-monitoring-levels.transaction-service=HIGH
```

- 3 **Use the `freeze-transaction-service` subcommand to halt in-process transactions. See [“To Stop the Transaction Service” on page 382](#).**

4 Identify the ID of the transaction you want to roll back.

To see a list of IDs of active transactions, use the `get` subcommand with the `--monitor` option to get the monitoring data for the `activeids` statistic. See [“Transaction Service Statistics” on page 205](#). For example:

```
asadmin> get --monitor instance1.server.transaction-service.activeids-current
```

5 Roll back the transaction by using the `rollback-transaction(1)` subcommand.

The transaction is not rolled back at the time of this command's execution, but only marked for rollback. The transaction is rolled back when it is completed.

Example 18–2 Rolling Back a Transaction

This example rolls back the transaction with transaction ID `0000000000000001_00`.

```
asadmin> rollback-transaction --target instance1 0000000000000001_00
Command rollback-transaction executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help rollback-transaction` at the command line.

▼ To Restart the Transaction Service

Use the `unfreeze-transaction-service` subcommand in remote mode to resume all the suspended in-flight transactions. Run this subcommand to restart the transaction service after it has been frozen.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Restart the suspended transaction service by using the `unfreeze-transaction-service(1)` subcommand.

Example 18–3 Restarting the Transaction Service

This example restarts the transaction service after it has been frozen.

```
asadmin> unfreeze-transaction-service --target instance1
Command unfreeze-transaction-service executed successfully
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help unfreeze-transaction-service` at the command line.

Determining Local Transaction Completion at Shutdown

When you shut down a GlassFish Server instance, all database connections are closed. When an Oracle JDBC driver-based database connection is closed in the middle of a non-XA transaction, all pending changes are committed. Other databases usually roll back pending changes when a connection is closed without being explicitly committed. To determine the exact behavior for your database, refer to the documentation from your JDBC driver vendor.

To explicitly specify whether GlassFish Server commits or rolls back non-XA transactions at server shutdown, set the

`com.sun.enterprise.in-progress-local-transaction.completion-mode` JVM option to either commit or rollback using the `create-jvm-options(1)` subcommand. For example:

```
asadmin> create-jvm-options -Dcom.sun.enterprise.in-progress-local-transaction.completion-mode=rollback
```

Recovering Transactions

There are some situations where the commit or rollback operations might be interrupted, typically because the server crashed or a resource manager crashed. Crash situations can leave some transactions stranded between steps. GlassFish Server is designed to recover from these failures. If the failed transaction spans multiple servers, the server that started the transaction can contact the other servers to get the outcome of the transaction. If the other servers are unreachable, the transaction uses heuristic decision information to determine the outcome.

The following topics are addressed here:

- [“Automatic Transaction Recovery” on page 384](#)
- [“To Manually Recover Transactions” on page 385](#)
- [“Distributed Transaction Recovery” on page 386](#)
- [“Recovery Workarounds and Limitations” on page 386](#)

Automatic Transaction Recovery

GlassFish Server can perform automatic recovery in these ways:

- Pending transactions are completed upon server startup if `automatic-recovery` is set to `true`.
- Periodic automatic recovery is performed by a background thread if the `pending-txn-cleanup-interval` property is set to a positive value.

Changing these settings requires a server restart. For more information about how to change these settings, see [“Configuring the Transaction Service” on page 380](#).

If commit fails during recovery, a message is written to the server log.

▼ To Manually Recover Transactions

Use the `recover-transactions` subcommand in remote mode to manually recover transactions that were pending when a resource or a server instance failed.

For a standalone server, do not use manual transaction recovery to recover transactions after a server failure. For a standalone server, manual transaction recovery can recover transactions only when a resource fails, but the server is still running. If a standalone server fails, only the full startup recovery process can recover transactions that were pending when the server failed.

For an installation of multiple server instances, you can use manual transaction recovery from a surviving server instance to recover transactions after a server failure. For manual transaction recovery to work properly, transaction logs must be stored on a shared file system that is accessible to all server instances. See [“Transaction Logging” on page 388](#).

When you execute `recover-transactions` in non-delegated mode, you can recover transactions that didn't complete two-phase commit because of a resource crash. To use manual transaction recovery in this way, the following conditions must be met:

- The `recover-transactions` command should be executed after the resource is restarted.
- Connection validation should be enabled so the connection pool is refreshed when the resource is accessed after the recovery. For more information, see “Connection Validation Settings” in *GlassFish Server Open Source Edition 3.1 Performance Tuning Guide*.

If commit fails during recovery, a message is written to the server log.

Note – A JMS resource crash is handled the same way as any other resource.

You can list in-doubt Open Message Queue transactions using the `imqcmd list txn` subcommand. For more information, see “Managing Transactions” in *Open Message Queue 4.5 Administration Guide*.

1 Ensure that the server is running.

Remote subcommands require a running server.

2 Manually recover transactions by using the `recover-transactions(1)` subcommand.

Example 18–4 Manually Recovering Transactions

This example performs manual recovery of transactions on `instance1`, saving them to `instance2`.

```
asadmin recover-transactions --target instance2 instance1
Transaction recovered.
```

See Also You can also view the full syntax and options of the subcommand by typing `asadmin help recover-transactions` at the command line.

Distributed Transaction Recovery

To enable cluster-wide automatic recovery, you must first facilitate storing of transaction logs in a shared file system. See [“Transaction Logging” on page 388](#).

Next, you must set the transaction service's `delegated-recovery` property to `true` (the default is `false`). For information about setting `tx-log-dir` and `delegated-recovery`, see [“Configuring the Transaction Service” on page 380](#).

Recovery Workarounds and Limitations

The GlassFish Server provides workarounds for some known issues with transaction recovery implementations.

Note – These workarounds do not imply support for any particular JDBC driver.

General Recovery Limitations

The following general limitations apply to transaction recovery:

- Recovery succeeds if there are no exceptions during the process. This is independent of the number of transactions that need to be recovered.
- Only transactions that did not complete the two-phase commit can be recovered (one of the XA resources failed or GlassFish Server crashed after resources were prepared).
- Manual transaction recovery cannot recover transactions after a server crash on a standalone server instance. Manual operations are intended for cases when a resource dies unexpectedly while the server is running. In case of a server crash, only startup recovery can recover in-doubt transactions.
- It is not possible to list transaction IDs for in-doubt transactions.
- Delegated transaction recovery (by a different server instance in a cluster) is not possible if the failed instance used an `EMBEDDED` Message Queue broker, or if it used a `LOCAL` or `REMOTE` Message Queue broker and the broker also failed. In this case, only automatic recovery on server instance restart is possible. This is because for conventional Message Queue clustering, state information in a failed broker is not available until the broker restarts.

Oracle Setup for Transaction Recovery

You must configure the following grant statements in your Oracle database to set up transaction recovery:

```
grant select on SYS.DBA_PENDING_TRANSACTIONS to user;
grant execute on SYS.DBMS_SYSTEM to user;
grant select on SYS.PENDING_TRANS$ to user;
grant select on SYS.DBA_2PC_NEIGHBORS to user;
grant execute on SYS.DBMS_XA to user;
grant select on SYS.DBA_2PC_PENDING to user;
```

The *user* is the database administrator. On some versions of the Oracle driver the last grant execute fails. You can ignore this.

Oracle Thin Driver

In the Oracle thin driver, the `XAResource.recover` method repeatedly returns the same set of in-doubt Xids regardless of the input flag. According to the XA specifications, the Transaction Manager initially calls this method with `TMSTARTSCAN` and then with `TMNOFLAGS` repeatedly until no Xids are returned. The `XAResource.commit` method also has some issues.

To disable the GlassFish Server workaround, set the `oracle-xa-recovery-workaround` property value to `false`. For details about how to set this property, see [“Configuring the Transaction Service” on page 380](#). This workaround is used unless explicitly disabled.

Delegated Recovery After Server Crash Doesn't Work on MySQL

The MySQL database supports XA transaction recovery only when the database crashes. When a GlassFish Server instance crashes, MySQL rolls back prepared transactions.

Call to `XATerminator.recover()` During `ResourceAdapter.start()` Hangs If Automatic Recovery Is Enabled

Calls to `XATerminator.recover()` from the `ResourceAdapter.start()` method never return because GlassFish Server deadlocks. This only occurs when automatic recovery is enabled.

It is not advisable to do transactional activities, such as starting a transaction or calling `XATerminator.recover()`, during `ResourceAdapter.start()`. For more information, see <http://markmail.org/message/ogc7qndhaywfkdrp#query:+page:1+mid:kyyzpcexusbnv7ri+state:results>.

Transaction Logging

The transaction service writes transactional activity into transaction logs so that transactions can be recovered. You can control transaction logging in these ways:

- Set the location of the transaction log files in one of these ways:
 - Set the GlassFish Server's `log-root` setting to a shared file system base directory and set the transaction service's `tx-log-dir` attribute to a relative path.
 - Set `tx-log-dir` to an absolute path to a shared file system directory, in which case `log-root` is ignored for transaction logs.
 - Set a system property called `TX-LOG-DIR` to a shared file system directory. For example:

```
asadmin> create-system-properties --target server TX-LOG-DIR=/inst1/logs
```

For information about setting `log-root` and other general logging settings, see [Chapter 7, “Administering the Logging Service.”](#)

- Turn off transaction logging by setting the `disable-distributed-transaction-logging` property to `true` and the `automatic-recovery` attribute to `false`. Do this *only* if performance is more important than transaction recovery.

Note – All instances in a cluster must be owned by the same user (`uid`), and read/write permissions for that user must be set on the transaction log directories.

Transaction logs should be stored in a high-availability network file system (NFS) to avoid a single point of failure.

▼ To Store Transaction Logs in a Database

For multi-core machines, logging transactions to a database may be more efficient.

This feature is intended for resource recovery on a standalone server instance while the instance is healthy, not for a server crash. It is not intended for use on a cluster.

- 1 **Create a JDBC connection Pool, and set the `non-transactional-connections` attribute to `true`.**
- 2 **Create a JDBC resource that uses the connection pool and note the JNDI name of the JDBC resource.**
- 3 **Create a table named `txn_log_table` with the following schema:**

Column Name	JDBC Type
-------------	-----------

LOCALTID	BIGINT
SERVERNAME	VARCHAR(n)
GTRID	VARBINARY

The size of the SERVERNAME column should be at least the length of the GlassFish Server host name plus 10 characters.

The size of the GTRID column should be at least 64 bytes.

4 Add the db-logging- resource property to the transaction service. For example:

```
asadmin set server-config.transaction-service.property.db-logging-resource="jdbc/TxnDS"
```

The property's value should be the JNDI name of the JDBC resource configured previously.

5 To disable file synchronization, use the following asadmin create-jvm-options command:

```
asadmin create-jvm-options -Dcom.sun.appserv.transaction.nofdsync
```

6 Restart the server.

Next Steps To define the SQL used by the transaction manager when it is storing its transaction logs in the database, use the following flags:

```
-Dcom.sun.jts.dblogging.insertquery=sql statement
```

```
-Dcom.sun.jts.dblogging.deletequery=sql statement
```

The default statements are as follows:

```
-Dcom.sun.jts.dblogging.insertquery=insert into txn_log_table values ( ?, ?, ? )
```

```
-Dcom.sun.jts.dblogging.deletequery=delete from txn_log_table where localtid =  
? and servername = ?
```

To set one of these flags using the asadmin create-jvm-options command, you must quote the statement. For example:

```
create-jvm-options '-Dcom.sun.jts.dblogging.deletequery=delete from  
txn_log_table where gtrid = ?'
```

You can also set JVM options in the Administration Console. Select the JVM Settings component under the relevant configuration. These flags and their statements must also be quoted in the Administration Console. For example:

```
'-Dcom.sun.jts.dblogging.deletequery=delete from txn_log_table where gtrid = ?'
```

See Also For information about JDBC connection pools and resources, see [Chapter 11, “Administering Database Connectivity.”](#) For more information about the asadmin create-jvm-options command, see the *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual*.

PART III

Appendixes

Subcommands for the asadmin Utility

This appendix lists the asadmin subcommands that are included with this release of the GlassFish Server Open Source Edition 3.1 software.

- “General Administration Subcommands” on page 394
- “Connectivity Subcommands” on page 396
- “Domain Subcommands” on page 399
- “Internet Connectivity Subcommands” on page 400
- “JavaMail Subcommands” on page 401
- “JMS Subcommands” on page 402
- “JNDI Subcommands” on page 403
- “JVM Subcommands” on page 404
- “Life Cycle Module Subcommands” on page 404
- “Logging and Monitoring Subcommands” on page 405
- “ORB Subcommands” on page 406
- “Thread Pool Subcommands” on page 406
- “Transaction Service Subcommands” on page 406

For information and instructions on using the asadmin application deployment subcommands, see *GlassFish Server Open Source Edition 3.1 Application Deployment Guide*.

Online help for the asadmin subcommands can be invoked on the command line, for example, `asadmin create-domain --help`. The *GlassFish Server Open Source Edition 3.1-3.1.1 Reference Manual* also provides a collection of these help pages.

Note – The common options used with remote subcommands are described in the `asadmin(1M)` help page.

General Administration Subcommands

<code>add-resources(1)</code>	Creates the resources named in the specified XML file. Supported in remote mode only. For procedural information in this guide, see “To Add Resources From an XML File” on page 62 .
<code>asadmin(1M)</code>	Describes how the asadmin utility works.
<code>create-service(1)</code>	Configures the starting of a domain administration server (DAS) on an unattended boot. On Oracle Solaris 10, this subcommand uses the Service Management Facility (SMF). For procedural information in this guide, see “To Configure a DAS or an Instance for Automatic Restart on Oracle Solaris” on page 120 .
<code>create-system-properties(1)</code>	Creates or updates system properties. Supported in remote mode only. For procedural information in this guide, see “To Create System Properties” on page 60 .
<code>delete-system-property(1)</code>	Deletes system properties of a domain or configuration, or server instance. Supported in remote mode only. For procedural information in this guide, see “To Delete a System Property” on page 61 .
<code>get(1)</code>	Gets an attribute of an element in the <code>domain.xml</code> file. With the <code>-m</code> option, gets the names and values of the monitorable or configurable attributes. For procedural information in this guide, see “Guidelines for Using the list and get Subcommands for Monitoring” on page 181 .
<code>list(1)</code>	Lists the configurable element. On Oracle Solaris, quotes are needed when running subcommands with <code>*</code> as the option value or operand. For procedural information in this guide, see “Guidelines for Using the list and get Subcommands for Monitoring” on page 181 .
<code>list-commands(1)</code>	Lists all the asadmin subcommands, local subcommands first, then remote subcommands. You can specify that only remote subcommands or only local subcommands be displayed. Supported in remote mode only. For procedural information in this guide, see “To List Subcommands” on page 66 .

<code>list-containers(1)</code>	Lists application containers and the status of each container. Supported in remote mode only. For procedural information in this guide, see “To List Containers” on page 64 .
<code>list-modules(1)</code>	Lists modules that are accessible to the GlassFish Server subsystem. The status of each module is included. Supported in remote mode only. For procedural information in this guide, see “To List Modules” on page 65 .
<code>list-system-properties(1)</code>	Lists the system properties of a domain or configuration. Supported in remote mode only. For procedural information in this guide, see “To List System Properties” on page 61 .
<code>list-timers(1)</code>	List the timers owned by a specific server instance. Supported in remote mode only. For procedural information in this guide, see “To List Timers” on page 66 .
<code>multimode(1)</code>	Provides an <code>asadmin></code> prompt for running multiple subcommands while preserving options and environment settings. Supported in local mode only. For procedural information, see “Using the asadmin Utility” on page 53 .
<code>set(1)</code>	Sets the values of one or more configurable attributes. For procedural information in this guide, see “Configuring Monitoring” on page 176 .
<code>show-component-status(1)</code>	Lists the status of existing components. Supported in remote mode only. For procedural information in this guide, see “To Show Component Status” on page 67 .
<code>start-database(1)</code>	Starts the Java DB server. Use this subcommand only for working with applications deployed to the GlassFish Server. For procedural information in this guide, see “To Start the Database” on page 247 .
<code>stop-database(1)</code>	Stops a process of the Java DB database server. For procedural information in this guide, see “To Stop the Database” on page 248 .
<code>version(1)</code>	Displays the version information for the option specified in archive or folder format. Supported in remote mode only. For procedural information in this guide, see “To Display the GlassFish Server Version” on page 63 .

Connectivity Subcommands

<code>create-admin-object(1)</code>	Creates an administered object. For procedural information in this guide, see “To Create an Administered Object” on page 290 .
<code>create-connector-connection-pool(1)</code>	Adds a new connector connection pool with the specified connection pool name. For procedural information in this guide, see “To Create a Connector Connection Pool” on page 275 .
<code>create-connector-resource(1)</code>	Creates a connector resource. For procedural information in this guide, see “To Create a Connector Resource” on page 278 .
<code>create-connector-security-map(1)</code>	Creates a connector security map for the specified connector connection pool. For procedural information, see “To Create a Connector Security Map” on page 284 .
<code>create-connector-work-security-map(1)</code>	Creates a connector work security map for the specified resource adapter. Supported in remote mode only. For procedural information in this guide, see “To Create a Connector Work Security Map” on page 287 .
<code>create-jdbc-resource(1)</code>	Creates a new JDBC resource. Supported in remote mode only. For procedural information in this guide, see “To Create a JDBC Resource” on page 259 .
<code>create-jdbc-connection-pool(1)</code>	Registers a new JDBC connection pool with the specified JDBC connection pool name. Supported in remote mode only. For procedural information in this guide, see “To Create a JDBC Connection Pool” on page 250 .
<code>create-resource-adapter-config(1)</code>	Creates configuration information for the connector module. Supported in remote mode only. For procedural information in this guide, see “To Create Configuration Information for a Resource Adapter” on page 281 .
<code>delete-admin-object(1)</code>	Deletes an administered object. For procedural information in this guide, see “To Delete an Administered Object” on page 291 .

<code>delete-connector-connection-pool(1)</code>	Removes the connector connection pool specified using the <code>connector_connection_pool_name</code> operand. For procedural information in this guide, see “To Delete a Connector Connection Pool” on page 278 .
<code>delete-connector-resource(1)</code>	Deletes connector resource. For procedural information in this guide, see “To Delete a Connector Resource” on page 280 .
<code>delete-connector-security-map(1)</code>	Deletes a specified connector security map. Supported in remote mode only. For procedural information in this guide, see “To Delete a Connector Security Map” on page 286 .
<code>delete-connector-work-security-map(1)</code>	Deletes a specified connector work security map. Supported in remote mode only. For procedural information in this guide, see “To Delete a Connector Work Security Map” on page 289 .
<code>delete-jdbc-connection-pool(1)</code>	Deletes the specified JDBC connection pool. Supported in remote mode only. For procedural information in this guide, see “To Delete a JDBC Connection Pool” on page 254 .
<code>delete-jdbc-resource(1)</code>	Deletes a JDBC resource. The specified JNDI name identifies the resource to be deleted. Supported in remote mode only. For procedural information in this guide, see “To Delete a JDBC Resource” on page 260 .
<code>delete-resource-adapter-config(1)</code>	Deletes configuration information for the connector module. Supported in remote mode only. For procedural information in this guide, see “To Delete a Resource Adapter Configuration” on page 283 .
<code>flush-connection-pool(1)</code>	Reinitializes all connections established in the specified connection. For procedural information in this guide, see “To Reset (Flush) a Connection Pool” on page 252 .

<code>list-admin-objects(1)</code>	Lists administered objects. For procedural information in this guide, see “To List Administered Objects” on page 290.
<code>list-connector-connection-pools(1)</code>	Lists the connector connection pools that have been created. For procedural information in this guide, see “To List Connector Connection Pools” on page 276.
<code>list-connector-resources(1)</code>	Creates connector resources. For procedural information in this guide, see “To List Connector Resources” on page 279.
<code>list-connector-security-maps(1)</code>	Lists the connector security maps belonging to a specified connector connection pool. For procedural information in this guide, see “To List Connector Security Maps” on page 284.
<code>list-connector-work-security-maps(1)</code>	Lists the existing connector work security maps for a resource adapter. Supported in remote mode only. For procedural information in this guide, see “To List Connector Work Security Maps” on page 288.
<code>list-jdbc-connection-pools(1)</code>	Lists the existing JDBC connection pools. Supported in remote mode only. For procedural information in this guide, see “To List JDBC Connection Pools” on page 251.
<code>list-jdbc-resources(1)</code>	Lists the existing JDBC resources. Supported in remote mode only. For procedural information in this guide, see “To List JDBC Resources” on page 260.
<code>list-resource-adapter-configs(1)</code>	Lists configuration information for the connector modules. Supported in remote mode only. For procedural information in this guide, see “To List Resource Adapter Configurations” on page 282.
<code>ping-connection-pool(1)</code>	Tests if a JDBC connection pool is usable. Supported in remote mode only. For procedural information in this guide, see “To Contact (Ping) a Connection Pool” on page 252.
<code>update-connector-security-map(1)</code>	Modifies a security map for the specified connector connection pool. For procedural

	information in this guide, see “To Update a Connector Security Map” on page 285 .
<code>update-connector-work-security-map(1)</code>	Modifies a work security map that belongs to a specific resource adapter (connector module). For procedure information in this guide, see “To Update a Connector Work Security Map” on page 288 .

Domain Subcommands

<code>create-domain(1)</code>	Creates the configuration of a domain. A domain can exist independent of other domains. Any user who has access to the <code>asadmin</code> utility on a given host can create a domain and store its configuration in a location of choice. For procedural information in this guide, see “To Create a Domain” on page 107 .
<code>delete-domain(1)</code>	Deletes the specified domain. The domain must be stopped before it can be deleted. For procedural information in this guide, see “To Delete a Domain” on page 114 .
<code>list-domains(1)</code>	Lists the existing domains and their statuses. If the domain directory is not specified, the domains in the default <i>as-install</i> /domains directory is displayed. For procedural information in this guide, see “To List Domains” on page 112 .
<code>login(1)</code>	Allows you to log in to a domain. For procedural information in this guide, see “To Log In to a Domain” on page 112 .
<code>restart-domain(1)</code>	Restarts the Domain Administration Server (DAS) of the specified domain. Supported in remote mode only. For procedural information in this guide, see “To Restart a Domain” on page 116 .
<code>start-domain(1)</code>	Starts a domain. If the domain directory is not specified, the default domain1 in the default <i>as-install</i> /domains directory is started. If there are two or more domains, the <i>domain_name</i> operand must be specified. For procedural information in this guide, see “To Start a Domain” on page 115 .
<code>stop-domain(1)</code>	Stops the domain administration server (DAS) of the specified domain. Supported in remote mode only. For procedural information in this guide, see “To Stop a Domain” on page 116 .
<code>uptime(1)</code>	Displays the length of time that the domain administration server (DAS) has been running since the last restart. Supported in remote mode only. For procedural information in this guide, see “To Display

[Domain Uptime](#)” on page 127.

Internet Connectivity Subcommands

<code>create-http(1)</code>	Creates a set of HTTP parameters for a protocol, which in turn configures one or more network listeners. Supported in remote mode only. For procedural information in this guide, see “To Create an HTTP Configuration” on page 298 .
<code>create-http-listener(1)</code>	Creates a new HTTP listener socket. Supported in remote mode only. For procedural information in this guide, see “To Create an Internet Connection” on page 296 .
<code>create-network-listener(1)</code>	Creates a new HTTP listener socket. Supported in remote mode only. For procedural information in this guide, see “To Create an Internet Connection” on page 296 .
<code>create-protocol(1)</code>	Creates a protocol for a listener. Supported in remote mode only. For procedural information in this guide, see “To Create a Protocol” on page 297 .
<code>create-transport(1)</code>	Creates a transport for a listener. Supported in remote mode only. For procedural information in this guide, see “To Create a Transport” on page 300 .
<code>create-virtual-server(1)</code>	Creates the specified virtual server element. Supported in remote mode only. For procedural information in this guide, see “To Create a Virtual Server” on page 306 .
<code>create-ssl(1)</code>	Creates and configures the SSL element in the selected HTTP listener to enable secure communication on that listener/service. Supported in remote mode only. For procedural information in this guide, see “To Configure an HTTP Listener for SSL” on page 304 .
<code>delete-http(1)</code>	Deletes an existing HTTP configuration. Supported in remote mode only. For procedural information in this guide, see “To Delete an HTTP Configuration” on page 299 .
<code>delete-http-listener(1)</code>	Deletes the specified HTTP listener. Supported in remote mode only. For procedural information in this guide, see “To Delete an HTTP Network Listener” on page 303 .
<code>delete-network-listener(1)</code>	Deletes the specified HTTP listener. Supported in remote mode only. For procedural information in this guide, see “To Delete an HTTP Network Listener” on page 303 .

<code>delete-protocol(1)</code>	Deletes an existing HTTP protocol. Supported in remote mode only. For procedural information in this guide, see “To Delete a Protocol” on page 298 .
<code>delete-ssl(1)</code>	Deletes the SSL element in the selected HTTP listener. Supported in remote mode only. For procedural information in this guide, see “To Delete SSL From an HTTP Listener” on page 304 .
<code>delete-transport(1)</code>	Deletes an existing HTTP transport. Supported in remote mode only. For procedural information in this guide, see “To Delete a Transport” on page 301 .
<code>delete-virtual-server(1)</code>	Deletes the specified virtual server element. Supported in remote mode only. For procedural information in this guide, see “To Delete a Virtual Server” on page 307 .
<code>list-http-listeners(1)</code>	Lists the existing HTTP listeners. Supported in remote mode only. For procedural information in this guide, see “To List HTTP Network Listeners” on page 302 .
<code>list-network-listeners(1)</code>	Lists the existing HTTP listeners. Supported in remote mode only. For procedural information in this guide, see “To List HTTP Network Listeners” on page 302 .
<code>list-protocols(1)</code>	Lists the existing HTTP protocols. Supported in remote mode only. For procedural information in this guide, see “To List Protocols” on page 297 .
<code>list-transports(1)</code>	Lists the existing HTTP transports. Supported in remote mode only. For procedural information in this guide, see “To List Transports” on page 300 .
<code>list-virtual-servers(1)</code>	Lists the existing virtual servers. Supported in remote mode only. For procedural information in this guide, see “To List Virtual Servers” on page 307 .

JavaMail Subcommands

<code>create-javamail-resource(1)</code>	Creates a JavaMail session resource. Supported in remote mode only. For procedural information in this guide, see “To Create a JavaMail Resource” on page 316 .
<code>delete-javamail-resource(1)</code>	Deletes a JavaMail session resource. Supported in remote mode only. For procedural information in this guide, see “To Delete a JavaMail Resource” on page 318 .

`list-javamail-resources(1)` Creates JavaMail session resources. Supported in remote mode only. For procedural information in this guide, see [“To List JavaMail Resources” on page 317](#).

JMS Subcommands

`create-jmsdest(1)` Creates a JMS physical destination. Along with the physical destination, you use the `create-jms-resource` subcommand to create a JMS destination resource that has a `Name` property that specifies the physical destination. Supported in remote mode only. For procedural information in this guide, see [“To Create a JMS Physical Destination” on page 332](#).

`create-jms-host(1)` Creates a JMS host within the JMS service. Supported in remote mode only. For procedural information in this guide, see [“To Create a JMS Host” on page 325](#).

`create-jms-resource(1)` Creates a JMS connection factory resource or JMS destination resource. Supported in remote mode only. Supported in remote mode only. For procedural information in this guide, see [“To Create a Connection Factory or Destination Resource” on page 329](#).

`delete-jmsdest(1)` Removes the specified JMS destination. Supported in remote mode only. For procedural information in this guide, see [“To Delete a JMS Physical Destination” on page 334](#).

`delete-jms-host(1)` Deletes a JMS host within the JMS service. Supported in remote mode only. For procedural information in this guide, see [“To Delete a JMS Host” on page 328](#).

`delete-jms-resource(1)` Deletes a JMS connection factory resource or JMS destination resource. Supported in remote mode only. For procedural information in this guide, see [“To Delete a Connection Factory or Destination Resource” on page 331](#).

`flush-jmsdest(1)` Purges the messages from a physical destination in the specified JMS Service configuration of the specified target. Supported in remote mode only. For procedural information in this guide, see [“To Purge Messages From a Physical Destination” on page 334](#).

`jms-ping(1)` Checks if the JMS service (also known as the JMS provider) is up and running. Supported in remote mode only. For procedural information in this guide, see [“Troubleshooting the JMS Service” on page 336](#).

<code>list-jmsdest(1)</code>	Lists the JMS physical destinations. Supported in remote mode only. For procedural information in this guide, see “To List JMS Physical Destinations” on page 333 .
<code>list-jms-hosts(1)</code>	Lists the existing JMS hosts. Supported in remote mode only. For procedural information in this guide, see “To List JMS Hosts” on page 326 .
<code>list-jms-resources(1)</code>	Lists the existing JMS connection factory or destination resources. Supported in remote mode only. For procedural information in this guide, see “To List JMS Resources” on page 331 .

JNDI Subcommands

<code>create-custom-resource(1)</code>	Creates a custom JNDI resource. Supported in remote mode only. For procedural information in this guide, see “To Create a Custom JNDI Resource” on page 370 .
<code>create-jndi-resource(1)</code>	Creates an external JNDI resource. Supported in remote mode only. For procedural information in this guide, see “To Register an External JNDI Resource” on page 372 .
<code>delete-custom-resource(1)</code>	Deletes a custom JNDI resource. Supported in remote mode only. For procedural information in this guide, see “To Delete a Custom JNDI Resource” on page 371 .
<code>delete-jndi-resource(1)</code>	Deletes an external JNDI resource. Supported in remote mode only. For procedural information in this guide, see “To Delete an External JNDI Resource” on page 374 .
<code>list-custom-resources(1)</code>	Lists the existing custom JNDI resources. Supported in remote mode only. For procedural information in this guide, see “To List Custom JNDI Resources” on page 370 .
<code>list-jndi-entries(1)</code>	Lists the entries in the JNDI tree. Supported in remote mode only. For procedural information in this guide, see “To List External JNDI Entries” on page 373 .
<code>list-jndi-resources(1)</code>	Lists the existing external JNDI resources. Supported in remote mode only. For procedural information in this guide, see “To List External JNDI Resources” on page 373 .

JVM Subcommands

<code>create-jvm-options(1)</code>	Creates a JVM option in the Java configuration or profiler elements of the <code>domain.xml</code> file. Supported in remote mode only. For procedural information in this guide, see “To Create JVM Options” on page 132 .
<code>create-profiler(1)</code>	Creates a profiler element. Supported in remote mode only. For procedural information in this guide, see “To Create a Profiler” on page 135 .
<code>delete-jvm-options(1)</code>	Deletes the specified JVM option from the Java configuration or profiler elements of the <code>domain.xml</code> file. Supported in remote mode only. For procedural information in this guide, see “To Delete JVM Options” on page 133 .
<code>delete-profiler(1)</code>	Deletes the specified profiler element. Supported in remote mode only. For procedural information in this guide, see “To Delete a Profiler” on page 136 .
<code>generate-jvm-report(1)</code>	Generates a report showing the threads, classes, and memory for the virtual machine that runs GlassFish Server. For procedural information in this guide, see “To Generate a JVM Report” on page 134 .
<code>list-jvm-options(1)</code>	Lists the command-line options that are passed to the Java application launcher when GlassFish Server is started. Supported in remote mode only. For procedural information in this guide, see “To List JVM Options” on page 132 .

Life Cycle Module Subcommands

<code>create-lifecycle-module(1)</code>	Creates a new life cycle module. Supported in remote mode only. For procedural information in this guide, see “To Create a Life Cycle Module” on page 212 .
<code>list-lifecycle-modules(1)</code>	Lists life cycle modules. Supported in remote mode only. For procedural information in this guide, see “To List Life Cycle Modules” on page 213 .
<code>delete-lifecycle-module(1)</code>	Deletes an existing life cycle module. Supported in remote mode only. For procedural information in this guide, see “To Delete a Life Cycle Module” on page 214 .

Logging and Monitoring Subcommands

<code>collect-log-files(1)</code>	Collects all available log files and creates a ZIP archive. Supported in remote mode only. For procedural information in this guide, see “To Collect Log Files into a ZIP Archive” on page 167 .
<code>disable-monitoring(1)</code>	Disables the monitoring service. Supported in remote mode only. For procedural information in this guide, see “To Disable Monitoring” on page 177 .
<code>enable-monitoring(1)</code>	Enables the monitoring service. Supported in remote mode only. For procedural information in this guide, see “To Enable Monitoring” on page 176 .
<code>list-log-attributes(1)</code>	Lists log file attributes. Supported in remote mode only. For procedural information in this guide, see “Configuring the Logging Service” on page 156 .
<code>list-log-levels(1)</code>	Lists the existing loggers. Supported in remote mode only. For procedural information in this guide, see “To List Log Levels” on page 159 .
<code>monitor(1)</code>	Displays monitoring information for the common GlassFish Server resources. Supported in remote mode only. For procedural information in this guide, see “To View Common Monitoring Data” on page 179 .
<code>rotate-log(1)</code>	Rotates the <code>server.log</code> file and stores the old data in a time-stamped file. Supported in remote mode only. For procedural information in this guide, see “To Rotate Log Files Manually” on page 165 .
<code>set-log-attributes(1)</code>	Sets log file attributes. Supported in remote mode only. For procedural information in this guide, see “Configuring the Logging Service” on page 156 .
<code>set-log-levels(1)</code>	Sets the log level for a module. Supported in remote mode only. For procedural information in this guide, see “Setting Log Levels” on page 159 .

ORB Subcommands

<code>create-iiop-listener(1)</code>	Creates an IIOP listener. Supported in remote mode only. For procedural information in this guide, see “To Create an IIOP Listener” on page 312 .
<code>delete-iiop-listener(1)</code>	Deletes an IIOP listener. Supported in remote mode only. For procedural information in this guide, see “To Delete an IIOP Listener” on page 314 .
<code>list-iiop-listeners(1)</code>	Lists the existing IIOP listeners. Supported in remote mode only. For procedural information in this guide, see “To List IIOP Listeners” on page 313 .

Thread Pool Subcommands

<code>create-threadpool(1)</code>	Creates a new thread pool. Supported in remote mode only. For procedural information in this guide, see “To Create a Thread Pool” on page 138 .
<code>delete-threadpool(1)</code>	Deletes the specified thread pool. Supported in remote mode only. For procedural information in this guide, see “To Delete a Thread Pool” on page 140 .
<code>list-threadpools(1)</code>	Lists the existing thread pools. Supported in remote mode only. For procedural information in this guide, see “To List Thread Pools” on page 139 .

Transaction Service Subcommands

<code>freeze-transaction-service(1)</code>	Freezes the transaction subsystem during which time all the in-flight transactions are suspended. Supported in remote mode only. For procedural information, see “To Stop the Transaction Service” on page 382 .
<code>recover-transactions(1)</code>	Manually recovers pending transactions. Supported in remote mode only. For procedural information, see “To Manually Recover Transactions” on page 385 .
<code>rollback-transaction(1)</code>	Rolls back the named transaction. Supported in remote mode only. For procedural information, see “To Roll Back a Transaction” on page 382 .

`unfreeze-transaction-service(1)` Resumes all the suspended in-flight transactions. Invoke this subcommand on an already frozen transaction. Supported in remote mode only. For procedural information, see [“To Restart the Transaction Service” on page 383](#).

Index

A

accessing a database, 246–249

add-on components

about monitoring, 175

installing, 221

overview, 215

repositories, 216–219

reverting to prior version, 227–230

updating, 224–225

updating an image, 226

add-resources command, 62

adding

a logging handler, 166–167

new components, 221

resources, 62

additional information, Update Tool, 220

Admin Console

Edit Connection Pool Advanced Attributes page

SQL Trace Listeners field, 257

Statement Cache Size field, 257

Statement Timeout field, 256

Edit Connection Pool page

Init SQL field, 255

Transaction Log Location field, 388

Transaction Service page, 380

administered objects

creating, 290

deleting, 291–292

editing, 291

listing, 290–291

Administration Console

extending GlassFish Server, 220–221

Administration Console (*Continued*)

overview, 42

starting, 42

updating GlassFish Server, 220–221

anonymous login, 33

Apache Felix Gogo remote shell, 44–49

Apache Felix Web Console, 44–49

Apache HTTP Server, 144

applications

listing, 63

monitoring statistics, 185

asadmin command

create-jdbc-connection-pool

--initsql option, 255

--sqltracelisteners option, 257

--statementcachesize option, 257

--statementtimeout option, 256

create-jvm-options

com.sun.appserv.transaction.nofdsync
option, 389

get, 381

set

init-sql option, 255

sql-trace-listeners option, 257

statement-cache-size option, 257

transaction service settings, 380

asadmin utility

command syntax, 54–55

commands listing, 393–407

help information, 56–57

listing commands, 66

man pages, 56–57

asadmin utility (*Continued*)

- operands, 55
- options, 54–55
- overview, 43, 53–60
- path settings, 54
- scripts, 59–60
- single mode, 55–56
- subcommand options, 54–55
- subcommands, 54

B

- backing up, domain, 122
- backup-domain command, 122
- bean-cache, monitoring statistics, 185

C

- cache, (EJB) monitoring statistics, 185
- certificates, creating for mod_jk, 148
- class loading monitoring statistics for JVM, 192
- cluster, log, 152–154
- command-line utility, overview, 43
- commands, for asadmin utility, 393–407
- compilation monitoring statistics for JVM, 194
- component status, showing, 67
- configuration
 - overview, 34–42
 - REST methods, 71–80
 - REST URLs, 68–69
- configuration (HTTP), creating, 298–299
- configuration objects, REST resources, 82–92
- configuring
 - database access, 249–262
 - generic resource adapter, 337–338
 - HTTP listeners for SSL, 304
 - IIOP listeners, 312–314
 - JDBC resources, 258–261
 - JVM, 131–136
 - life cycle modules, 212–214
 - logging service, 156–167
 - monitoring, 176–178
 - the ORB, 312

configuring (*Continued*)

- using dotted names, 37–38
- connection factory
 - creating, 329–330
 - deleting, 331–332, 334–335
 - updating, 329–330
- connection manager, ORB monitoring statistics, 199
- connection pools
 - monitoring statistics, 190
 - overview, 250–258
 - pinging, 252
 - resetting, 252–253
- connection pools (JDBC)
 - configuring, 249–262
 - deleting, 254
 - editing, 253
 - listing, 251–252
- connectivity, setting up for databases, 245–272
- connector connection pool
 - connecting to (ping), 277
 - resetting (flush), 277
- connector connection pools
 - administering, 275–278
 - creating, 275–276
 - deleting, 278
 - editing, 277
 - listing, 276–277
 - pinging, 276
- connector resources
 - administering, 278–281
 - creating, 278–279
 - deleting, 280–281
 - editing, 280
 - listing, 279–280
- connector security maps
 - administering, 283–286
 - creating, 284
 - deleting, 286
 - listing, 284–285
 - updating, 285–286
- connector work security map, updating, 288–289
- connector work security maps
 - administering, 286–289
 - creating, 287–288

- connector work security maps (*Continued*)
 - deleting, 289
 - listing, 288
- connectors, and transactions, 379
- contacting connection pools (ping), 252
- container monitoring statistics for web, 206
- containers, listing, 64
- content-type header, 104
- context root, 142
- contrib.glassfish.oracle.com publisher, 216, 219
- contrib.glassfish.org publisher, 216
- CORBA, 311
- create-admin-object command, 290
- create-connector-security-map command, 284
- create-connector-work-security-map
 - command, 287–288
- create-connector-connection-pool
 - command, 275–276
- create-custom-resource command, 370
- create-domain subcommand, 107
- create-http-listener command, 301–302
 - for mod_jk, 145
- create-http subcommand, 298–299
- create-iiop-listener command, 312–313
- create-javamail-resource command, 316–317
- create-jdbc-connection-pool command, 250–251
 - initsql option, 255
 - sqltracelisteners option, 257
 - statementcachesize option, 257
 - statementtimeout option, 256
- create-jdbc-resource subcommand, 259
- create-jms-host command, 325–326
- create-jms-resource command, 329–330
- create-jmsdest command, 332–333
- create-jndi-resource command, 372
- create-jvm-options command, 132
 - com.sun.appserv.transaction.nofdsync option, 389
- create-lifecycle-module subcommand, 212–213
- create-network-listener command, 296, 301–302
- create-profiler command, 135
- create-protocol subcommand, 297
- create-resource-adapter-config command, 281–282
- create-service command, 118–119, 119–120, 120
- create-ssl command, 304
- create-system-properties command, 60
- create-threadpool command, 138–139
- create-transport subcommand, 300
- create-virtual-server command, 306–307
- create-connector-resource command, 278–279
- creating
 - administered objects, 290
 - connector connection pool, 275–276
 - connector resource, 278–279
 - connector security map, 284
 - connector work security map, 287–288
 - custom resource, 370
 - domain, 107
 - external JNDI resource, 372
 - HTTP configuration, 298–299
 - HTTP listeners, 301–302
 - HTTP protocol, 297
 - HTTP transport, 300
 - IIOP listeners, 312–313
 - internet connection, 296
 - JavaMail resource, 316–317
 - JDBC connection pools, 250–251
 - JDBC resource, 259
 - JMS hosts, 325–326
 - JMS physical destination, 332–333
 - JMS resource, 329–330
 - JVM options, 132
 - life cycle modules, 212–213
 - profilers, 135
 - resource-adapter-config, 281–282
 - system properties, 60
 - threadpools, 138–139
 - virtual servers, 306–307
- cURL, 67
- custom resources
 - creating, 370
 - deleting, 371
 - listing, 370–371
 - updating, 371
- customizing, domains, 108–112

D**DAS**

- displaying uptime, 127
- overview, 107

databases

- administering connectivity, 245–272
- as transaction resource managers, 379
- detecting, 262
- JNDI names, 368
- resource references, 369
- setting up access, 246–249
- starting, 247–248
- stopping, 248
- supported, 262, 263–272

default listener ports, 295**default login, 106****default login identity, 33, 107, 112–114****default virtual server, 305****default web module, 141, 308****default-web.xml file, 142–143****defaults, server, 106****delete-admin-object command, 291–292****delete-connector-connection-pool command, 278****delete-connector-resource command, 280–281****delete-connector-security-map command, 286****delete-connector-work-security-map command, 289****delete-custom-resource command, 371****delete-domain command, 114****delete-http command, 299****delete-http-listener command, 303–304****delete-iiop-listener command, 314****delete-javamail-resource command, 318****delete-jdbc-connection-pool command, 254****delete-jdbc-resource command, 260–261****delete-jms-host command, 328****delete-jms-resource command, 331–332****delete-jmsdest command, 334–335****delete-jndi-resource command, 374****delete-jvm-options command, 133–134****delete-lifecycle-module subcommand, 214****delete-network-listener command, 303–304****delete-profiler command, 136****delete-protocol command, 298****delete-resource-adapter-config command, 283****delete-ssl command, 304–305****delete-system-property command, 61****delete-threadpool command, 140****delete-transport command, 301****delete-virtual-server command, 307–308****deleting****administered object, 291–292****connector connection pool, 278****connector resource, 280–281****connector security map, 286****connector work security map, 289****custom resource, 371****domain, 114****external JNDI resource, 374****HTTP configuration, 299****HTTP listeners, 303–304****HTTP protocol, 298****IIOP listeners, 314****JavaMail resource, 318****JDBC connection pools, 254****JDBC resources, 260–261****JMS hosts, 328****JMS physical destination, 334–335****JMS resource, 331–332****JVM options, 133–134****life cycle modules, 214****profilers, 136****resource adapter configuration, 283****SSL from HTTP listeners, 304–305****system properties, 61****threadpools, 140****transport, 301****virtual servers, 307–308****deployment, REST interfaces, 80–81****Derby JDBC driver, 264–265****destination (physical), deleting, 334–335****destination resource****creating, 329–330****deleting, 331–332****updating, 329–330****dev.glassfish.oracle.com publisher, 216****dev.glassfish.org publisher, 219****directory listings, disabling, 142****disable-monitoring subcommand, 177–178**

- disabling, monitoring, 177–178
- displaying
 - domain uptime, 127
 - version information, 63
- document root, 308
- domains
 - administering, 105–130
 - backing up, 122
 - changing administration port, 128–130
 - creating, 107
 - customizing, 108–112
 - deleting, 114
 - displaying uptime, 127
 - listing, 112
 - overview, 106
 - restarting, 116
 - restarting automatically, 118–119, 119–120, 120
 - restoring, 123
 - starting, 115
 - stopping, 116
 - switching to another Java version, 127
 - templates, 108–112
- dotted names
 - comparison with REST URLs, 69
 - for configuration, 37–38
 - for monitoring, 170, 181–182, 182–184
- dynamic configuration changes, 41

E

- editing
 - administered object, 291
 - connector connection pool, 277
 - connector resource, 280
 - JDBC connection pools, 253
 - resource adapter configuration, 282
- EJB
 - cache monitoring statistics, 185
 - container monitoring statistics, 186
 - method monitoring statistics, 187
 - pool monitoring statistics, 187, 188
- enable-monitoring subcommand, 176–177
- enabling
 - mod_jk, 144

- enabling (*Continued*)
 - monitoring, 176–177
- ending, multimode session, 58–59
- extending GlassFish Server, 215–241
- external JNDI resource
 - creating, 372
 - deleting, 374
 - updating, 374
- external JNDI resources, listing, 373
- external repositories, accessing, 372

F

- Felix Gogo remote shell, 44–49
- flush-connection-pool command, 252–253
- flush-jmsdest command, 334
- flushing (purging) messages from JMS physical destination, 334
- formats
 - REST resources
 - configuration objects, 82–92
 - content types, 104
 - log files, 100–103
 - monitoring objects, 92–99
- freeze-transaction-service subcommand, 382

G

- garbage collectors monitoring statistics for JVM, 194
- generate-jvm-report command, 134
- generating, JVM report, 134
- generic resource adapter, configuring, 337–338
- get command, 177–178, 182–184, 381
 - guidelines, 181–182
- get subcommand, 176–177
- glassfish-jk.properties file, 145
- GlassFish Server
 - extending, 215–241
 - updating, 215–241
- GlassFish Server Open Source Edition
 - repositories, 219
 - upgrading from, 230–234
- global log levels, setting, 160–161

Gogo remote shell, 44–49

H

headless systems, updating, 220

help information, asadmin utility, 56–57

HK2 component, 166

HTML format

- REST resources

- configuration objects, 92

- monitoring objects, 99

HTTP configuration

- creating, 298–299

- deleting, 299

HTTP listeners

- administering, 295–305

- common monitoring statistics, 180

- configuring for SSL, 304

- creating, 301–302

- deleting, 303–304

- deleting SSL from, 304–305

- for mod_jk, 145

- listing, 302–303

- overview, 294

- ports, 295

- updating, 303

HTTP protocol, creating, 297

HTTP protocols, listing, 297–298

HTTP service

- administering, 293–309

- monitoring statistics, 188

- virtual server statistics, 188

HTTP transport, creating, 300

HTTP transports, listing, 300

httpd.conf file, 145

I

IBM DB2 JDBC driver, 263–264, 267–268

IIOP listeners

- configuring, 312–314

- creating, 312–313

- deleting, 314

IIOP listeners (*Continued*)

- listing, 313

- updating, 313

image, updating all installed components, 226

Inet MSSQL JDBC driver, 271

Inet Oracle JDBC driver, 270–271

Inet Sybase JDBC driver, 271–272

Informix Type 4 JDBC driver, 268

installed components

- uninstalling, 227–228

- updating, 224–225

installing

- add-on components, 221

- database and driver, 247

instances

- overview, 105–106

- restarting automatically, 118–119, 119–120, 120

internet connection, creating, 296

J

Java, switching version for a domain, 127

Java DB, utility scripts, 248–249

Java DB driver, 264–265

Java Message Service, *See* JMS

JavaMail, 315–318

- creating a resource, 316–317

- deleting a resource, 318

- listing resources, 317

- overview, 315

- updating a resource, 317–318

JavaScript Object Notation, *See* JSON

JConsole, setting up connectivity, 208–209

JDBC

- configuring, 245–272

- configuring resources, 258–261

- creating a resource, 259

- creating connection pool, 250–251

- database setup, 246–249

- deleting connection pools, 254

- deleting resources, 260–261

- detecting drivers, 262

- flushing connection pools, 252–253

- integrating driver JAR files, 262

JDBC (Continued)

- listing connection pools, 251–252
- listing resources, 260
- pinging connection pools, 252
- supported drivers, 262, 263–272
- updating resources, 260

JDBC connection pools

- creating, 250–251
- deleting, 254
- flushing, 252–253
- listing, 251–252
- monitoring statistics, 200
- pinging, 252

Jersey

- monitoring statistics, 190

JMS

- and transactions, 379
- configuring, 321–323
- creating a host, 325–326
- creating a physical destination, 332–333
- creating a resource, 329–330
- deleting a host, 328
- deleting a physical destination, 334–335
- deleting a resource, 331–332
- high availability, 321
- listing hosts, 326–327
- listing physical destinations, 333–334
- listing resources, 331
- monitoring statistics, 190–192
 - connector connection pool, 190
- overview, 320–321, 328–332
- purging (flushing) messages, 334
- resource adapter, generic, 337–338
- system connector for, 320–321
- troubleshooting, 336
- updating a host, 327–328
- updating a physical destination properties, 332–333
- updating a resource, 329–330
- work management monitoring statistics, 192

jmsra system JMS connector, 320–321**JNDI**

- creating a custom resource, 370
- creating an external resource, 372
- deleting a custom resource, 371

JNDI (Continued)

- deleting an external resource, 374
- external repositories, 372
- listing custom resources, 370–371
- listing entries, 373
- listing external JNDI resources, 373
- lookups and associated references, 369
- overview, 367–369
- updating a custom resource, 371
- updating an external resource, 374
- vendor-specific names, 375

JNDI resource, registering, 372**JSON format****REST resources**

- configuration objects, 83–86
- log file details, 100–102
- monitoring objects, 92–95

JSP monitoring statistics for web, 206**JVM**

- configuring, 131–136
- creating options, 132
- deleting options, 133–134
- generating a report, 134
- listing options, 132–133
- monitoring statistics, 180, 192
 - class loading system statistics, 192
 - compilation system statistics, 194
 - garbage collectors statistics, 194
 - memory statistics, 194
 - operating system statistics, 195
 - runtime statistics, 196
- tuning, 131–134

L**last agent optimization, 379****levels**

- listing for logging, 159–160
- setting for logging, 161–162

life cycle modules

- configuring, 212–214
- creating, 212–213
- deleting, 214
- listing, 213

life cycle modules (*Continued*)

updating, 213–214

Linux, restarting domain or instance

automatically, 119–120

list-admin-objects command, 290–291

list-applications command, 63

list-backups subcommand, 124–125

list command, 182–184

guidelines, 181–182

list-commands subcommand, 66

list-connector-security-map command, 284–285

list-connector-connection-pools command, 276–277

list-connector-resources command, 279–280

list-connector-work-security-maps command, 288

list-containers command, 64

list-custom-resources command, 370–371

list-domains subcommand, 112

list-http-listeners subcommand, 302–303

list-iiop-listeners command, 313

list-javamail-resources command, 317

list-jdbc-connection-pools command, 251–252

list-jdbc-resources command, 260

list-jms-hosts command, 326–327

list-jms-resources command, 331

list-jndi-entries command, 373

list-jndi-resources command, 373

list-jvm-options command, 132–133

list-lifecycle-modules subcommand, 213

list-log-attributes subcommand, 156–167

list-log-levels subcommand, 159–160, 161–162

list-modules command, 65

list-network-listeners subcommand, 302–303

list-protocols subcommand, 297–298

list-resource-adapter-configs command, 282

list-system-properties command, 61

list-threadpools command, 139

list-timers command, 66–67

list-transport subcommand, 300

list-virtual-servers command, 307

list-jmsdest command, 333–334

listener ports, 295

listing

administered objects, 290–291

applications, 63

listing (*Continued*)

component status, 67

connector connection pools, 276–277

connector resources, 279–280

connector security maps, 284–285

connector work security maps, 288

containers, 64

custom resources, 370–371

domain, 112

external JNDI resources, 373

HTTP listeners, 302–303

HTTP protocols, 297–298

HTTP transports, 300

IIOP listeners, 313

JavaMail resources, 317

JDBC connection pools, 251–252

JDBC resources, 260

JMS hosts, 326–327

JMS physical destinations, 333–334

JMS resources, 331

JNDI entries, 373

JVM options, 132–133

life cycle modules, 213

module log levels, 159–160

modules, 65

remote commands, 66

resource adapter configurations, 282

system properties, 61

threadpools, 139

timers, 66–67

version information, 63

virtual servers, 307

load balancing

enabling security for mod_jk, 148, 149

load balancing with mod_jk, 146

local subcommands, 54

log file, REST URLs, 70–71

log files

about, 152–154

changing name or location, 156–158

cluster, 152–154

locations, 152–153

REST resources, 100–103

rotation, 154

- log files (*Continued*)
 - server, 152–154
 - setting rotation, 162–166
- log in using default identity, 33, 107
- log in with default identity, 112–114
- log levels
 - global settings, 160–161
 - setting, 159–162
- log record format, 153
- log targets, 155
- logging
 - administering, 151–168
 - configuration file, 160
 - log level listing, 159–160
 - log level setting, 161–162
 - namespaces, 154
 - output from servlets, 142
 - overview, 151–156
 - rotating logs, 165
- logging in to a domain (server), 112–114
- logging properties, 155–156
- logging.properties file, 160
- logging service, configuring, 156–167
- login command, 112–114

M

- man pages, asadmin utility, 56–57
- memory monitoring statistics for JVM, 194
- Message Queue, connector for, 320–321
- messages, purging (flushing) from physical destination, 334
- method (EJB) monitoring, EJB method, 187
- methods, REST interfaces, 71–80
- mime-mapping element, 143
- mod_jk, 144–149
 - enabling, 144
 - Implementing security, 148
 - load balancing, 146
 - load balancing with SSL, 149
- modules, listing, 65
- monitor command, 179
- monitoring, 169–209
 - administrator tasks, 176

- monitoring (*Continued*)
 - applications statistics, 185
 - bean-cache attributes, 185
 - common statistics, 180–181
 - configuring, 176–178
 - disabling, 177–178
 - EJB container, 186
 - EJB pool, 187, 188
 - enabling, 176–177
 - for add-on components, 175
 - HTTP service statistics, 188
 - HTTP service virtual server statistics, 188
 - Jersey statistics, 190
 - JMS connector connection pool statistics, 190
 - JMS statistics, 190–192
 - JVM statistics, 192
 - network statistics, 196
 - ORB service statistics, 199
 - overview, 169–176
 - resource statistics, 200
 - REST methods, 71–80
 - REST URLs, 68–69
 - security statistics, 202
 - statistics
 - JVM, 180
 - Web module, 180–181
 - thread pool statistics, 203
 - timer statistics, 188
 - transaction service statistics, 205
 - viewing common data, 179
 - viewing comprehensive data, 182–184
 - web statistics, 205
- monitoring objects, REST resources, 92–99
- MSSQL Inet JDBC driver, 271
- MSSQL/SQL Server2000 Data Direct JDBC driver, 268–269
- multimode
 - ending session, 58–59
 - overview, 57–58
 - starting session, 57–58
- multimode command, 57–58
- MySQL Server2000 Data Direct JDBC driver, 269
- MySQL Type 4 JDBC driver, 265

N

- namespaces (logging), 154
- naming, JNDI and resource reference, 369
- network, monitoring statistics, 196
- network listeners
 - See HTTP listeners
- overview, 294
- network service, administering, 293–309
- non-CRUD operations, REST interfaces, 80–81

O

- Object Request Broker (ORB), 311
- offline updates, pkg command, 234–241
- online help
 - asadmin utility, 56–57
 - overview, 43
 - Update Tool, 44
- operands, asadmin utility subcommands, 55
- operating system monitoring statistics for JVM, 195
- options
 - asadmin utility, 54–55
 - specifying for multiple subcommands, 57–58
- Oracle Data Direct JDBC driver, 269–270
- Oracle GlassFish Server
 - repositories, 216–219
 - upgrading to, 230–234
- Oracle Inet JDBC driver, 270–271
- Oracle OCI JDBC driver, 265–266
- Oracle Solaris, restarting domain or instance
 - automatically, 120
- Oracle Thin Type 4 Driver, workaround for, 387
- Oracle Thin Type 4 JDBC driver, 266–267
 - workaround for, 267
- oracle-xa-recovery-workaround property, 267, 387
- ORB
 - configuring, 312
 - IIOP listeners, 312–314
 - overview, 311
 - service, monitoring, 199
- OSGi module management subsystem, 44–49
- OSGi modules, *See* add-on components
- overview
 - Administration Console, 42

- overview (*Continued*)

- Apache Felix Gogo remote shell, 44–49
- asadmin utility, 43, 53–60
- configuration, 34–42
- DAS, 107
- domains, 106
- extending GlassFish Server, 215
- Felix Gogo remote shell, 44–49
- GlassFish Server tools, 42–49
- HTTP listeners, 294
- instances, 105–106
- JavaMail, 315
- JConsole, 49
- JMS, 320–321
- JMS resources, 328–332
- JNDI, 367–369
- keytool utility, 49
- logging, 151–156
- monitoring, 169–176
- multimode, 57–58
- network listeners, 294
- ORB, 311
- OSGi module management subsystem, 44–49
- thread pools, 137
- transactions, 377–380
- Update Tool, 44
- virtual servers, 294

P

- path settings, asadmin utility, 54
- paths, pkg command, 220
- physical destination (JMS), creating, 332–333
- ping-connection-pool command, 252, 276
- pkg command, 220
- pkg command, 44, 221
 - offline updates, 234–241
 - repositories, 234–241
- pkg.depotd, 234–241
- plug-ins, *See* add-on components
- ports
 - changing for domain, 128–130
 - defaults for listeners, 295
- PostgreSQL JDBC driver, 267

preferred publisher, 216
 profilers
 administering, 135–136
 creating, 135
 deleting, 136
 elements in domain.xml, 132
 properties, administering for system, 60–62
 protocol
 creating, 297
 deleting, 298
 protocols, listing, 297–298

Q

queries, REST interfaces, 80–81

R

recover-transactions subcommand, 385–386
 recovering
 transactions automatically, 384–385
 transactions manually, 385–386
 redirecting a URL, 143–144
 registering, JNDI resource, 372
 release.glassfish.oracle.com publisher, 216
 release.javaeejdk.oracle.com publisher, 219
 remote commands, listing, 66
 remote shell, Apache Felix Gogo, 44–49
 remote subcommands, 54
 repositories
 IPS, 216–219
 pkg command, 234–241
 representational state transfer interfaces, *See* REST interfaces
 request monitoring statistics for web, 207
 resetting connection pools (flush), 252–253
 resource adapter, generic, JMS, 337–338
 resource adapter configuration,
 administering, 281–283
 resource adapter configurations
 creating, 281–282
 deleting, 283
 editing, 282
 resource adapter configurations (*Continued*)
 listing, 282
 resource managers, 379
 resource references, 369
 resources
 adding, 62
 custom, 370
 resources (JDBC), administering, 258–261
 REST interfaces, 43
 comparison of dotted names with URLs, 69
 configuration, 68–69, 71–80
 content types, 104
 HTML representation
 configuration objects, 92
 monitoring objects, 99
 JSON representation
 configuration objects, 83–86
 log file details, 100–102
 monitoring objects, 92–95
 log file, 70–71
 methods, 71–80
 monitoring, 68–69, 71–80
 non-CRUD operations, 80–81
 representation of resources
 configuration objects, 82–92
 log files, 100–103
 monitoring objects, 92–99
 security, 81–82
 URLs, 68–71
 XML representation
 configuration objects, 86–91
 log file details, 102–103
 monitoring objects, 95–98
 restart domain (server), 115, 116
 restart-domain command, 116
 restarting domain (server) automatically, 118–119,
 119–120, 120
 restarting instance automatically, 118–119, 119–120,
 120
 restore-domain command, 123
 restoring, domain, 123
 reverting, to a prior add-on component, 227–230
 rollback-transaction subcommand, 382–383
 rolling back, transactions, 382–383

- rotate-log subcommand, 165
- rotating log files, 154
- runtime monitoring statistics for JVM, 196

S

scripts

- asadmin utility, 59–60
- for Java DB, 248–249
- subcommands, 59–60

security

- disabling directory listings, 142
- monitoring statistics, 202
- REST interfaces, 81–82

- self-signed certificate, 148

- server, log, 152–154

- ServletContext.log messages, 142

servlets

- changing log output, 142
- invoking using a URL, 141
- specification
 - mime-mapping, 143

- session monitoring statistics for web, 208

set command

- for updating a thread pool, 139–140
- init-sql option, 255
- sql-trace-listeners option, 257
- statement-cache-size option, 257
- transaction service settings, 380
- updating a connection factory, 329–330
- updating a custom JNDI resource, 371
- updating a JavaMail resource, 317–318
- updating a JMS host, 327–328
- updating an external JNDI resource, 374

- set-log-attributes subcommand, 156–167

- set-log-levels subcommand, 159–162

- set subcommand, 177–178

settings

- global log levels, 160–161
- JConsole, 208–209
- module log level, 161–162
- monitoring, 176–178

- show-component-status command, 67

- showing, component status, 67

- single mode, asadmin utility, 55–56

SSL

- applying to mod_jk, 148
- configuring for HTTP listener, 304
- deleting from HTTP listener, 304–305

- stable.glassfish.org publisher, 219

- start-database command, 247–248

- start-domain command, 115

starting

- Administration Console, 42
- databases, 247–248
- domains, 115
- multimode session, 57–58
- the transaction service, 383
- Update Tool, 220
- Windows default domain, 115

- state management, REST interfaces, 80–81

statistics

- applications monitoring, 185
- EJB, 187
- for common monitoring, 180–181
- for comprehensive monitoring, 184–208
- HTTP monitoring, 188–190
- Jersey, 190
- JMS, 190
- JVM class loading system monitoring, 192
- JVM compilation system monitoring, 194
- JVM garbage collectors monitoring, 194
- JVM memory monitoring, 194
- JVM operating system monitoring, 195
- JVM runtime monitoring, 196
- network monitoring, 196
- ORB monitoring, 199–200
- resource (connection pool) monitoring, 200
- security monitoring, 202
- thread pool monitoring, 203
- timers monitoring, 188
- transactions monitoring, 205
- web monitoring, 205

- stop-database command, 248

- stop-domain command, 116

stopping

- databases, 248
- domains, 116

stopping (*Continued*)

- multimode session, 58–59
- the transaction service, 382
- Windows default domain, 116

subcommands

- definition, 54
- help information, 56–57
- man pages, 56–57
- operands, 55
- options, 54–55
- scripts, 59–60

Sybase Data Direct JDBC driver, 270

Sybase Inet JDBC driver, 271–272

Sybase JConnect Type 4 JDBC driver, 272

system properties

- administering, 60–62
- creating, 60
- deleting, 61
- listing, 61

T

tasks for administration, monitoring, 176

Telnet service, 44–49

templates, domains, 108–112

thread pools, 137–140

- monitoring statistics, 203
- overview, 137

threadpools

- creating, 138–139
- deleting, 140
- listing, 139
- updating, 139–140

timers

- listing, 66–67
- statistics, 188

Tomcat

Apache Connector mod_jk, 144, 146

tools

- for administering GlassFish Server, 42–49
- overview, 42–49

transaction service, monitoring, 205

transactions, 377–389

- configuring, 380–381

transactions (*Continued*)

- JMS and Message Queue, 385
- local or global scope of, 379–380
- logging for recovery, 388–389
- logging to a database, 388–389
- manual recovery limitation, 386
- overview, 377–380
- recovering, 384–387
- recovering automatically, 384–385
- recovering manually, 385–386
- recovery limitations, 386–387
- resource managers, 379
- rolling back, 382–383
- starting (unfreezing) the service, 383
- stopping (freezing) the service, 382

transport

- creating, 300
- deleting, 301

transports, listing, 300

tree structure for monitoring, 170–175

troubleshooting, JMS, 336

tuning the JVM, 131–134

U

unfreeze-transaction-service subcommand, 383

uninstalling, installed components, 227–228

update-connector-security-map command, 285–286

update-connector-work-security-map
command, 288–289

update-http-listener subcommand, 303

update-iiop-listener command, 313

update-javamail-resource command, 317–318

update-jdbc-resource command, 260

update-network-listener subcommand, 303

Update Tool, 220

- offline updates, 234–241

overview, 44

- using the pkg command, 215, 234–241

update-virtual-server command, 307

updatetool command, 44

updating

- all installed components in an image, 226
- connection factory, 329–330

updating (*Continued*)

- connector security map, 285–286
 - connector work security map, 288–289
 - custom resource, 371
 - external JNDI resource, 374
 - HTTP listeners, 303
 - IIOP listeners, 313
 - installed components, 224–225
 - JavaMail resource, 317–318
 - JDBC resources, 260
 - JMS host, 327–328
 - JMS physical destination properties, 332–333
 - life cycle modules, 213–214
 - threadpools, 139–140
 - virtual servers, 307
- updatingGlassFish Server, 215–241
- uptime command, 127
- URL, redirecting, 143–144
- URLs, REST interfaces, 68–71

V

- vendor-specific, JNDI names, 375
- version command, 63
- viewing
- applications, 63
 - common monitoring data, 179
 - comprehensive monitoring data, 182–184
 - containers, 64
 - DAS uptime, 127
 - GlassFish Server version, 63
 - JDBC connection pools, 251–252
 - JDBC resources, 260
 - JVM options, 132–133
 - modules, 65
 - subcommands, 66
 - system properties, 61
 - virtual servers, 307

virtual servers

- administering, 305–309
- creating, 306–307
- default, 305
- deleting, 307–308
- listing, 307

virtual servers (*Continued*)

- monitoring statistics, 188
- overview, 294
- updating, 307

W

web

- monitoring statistics, 205
- JSP statistics, 206
- request statistics, 207
- session statistics, 208

web applications

- default, 141, 308
- defining global features, 142–143
- mod_jk, 144
- redirecting a URL, 143–144
- ways to invoke a servlet, 141

web container, monitoring statistics, 206

web module, monitoring statistics, 180–181

Wget, 67

Windows

- invoking the Administration Console, 42
- restarting domain or instance
 - automatically, 118–119
 - starting the default domain, 115
 - stopping the default domain, 116
- work management, monitoring, 192
- work security maps, 286–289
- workers.properties file, 145

X

XA resource, 379–380

XML format

- REST resources
 - configuration objects, 86–91
 - log file details, 102–103
 - monitoring objects, 95–98